aws

ONTAP User Guide

FSx for ONTAP

Copyright © 2026 Amazon Web Services, Inc. and/or its affiliates. All rights reserved.

FSx for ONTAP: ONTAP User Guide

Copyright © 2026 Amazon Web Services, Inc. and/or its affiliates. All rights reserved.

Amazon's trademarks and trade dress may not be used in connection with any product or service that is not Amazon's, in any manner that is likely to cause confusion among customers, or in any manner that disparages or discredits Amazon. All other trademarks not owned by Amazon are the property of their respective owners, who may or may not be affiliated with, connected to, or sponsored by Amazon.

Table of Contents

What is Amazon FSx for NetApp ONTAP? 1
Features of FSx for ONTAP 2
Security and data protection 3
Monitoring tools 3
Pricing for FSx for ONTAP 3
FSx for ONTAP on AWS re:Post 4
Are you a first-time Amazon FSx user? 4
How it works 5
File systems 5
Storage virtual machines 5
Volumes 6
Storage tiers 6
Data tiering 7
Storage efficiency 7
Accessing your data 7
Managing FSx for ONTAP resources 7
Getting started 9
Setting up 9
Sign up for an AWS account 9
Next step 9
Create your FSx for ONTAP file system 10
Create Microsoft Active Directory-joined SVM 13
Mounting your file system 14
Cleaning up resources 15
AWS Regions 17
Accessing your data 21
Supported clients 22
Using block storage protocols 23
Accessing data from within the AWS Cloud 23
Accessing data from the same VPC 24
Accessing data from a different VPC 24
Accessing data from on-premises 28
Accessing NFS, SMB, ONTAP CLI and API from on-premises 28
Accessing inter-cluster endpoints from on-premises 30

Configure routing to access Multi-AZ file systems from outside your VPC 30
Configure routing to access Multi-AZ file systems from on-premises 32
Mounting on Linux clients 33
Using /etc/fstab to mount automatically on instance reboot 34
Mounting on Windows clients 36
Prerequisites 36
Mounting on macOS clients 37
Provisioning iSCSI for Linux 40
Before you begin 40
Install and configure iSCSI on the Linux host 42
Configure iSCSI on the FSx for ONTAP file system 43
Mount an iSCSI LUN on your Linux client 46
Provisioning iSCSI for Windows 52
Configure iSCSI on the Windows client 53
Configure iSCSI on the FSx for ONTAP file system 54
Mount an iSCSI LUN on the Windows client 56
Validating your iSCSI configuration 59
Verify Host Utilities registry settings 60
Provisioning NVMe/TCP for Linux 61
Before you begin 61
Install and configure NVMe on the Linux host 62
Configure NVMe on the FSx for ONTAP file system 63
Mount an NVMe device on your Linux client 66
Accessing data via S3 access points 71
AWS Regions with Amazon S3 access points for FSx for ONTAP 72
Naming rules, restrictions, and limitations 73
Referencing access points 74
Access point compatibility 76
Managing access 80
Creating an access point 83
Configuring network access 90
Managing access points 104
Using access points 108
Using with AWS services 111
Troubleshooting access points 170
Accessing data from other AWS services 173

Using Amazon WorkSpaces ... 173
Using Amazon ECS ... 179
Using Amazon EVS ... 182
Using VMware Cloud ... 183
Availability, durability, and deployment options ... 184
Choosing a file system deployment type ... 184
Single-AZ deployment types ... 184
Multi-AZ deployment types ... 185
Choosing a file system generation ... 186
Failover process for FSx for ONTAP ... 188
Testing failover on a file system ... 188
Network resources ... 189
Subnets ... 189
File system elastic network interfaces ... 189
Performance ... 192
Measuring performance ... 192
Latency ... 192
Throughput and IOPS ... 192
SMB Multichannel and NFS nconnect support ... 193
Performance details ... 193
Impact of deployment type on performance ... 195
Impact of storage capacity on performance ... 197
Impact of throughput capacity on performance ... 198
Example: storage capacity and throughput capacity ... 204
Administering resources ... 205
Managing storage capacity ... 205
Storage tiers ... 206
Choosing file system storage capacity ... 207
File system storage capacity and IOPS ... 211
Volume storage capacity ... 238
Managing file systems ... 262
File system resources ... 263
Creating file systems ... 265
Updating file systems ... 279
Managing HA pairs ... 282
Managing the NVMe cache ... 290

Managing network type ... 291
Monitoring file system details ... 293
Deleting file systems ... 294
Managing SVMs ... 295
Maximum number of SVMs per file system ... 295
Creating SVMs ... 296
Updating SVMs ... 300
Managing SVM Microsoft Active Directory configurations ... 303
Auditing file access ... 304
Setting up workgroups ... 315
Monitoring SVM details ... 322
Deleting SVMs ... 322
Managing volumes ... 323
Volume styles ... 325
Volume types ... 327
Volume security style ... 327
Creating volumes ... 328
Updating volumes ... 333
Moving volumes ... 337
Monitoring volumes ... 341
Deleting volumes ... 343
Creating an iSCSI LUN ... 345
Next steps ... 347
Updating maintenance windows ... 347
Managing throughput capacity ... 349
When to modify throughput capacity ... 350
How concurrent requests are handled ... 350
Updating throughput capacity ... 351
Monitoring throughput capacity changes ... 352
Managing SMB shares ... 354
Managing with NetApp applications ... 356
Signing up for a NetApp account ... 357
Using NetApp Console ... 358
Using the NetApp ONTAP CLI ... 358
Using the ONTAP REST API ... 362
Tagging resources ... 362

Tag basics ... 363
Tagging your resources ... 364
Copying tags to backups ... 365
Tag restrictions ... 365
Permissions and tagging ... 366
Protecting your data ... 367
Backing up volumes ... 367
How backups work ... 368
Storage requirements ... 369
Automatic daily backups ... 370
User-initiated backups ... 371
Copying tags to backups ... 371
Using AWS Backup ... 371
Copying backups ... 372
Restoring backups ... 374
Backup performance ... 376
Backing up SnapLock volumes ... 377
Creating user-initiated backups ... 378
Copying backups within the same AWS account ... 378
Restoring backups ... 380
Restoring a subset of data ... 384
Monitoring volume restore progress ... 385
Deleting backups ... 387
Using volume snapshots ... 388
Snapshot policies ... 389
Restoring files from snapshots ... 390
Viewing the common snapshot ... 391
Updating snapshot reserve space ... 392
Disabling automatic snapshots ... 393
Deleting snapshots ... 395
Deleting snapshots ... 395
Snapshot reserve ... 397
Protecting data with Autonomous Ransomware Protection ... 397
How ARP works ... 398
What ARP looks for ... 398
How to respond to a suspected attack with ARP ... 399

Enabling ARP ... 400
Responding to ARP alerts ... 401
Understanding EMS alerts for ARP ... 403
Protecting data with SnapLock ... 404
How SnapLock works ... 405
Understanding SnapLock Compliance ... 409
Understanding SnapLock Enterprise ... 410
Understanding the SnapLock retention period ... 412
Committing files to WORM ... 414
Replicating your data with FlexCache ... 419
How FlexCache works ... 419
FlexCache write modes ... 419
FlexCache volume creation overview ... 420
Creating a FlexCache ... 420
Using SnapMirror for scheduled replication ... 426
Using NetApp Console to schedule replication ... 427
Using the ONTAP CLI to schedule replication ... 427
Billing and usage reporting ... 428
FSx for ONTAP billing report ... 428
FSx for ONTAP usage report ... 431
Monitoring file systems ... 436
Monitoring with CloudWatch ... 437
Accessing CloudWatch metrics ... 438
Monitoring in the Amazon FSx console ... 440
File system metrics ... 451
Second-generation file system metrics ... 472
Volume metrics ... 491
Monitoring EMS events ... 499
Overview of EMS events ... 500
Viewing EMS events ... 500
EMS event forwarding to a Syslog server ... 507
Monitoring with Data Infrastructure Insights ... 509
Monitoring with Harvest and Grafana ... 510
Getting started with Harvest and Grafana ... 510
Supported Harvest dashboards ... 510
Unsupported Harvest dashboards ... 511

CloudFormation template ... 512
Amazon EC2 instance types ... 512
Deployment procedure ... 513
Logging in to Grafana ... 516
Troubleshooting Harvest and Grafana ... 517
Monitoring with AWS CloudTrail ... 520
Amazon FSx Information in CloudTrail ... 520
Understanding Amazon FSx Log File Entries ... 521
Working with Active Directory ... 524
Self-managed Active Directory prerequisites ... 525
Self-managed Active Directory requirements ... 525
Network configuration requirements ... 525
Active Directory service account requirements ... 527
Self-managed Active Directory best practices ... 529
Delegating permissions to your Amazon FSx service account ... 529
Keep an AD configuration updated ... 530
Limit traffic within a VPC with security groups ... 531
Creating outbound security group rules ... 531
Storing Active Directory credentials using AWS Secrets Manager ... 531
How joining SVMs to Active Directory works ... 539
Active Directory information needed ... 541
Managing SVM Active Directory configurations ... 542
Joining SVMs to Active Directory ... 543
Updating Active Directory configurations ... 546
Updating Active Directory configurations with the NetApp CLI ... 547
Migrating to Amazon FSx ... 553
Migrating using SnapMirror ... 553
Before you begin ... 555
Create the destination volume ... 556
Record the source and destination inter-cluster LIFs ... 558
Establish cluster peering between source and destination ... 558
Create an SVM peering relationship ... 559
Create the SnapMirror relationship ... 560
Transfer data to your FSx for ONTAP file system ... 561
Cutting over to Amazon FSx ... 562
Migrating files with AWS DataSync ... 563

Prerequisites ... 564
DataSync migration basic steps ... 564
Security ... 565
Data protection ... 566
Data encryption in FSx for ONTAP ... 567
Encryption at rest ... 567
Encrypting data in transit ... 569
Identity and access management ... 591
Audience ... 591
Authenticating with identities ... 592
Managing access using policies ... 593
FSx for ONTAP and IAM ... 594
Identity-based policy examples ... 599
Troubleshooting IAM ... 602
Using service-linked roles ... 604
Using tags with Amazon FSx ... 609
AWS managed policies ... 615
AmazonFSxServiceRolePolicy ... 616
AmazonFSxDeleteServiceLinkedRoleAccess ... 616
AmazonFSxFullAccess ... 616
AmazonFSxConsoleFullAccess ... 617
AmazonFSxConsoleReadOnlyAccess ... 618
AmazonFSxReadOnlyAccess ... 619
Policy updates ... 620
File System Access Control with Amazon VPC ... 631
Amazon VPC security groups ... 632
Compliance Validation ... 634
Interface VPC endpoints ... 635
Considerations for Amazon FSx interface VPC endpoints ... 635
Creating an interface VPC endpoint for Amazon FSx API ... 636
Creating a VPC endpoint policy for Amazon FSx ... 637
Resilience ... 637
Backup and restore ... 637
Snapshots ... 638
Availability Zones ... 638
Infrastructure Security ... 638

Using antivirus software ... 639
ONTAP roles and users ... 639
File system administrator roles and users ... 640
SVM administrator roles and users ... 641
Authenticating ONTAP users with Active Directory ... 643
Creating new ONTAP users for file system and SVM administration ... 644
Creating ONTAP users ... 645
Creating SVM roles ... 648
Configuring Active Directory authentication for ONTAP users ... 649
Configuring public key authentication ... 651
Updating password requirements ... 653
Updating the `fsxadmin` account password fails ... 653
Quotas ... 655
Quotas that you can increase ... 655
Resource quotas for each file system ... 657
Troubleshooting ... 663
Misconfigured file systems ... 663
VPC sharing disabled ... 663
Can't create Multi-AZ file system ... 664
SSD tier more than 90% full ... 664
You can't access your file system ... 665
Missing route table tags ... 665
Too many routes ... 666
Missing routes to servers ... 666
Modified or deleted ENI ... 666
Deleted ENI ... 666
Missing inbound rules ... 667
Missing outbound rules ... 667
The compute instance's subnet doesn't use any of the route tables associated with your file system ... 667
Can't update Multi-AZ route table ... 667
Can't access iSCSI ... 668
Unshared VPC subnet ... 668
NFS, SMB, ONTAP CLI and API inaccessible from different VPC and on-premises ... 668
Misconfigured SVM ... 668
Your SVM has an offline volume ... 669

Your SVM has an offline volume with an iSCSI LUN or an NVMe/TCP namespace 669
The AWS Secrets Manager secret or KMS key is not configured correctly 669
Troubleshooting SSD decrease issues 670
SSD decrease paused – high utilization 670
SSD decrease paused – FlexClone 671
Volume redirect failed during decrease 671
SSD decrease taking too long 672
Can't join SVM to Active Directory 672
SVM NetBIOS name same as home domain 673
SVM is joined to another Active Directory 673
SVM NetBIOS name already used 674
Amazon FSx can't access your Active Directory service account credentials in AWS Secrets Manager 674
FSx can't reach Active Directory domain controllers 676
Insufficient port configuration or service account permissions 676
Invalid service account credentials 677
Amazon FSx can't connect to your Active Directory domain controllers because of insufficient service account credentials 677
Can't reach Active Directory DNS servers or domain controllers 678
Invalid Active Directory domain name 680
Service account can't access Active Directory administrators group 681
Specified OU is invalid 682
Can't delete SVM or volume 682
Identifying failed deletions 683
SVM deletion: Route tables inaccessible 683
SVM deletion: Peer relationship 684
SVM or volume deletion: SnapMirror 685
SVM deletion: Kerberos-enabled LIF 686
SVM deletion: Other reason 688
Volume deletion: FlexCache relationship 690
Misconfigured volume 691
Volume over 98% full 691
Block storage volume is offline 691
Offline FlexCache origin volume 692
Offline volume with SnapMirror relationship 692
Block storage volume is restricted 693

Restricted FlexCache origin volume ... 693
Restricted volume with SnapMirror relationship ... 693
Volume has insufficient storage ... 694
Determine how your volume storage capacity is being used ... 694
Increasing a volume's storage capacity ... 695
Using volume autosizing ... 695
Your file system's primary storage is full ... 695
Deleting snapshots ... 695
Increasing a volume's maximum file capacity ... 696
Failed volume backups ... 696
Recovering deleted volumes ... 697
Troubleshooting network issues ... 697
You want to capture a packet trace ... 697
I/O errors and NFS lock reclaim failures ... 700
I/O errors during failovers ... 700
NFSv4 alternatives ... 702
Document history ... 704

What is Amazon FSx for NetApp ONTAP?

Amazon FSx for NetApp ONTAP is a fully managed service that provides highly reliable, scalable, high-performing, and feature-rich file storage built on NetApp's popular ONTAP file system. FSx for ONTAP combines the familiar features, performance, capabilities, and API operations of NetApp file systems with the agility, scalability, and simplicity of a fully managed AWS service.

FSx for ONTAP provides feature-rich, fast, and flexible shared file storage that’s broadly accessible from Linux, Windows, and macOS compute instances running in AWS or on premises. FSx for ONTAP offers high-performance solid state drive (SSD) storage with submillisecond latencies. With FSx for ONTAP, you can achieve SSD levels of performance for your workload while paying for SSD storage for only a small fraction of your data.

Managing your data with FSx for ONTAP is easier because you can snapshot, clone, and replicate your files with the click of a button. In addition, FSx for ONTAP automatically tiers your data to lower-cost, elastic storage, lessening the need for you to provision or manage capacity.

FSx for ONTAP also provides highly available and durable storage with fully managed backups and support for cross-Region disaster recovery. To make it easier to protect and secure your data, FSx for ONTAP supports popular data security and antivirus applications.

For customers who use NetApp ONTAP on-premises, FSx for ONTAP is an ideal solution to migrate, back up, or burst your file-based applications from on-premises to AWS without the need to change your application code or how you manage your data.

As a fully managed service, FSx for ONTAP makes it easier to launch and scale reliable, high-performing, and secure shared file storage in the cloud. With FSx for ONTAP, you no longer have to worry about:

- Setting up and provisioning file servers and storage volumes
- Replicating data
- Installing and patching file server software
- Detecting and addressing hardware failures
- Managing failover and failback
- Manually performing backups

FSx for ONTAP also provides rich integration with other AWS services, such as AWS Identity and Access Management (IAM), Amazon WorkSpaces, AWS Key Management Service (AWS KMS), and AWS CloudTrail.

Topics

- Features of FSx for ONTAP
- Security and data protection
- Monitoring tools
- Pricing for FSx for ONTAP
- FSx for ONTAP on AWS re:Post
- Are you a first-time Amazon FSx user?

Features of FSx for ONTAP

With FSx for ONTAP, you get a fully managed file storage solution with:

- Support for petabyte-scale datasets in a single namespace
- Up to tens of gigabytes per second (GBps) of throughput per file system
- Multi-protocol access to data using the Network File System (NFS), Server Message Block (SMB), Internet Small Computer Systems Interface (iSCSI), and Non-Volatile Memory Express (NVMe) protocols
- Highly available and durable Multi-AZ and Single-AZ deployment options
- Automatic data-tiering that reduces storage costs by automatically transitioning infrequently accessed data to a lower-cost storage tier based on your access patterns
- Data compression, deduplication, and compaction to reduce your storage consumption
- Support for two network type options, IPv4-only and dual-stack (which supports both IPv4 and IPv6), to access and manage your file system
- Support for NetApp's SnapMirror replication feature
- Support for NetApp's FlexCache on-premises caching solution
- Support for access and management using native AWS or NetApp tools and API operations
  - AWS Management Console, AWS Command Line Interface (AWS CLI), and SDKs
  - NetApp ONTAP CLI, REST API, and NetApp Console

Security and data protection

The shared responsibility model is employed as it relates to Security in Amazon FSx for NetApp ONTAP. Amazon FSx provides multiple levels of security and compliance to facilitate protecting your data.

FSx for ONTAP supports the following data protection, security, and access control features:

- Encrypting data at rest for file system data and backups using AWS KMS keys
- Encrypting data in transit using:
  - SMB Kerberos
  - IPSEC
  - Nitro-based encryption
- On-demand antivirus scanning
- Authentication and authorization using Microsoft Active Directory
- File access auditing
- NetAppSnapLock WORM with Compliance and Enterprise retention modes

For more information, see Data protection in Amazon FSx for NetApp ONTAP and Protecting your data.

Additionally, Amazon FSx protects your data with highly durable file system backups. Amazon FSx performs automatic daily backups, and you can take additional backups at any point. For more information, see Protecting your data.

Monitoring tools

Monitoring tools include CloudWatch, CloudTrail, ONTAP EMS events, NetApp Data Infrastructure Insights, and NetApp Harvest.

Pricing for FSx for ONTAP

You are billed for file systems based on the following categories:

- SSD storage capacity (per gigabyte-month, or GB-month)
- SSD IOPS that you provision above three IOPS/GB (per IOPS-month)

- Throughput capacity (per megabytes per second [MBps]-month)
- Capacity pool storage consumption (per GB-month)
- Capacity pool requests (per read and write)
- Backup storage consumption (per GB-month)

For more information about pricing and fees associated with the service, see Amazon FSx for NetApp ONTAP pricing.

FSx for ONTAP on AWS re:Post

If you encounter issues while using Amazon FSx, use AWS re:Post to get answers to your FSx for ONTAP questions.

Are you a first-time Amazon FSx user?

If you're a first-time user of Amazon FSx, we recommend that you read the following sections in order:

1. If you're new to AWS, see Setting up FSx for ONTAP to set up an AWS account.
2. If you're ready to create your first Amazon FSx file system, follow the instructions in Getting started with Amazon FSx for NetApp ONTAP.
3. For information about performance, see Amazon FSx for NetApp ONTAP performance.
4. For Amazon FSx security details, see Security in Amazon FSx for NetApp ONTAP.
5. For information about the Amazon FSx API, see the Amazon FSx API Reference.

How Amazon FSx for NetApp ONTAP works

This topic introduces the major features of Amazon FSx for NetApp ONTAP file systems and how they work, with links to sections with in-depth descriptions, important implementation details, and step-by-step configuration procedures.

Topics

- FSx for ONTAP file systems
- Storage virtual machines
- Volumes
- Storage tiers
- Storage efficiency
- Accessing data stored on FSx for ONTAP file systems
- Managing FSx for ONTAP resources

FSx for ONTAP file systems

A file system is the primary FSx for ONTAP resource, analogous to an on-premises NetApp ONTAP cluster. You specify the solid state drive (SSD) storage capacity and throughput capacity for your file system, and choose an Amazon Virtual Private Cloud (VPC) where your file system is created. For more information, see Managing FSx for ONTAP file systems.

Your file system can have one to 12 high-availability (HA) pairs depending on its configuration. An HA pair is made up of two file servers in an active-standby configuration. First-generation FSx for ONTAP file systems and second-generation Multi-AZ file systems support one HA pair. Second-generation Single-AZ file systems support up to 12 HA pairs. For more information, see Managing high-availability (HA) pairs.

Storage virtual machines

A storage virtual machine (SVM) is an isolated file server with its own administrative and data access endpoints for administering and accessing data. When you access data in your FSx for ONTAP file system, your clients and workstations interface with an SVM using the SVM's endpoint IP address. For more information, see Managing SVMs.

You can join SVMs to a Microsoft Active Directory for file access authentication and authorization. For more information, see Working with Microsoft Active Directory in FSx for ONTAP.

Volumes

FSx for ONTAP **volumes** are virtual resources that you use for organizing and grouping your data. Volumes are logical containers that are hosted on SVMs, and data stored in them consumes physical storage capacity on your file system.

When you create a volume, you set its size, which determines the amount of physical data that you can store in it, regardless of which storage tier the data is stored on. You also set the volume type, either RW (read-writable) or DP (data protection). A DP volume is read-only and can be used as the destination in a NetApp SnapMirror or SnapVault relationship.

FSx for ONTAP volumes are thin provisioned, meaning that they only consume storage capacity for the data stored in them. With thin-provisioned volumes, storage capacity is not reserved in advance. Instead, storage is allocated dynamically, as it is needed. Free space is released back to the file system when data in the volume or LUN is deleted. For example, you can create three 10 TiB volumes on a file system configured with 10 TiB of free storage capacity, as long as the total amount of data stored in the three volumes doesn't exceed 10 TiB at any time. The amount of data physically stored on a volume counts toward your overall storage capacity consumption. For more information, see Managing FSx for ONTAP volumes.

Storage tiers

An FSx for ONTAP file system has two *storage tiers*: primary storage and capacity pool storage. Primary storage is provisioned, scalable, high-performance SSD storage that's purpose-built for the active portion of your data set. Capacity pool storage is a fully elastic storage tier that can scale to petabytes in size and is cost optimized for infrequently accessed data. Data that you write to your volumes consumes capacity on your storage tiers. For more information, see FSx for ONTAP storage tiers. You can increase the SSD storage capacity of your file system as your storage needs grow. On second-generation file systems, you can also decrease SSD storage capacity when your high-performance storage requirements change, allowing you to optimize storage costs. For more information, see File system storage capacity and IOPS.

Data tiering

Data tiering is the process by which Amazon FSx for NetApp ONTAP automatically moves data between the *SSD* and the *capacity pool* storage tiers. Each volume has a tiering policy that controls whether data is moved to the capacity tier when it becomes inactive (cold). A volume's Tiering policy cooling period determines when data becomes inactive (cold). For more information, see Volume data tiering.

Storage efficiency

Amazon FSx for NetApp ONTAP supports ONTAP's block-level storage efficiency features—compaction, compression, and deduplication—to reduce the storage capacity that your data consumes. Storage efficiency features can reduce the footprint of your data in SSD storage, capacity pool storage, and backups. The typical storage capacity savings for general purpose file sharing workloads without sacrificing performance is 65% from compression, deduplication, and compaction, on both the SSD and capacity pool storage tiers. For more information, see Storage efficiency.

Accessing data stored on FSx for ONTAP file systems

You can access your data on FSx for ONTAP volumes from multiple Linux, Windows, or macOS clients simultaneously over the NFS (v3, v4, v4.1, v4.2) and SMB protocols. You can also access data using the Non-Volatile Memory Express (NVMe) and Internet Small Computer Systems Interface (iSCSI) block protocol. For more information, see Accessing your FSx for ONTAP data.

Managing FSx for ONTAP resources

There are several ways that you can interact with your FSx for ONTAP file system and manage its resources. You can manage your FSx for ONTAP resources using both AWS and NetApp ONTAP management tools:

- AWS management tools
  - The AWS Management Console
  - The AWS Command Line Interface (AWS CLI)
  - The Amazon FSx API and SDKs
  - AWS CloudFormation

- NetApp management tools:
  - NetApp Console
  - The NetApp ONTAP CLI
  - The NetApp ONTAP REST API

For more information, see Administering resources.

Getting started with Amazon FSx for NetApp ONTAP

Learn how to get started using Amazon FSx for NetApp ONTAP. This getting started exercise includes the following steps.

1. Sign up for an AWS account and create an administrative user in the account.
2. Create an Amazon FSx for NetApp ONTAP file system using the Amazon FSx console.
3. Mount your file system from an Amazon EC2 Linux instance.
4. Clean up the resources you created.

Topics

- Setting up FSx for ONTAP
- Create an Amazon FSx for NetApp ONTAP file system
- Mounting your file system from an Amazon EC2 Linux instance
- Cleaning up resources

Setting up FSx for ONTAP

Before you use Amazon FSx for the first time, complete the following tasks.

Topics

- Sign up for an AWS account
- Next step

Sign up for an AWS account

To get started with AWS, you need an AWS account. For information about creating an AWS account, see Getting started with an AWS account in the *AWS Account Management Reference Guide*.

Next step

To get started using FSx for ONTAP see Getting started with Amazon FSx for NetApp ONTAP for instructions to create your Amazon FSx resources.

Create an Amazon FSx for NetApp ONTAP file system

The Amazon FSx console has two options for creating a file system – a **Quick create** option and a **Standard create** option. To rapidly and easily create an Amazon FSx for NetApp ONTAP file system with the service recommended configuration, use the **Quick create** option.

The **Quick create** option configures this file system to allow data access from Linux instances over the Network File System (NFS) protocol. After your file system is created, you can create additional SVMs and volumes as needed, including an SVM joined to an Active Directory to allow access from Windows and macOS clients over the Server Message Block (SMB) protocol. You can also add additional high-availability (HA) pairs depending on the deployment type that you choose and how many HA pairs you add at creation.

> **Note**
>
> FSx for ONTAP file systems created with the **Quick create** option use a **Network type** of `IPv4`. To create a file system with a **Network type** of `Dual-stack` (which supports both IPv4 and IPv6), use the **Standard create** option.

For information about using the **Standard create** option to create a file system with a customized configuration, and for using the AWS CLI and API, see Creating file systems.

To create your file system

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. On the dashboard, choose **Create file system** to start the file system creation wizard.
3. On the **Select file system type** page, choose **Amazon FSx for NetApp ONTAP**, and then choose **Next**. The **Create ONTAP file system** page appears.
4. For **Creation method**, choose **Quick create**.
5. In the **Quick configuration** section, for **File system name - optional**, enter a name for your file system. It's easier to find and manage your file systems when you name them. You can use a maximum of 256 Unicode letters, white space, and numbers, plus these special characters: **+ -** (hyphen) **= . _** (underscore) **: /**
6. For **Deployment type** choose **Multi-AZ** or **Single-AZ**.

- **Multi-AZ** file systems replicate your data and support failover across multiple Availability Zones in the same AWS Region.
- **Single-AZ** file systems replicate your data and offer automatic failover within a single Availability Zone.

For more information, see *Availability, durability, and deployment options*.

> **Note**
>
> The latest generation FSx for ONTAP file system that is available for your AWS Region is chosen by default. You can specify the generation of your file system (in available AWS Regions) with the **Standard create** option. For more information, see Creating file systems.

7. For **SSD storage capacity**, specify the storage capacity of your file system, in gibibytes (GiB). Enter any whole number in the range of 1,024–1,048,576. For more information, see To create a file system (console).

   You can increase the amount of storage capacity as needed at any time after you create the file system. For more information, see Managing storage capacity.

8. For **Throughput capacity**, Amazon FSx automatically provides a recommended throughput capacity based on your SSD storage. You can also choose your file system's throughput (up to 73,728 MBps depending on the deployment type and amount of HA pairs).

9. For **Virtual Private Cloud (VPC)**, choose the Amazon VPC that you want to associate with your file system.

10. (Multi-AZ only) **Endpoint IP address range** specifies the IP address range in which the endpoints to access your file system are created.

    Choose a **Quick create** option for the endpoint IP address range:

    - **Unallocated IPv4 address range from your VPC** – Choose this option to have Amazon FSx use the last 64 IP addresses from the VPC's primary CIDR range as the endpoint IPv4 address range for the file system. Note that this range is shared across multiple file systems if you choose this option multiple times.

> **Note**
>
> - Each file system that you create consumes two IP addresses from this range—one for the cluster, and one for the first SVM. The first and last IP addresses are also reserved. For every additional SVM, the file system consumes another IP address. For example, a file system that hosts 10 SVMs uses 11 IP addresses. Additional file systems work in the same way. They consume the two initial IP addresses, plus one for each additional SVM. The maximum number of file systems using the same IP address range, each with a single SVM, is 31.
> - This option is grayed out if any of the last 64 IP addresses in a VPC's primary CIDR range are in use by a subnet.

- **Floating IPv4 address range outside your VPC** – Choose this option to have Amazon FSx use a 198.19.x.0/24 address range that isn't already used by any other file systems with the same VPC and route tables.

You can also specify your own IP address range in the **Standard create** option. The IP address range that you choose can either be inside or outside the VPC's IPv4 address range, as long as it doesn't overlap with any subnet, and as long as it isn't already used by another file system with the same VPC and route tables. We recommend using a range that is inside the VPC's IP address range.

> **Note**
>
> Ensure that all of the route tables you're using are associated with your Multi-AZ file system. Doing so helps prevent unavailability during a failover. For information about associating your Amazon VPC route tables with your file system, see Updating file systems.

11. For **Storage efficiency**, choose **Enabled** to turn on the ONTAP storage efficiency features (compression, deduplication, and compaction) or **Disabled** to turn them off.
12. Choose **Next**, and review the file system configuration on the **Create ONTAP file system** page. Note which file system settings you can modify after the file system is created.
13. Choose **Create file system**.

Quick create creates a file system with one SVM (named `fsx`) and one volume (named `vol1`). The volume has a junction path of `/vol1` and a capacity pool tiering policy of **Auto** (which will automatically tier any data that hasn't been accessed for 31 days to lower-cost capacity pool storage). The default snapshot policy gets assigned to the default volume. The file system data is encrypted at rest using your default service managed AWS KMS key.

Creating a Microsoft Active Directory-joined SVM

After creating your file system, you can create additional SVMs joined to Microsoft Active Directory to enable SMB access from Windows and macOS clients. FSx for ONTAP integrates with AWS Secrets Manager to securely manage your Microsoft Active Directory domain join service account credentials.

To create a Microsoft Active Directory-joined SVM

1. In the Amazon FSx console, choose **Storage virtual machines** from the left navigation pane.
2. Choose **Create storage virtual machine**.
3. For **File system**, select the file system you created.
4. For **Storage virtual machine name**, enter a name for your SVM.
5. For **Microsoft Active Directory configuration**, choose **Join a Microsoft Active Directory**.
6. For **Domain join service account credentials**, choose **Managed in Secrets Manager** (default) to use Secrets Manager for secure credential management.

   > **Note**
   >
   > Using Secrets Manager eliminates the need to store plaintext credentials and provides centralized credential management. For more information, see Storing Active Directory credentials using AWS Secrets Manager.

7. For **Secret**, choose an existing secret from Secrets Manager that contains your domain join service account credentials, or choose **Create new secret** to create one.
8. Complete the remaining Microsoft Active Directory configuration fields as needed for your environment.
9. Choose **Create storage virtual machine**.

Your SVM will be created and joined to Microsoft Active Directory using the credentials stored in Secrets Manager. You can now create SMB shares and volumes on this SVM for Windows and macOS client access.

Mounting your file system from an Amazon EC2 Linux instance

You can mount your file system from an Amazon Elastic Compute Cloud (Amazon EC2) instance. This procedure uses an instance running Amazon Linux 2.

To mount your file system from Amazon EC2

1. Open the Amazon EC2 console at https://console.aws.amazon.com/ec2/.
2. Create or select an Amazon EC2 instance running Amazon Linux 2 that is in the same virtual private cloud (VPC) as your file system. For more information about launching an instance, see Step 1: Launch an instance in the *Amazon EC2 User Guide*.
3. Connect to your Amazon EC2 Linux instance. For more information, see Connect to your Linux instance in the *Amazon EC2 User Guide*.
4. Open a terminal on your Amazon EC2 instance using secure shell (SSH), and log in with the appropriate credentials.
5. Create a directory on your Amazon EC2 instance to use as the volume's mount point with the following command. In the following example, replace *mount-point* with your own information.

   ```
   $ sudo mkdir /mount-point
   ```

6. Mount your Amazon FSx for NetApp ONTAP file system to the directory that you created. Use a `mount` command similar to the example that follows. In the following example, replace the following placeholder values with your own information.

   - *nfs_version* – The NFS version you are using; FSx for ONTAP supports versions 3, 4.0, 4.1, and 4.2.
   - *nfs-dns-name* – The NFS DNS name of the storage virtual machine (SVM) in which the volume you are mounting exists. You can find the NFS DNS name in the Amazon FSx console by choosing **Storage virtual machines**, then choosing the SVM on which the volume you are mounting exists. The NFS DNS name is found on the **Endpoints** panel.

- *volume-junction-path* – The junction path of the volume that you're mounting. You can find a volume's junction path in the Amazon FSx console on the **Summary** panel of the Volume details page.
- *mount-point* – The name of the directory that you created on your EC2 instance for the volume's mount point.

```
sudo mount -t nfs -o nfsvers=nfs_version nfs-dns-name:/volume-junction-path /mount-point
```

The following command uses example values.

```
sudo mount -t nfs -o nfsvers=4.1 svm-abcdef1234567890c.fs-012345abcdef6789b.fsx.us-east-2.amazonaws.com:/vol1 /fsxN
```

If you have issues with your Amazon EC2 instance (such as connections timing out), see Troubleshoot EC2 instances in the *Amazon EC2 User Guide*.

Cleaning up resources

After you have finished this exercise, you should follow these steps to clean up your resources and protect your AWS account.

To clean up resources

1. On the Amazon EC2 console, terminate your instance. For more information, see Terminate Your Instance in the *Amazon EC2 User Guide.*
2. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
3. On the Amazon FSx console, delete all of your FSx for ONTAP volumes that are not root volumes of your SVM. For more information, see Deleting volumes.
4. Delete all of your FSx for ONTAP SVMs. For more information, see Deleting storage virtual machines (SVM).
5. On the Amazon FSx console, delete your file system. When you delete a file system, all automatic backups are deleted automatically. However, you still must delete any manually created backups. The following steps outline this process.

a. From the console dashboard, choose the name of the file system that you created for this exercise.

b. For **Actions**, choose **Delete file system**.

c. In the **Delete file system** dialog box, enter the ID of the file system that you want to delete in the **File system ID** box.

d. Choose **Delete file system**.

e. While Amazon FSx deletes the file system, its status in the dashboard changes to **DELETING**. Once the file system is deleted, it no longer appears in the dashboard. Any automatic backups are deleted along with the file system.

f. Now you can delete any manually created backups for your file system. From the left-side navigation, choose **Backups**.

g. From the dashboard, choose any backups that have the same **File system ID** as the file system that you deleted, and choose **Delete backup**. Be sure to retain the final backup, if you created one.

h. The **Delete backups** dialog box opens. Keep the check box selected for the IDs of the backups that you want to delete, and then choose **Delete backups**.

Your Amazon FSx file system and any related automatic backups are now deleted, along with any manual backups that you chose to delete as well.

Availability by AWS Region

Amazon FSx for NetApp ONTAP file systems are available in the following AWS Regions, with deployment type support indicated for each region:

AWS Region	Single-AZ 1	Multi-AZ 1	Single-AZ 2	Multi-AZ 2		
US East (N. Virginia)	✓	✓	✓	✓		
US East (Ohio)	✓	✓	✓	✓		
US West (N. California)	✓	✓	✓	✓		
US West (Oregon)	✓	✓	✓	✓		
AWS GovCloud (US-East)	✓	✓				
AWS GovCloud (US-West)	✓	✓	✓	✓		
Africa (Cape Town)	✓	✓				
Asia Pacific (Hong Kong)	✓	✓				

AWS Region	Single-AZ 1	Multi-AZ 1	Single-AZ 2	Multi-AZ 2		
Asia Pacific (Tokyo)	✓	✓	✓	✓		
Asia Pacific (Seoul)	✓	✓	✓	✓		
Asia Pacific (Osaka)	✓	✓				
Asia Pacific (Mumbai)	✓	✓	✓	✓		
Asia Pacific (Hyderabad)	✓	✓	✓	✓		
Asia Pacific (Singapore)	✓	✓	✓	✓		
Asia Pacific (Sydney)	✓	✓	✓	✓		
Asia Pacific (Jakarta)	✓	✓				
Asia Pacific (Melbourne)	✓	✓				
Asia Pacific (Malaysia)	✓	✓				
Asia Pacific (New Zealand)	✓	✓				

AWS Region	Single-AZ 1	Multi-AZ 1	Single-AZ 2	Multi-AZ 2		
Asia Pacific (Taipei)	✓	✓				
Asia Pacific (Thailand)	✓	✓				
Canada (Central)	✓	✓	✓	✓		
Canada West (Calgary)	✓	✓				
Europe (Frankfurt)	✓	✓	✓	✓		
Europe (Zurich)	✓	✓	✓	✓		
Europe (Stockholm)	✓	✓	✓	✓		
Europe (Milan)	✓	✓				
Europe (Spain)	✓	✓	✓	✓		
Europe (Ireland)	✓	✓	✓	✓		
Europe (London)	✓	✓	✓	✓		

AWS Region	Single-AZ 1	Multi-AZ 1	Single-AZ 2	Multi-AZ 2		
Europe (Paris)	✓	✓				
Israel (Tel Aviv)	✓	✓				
Mexico (Central)	✓	✓				
Middle East (UAE)	✓	✓				
Middle East (Bahrain)	✓	✓				
South America (São Paulo)	✓	✓	✓	✓		

Accessing your FSx for ONTAP data

You can access your Amazon FSx file systems using a variety of supported clients and methods in both the AWS Cloud and on premises environments.

Each SVM has four endpoints that are used to access data or to manage the SVM using the NetApp ONTAP CLI or REST API:

- `Nfs` – For connecting using the Network File System (NFS) protocol
- `Smb` – For connecting using the Service Message Block (SMB) protocol (If your SVM is joined to an Active Directory, or you're using a workgroup.)
- `Iscsi` – For connecting using the Internet Small Computer Systems Interface (iSCSI) protocol for shared block storage support.
- `Nvme` – For connecting using the Non-Volatile Memory Express (NVMe) over TCP/IP for shared block storage support.
- `Management` – For managing SVMs using the NetApp ONTAP CLI or API, or NetApp Console

> **Note**
>
> The iSCSI protocol is available on all file systems that have 6 or fewer high-availability pairs (HA) pairs. The NVMe/TCP protocol is available on second-generation file systems that have 6 or fewer HA pairs.

Topics

- Supported clients
- Using block storage protocols
- Accessing data from within the AWS Cloud
- Accessing data from on-premises
- Configure routing to access Multi-AZ file systems from outside your VPC
- Configure routing to access Multi-AZ file systems from on-premises
- Mounting volumes on Linux clients
- Mounting volumes on Microsoft Windows clients
- Mounting volumes on macOS clients

- Provisioning iSCSI for Linux
- Provisioning iSCSI for Windows
- Provisioning NVMe/TCP for Linux
- Accessing your data via Amazon S3 access points
- Accessing data from other AWS services

Supported clients

FSx for ONTAP file systems support accessing data from a wide variety of compute instances and operating systems. It does this by supporting access using the Network File System (NFS) protocol (v3, v4.0, v4.1 and v4.2), all versions of the Server Message Block (SMB) protocol (including 2.0, 3.0, and 3.1.1), and the Internet Small Computer Systems Interface (iSCSI) protocol.

> **Important**
>
> Amazon FSx doesn't support accessing file systems from the public internet. Amazon FSx automatically detaches any Elastic IP address which is a public IP address reachable from the Internet, that gets attached to a file system's elastic network interface.

The following AWS compute instances are supported for use with FSx for ONTAP:

- Amazon Elastic Compute Cloud (Amazon EC2) instances running Linux with NFS or SMB support, Microsoft Windows, and MacOS. For more information see Mounting volumes on Linux clients Mounting volumes on Microsoft Windows clients, and Mounting volumes on macOS clients.
- Amazon Elastic Container Service (Amazon ECS) Docker containers on Amazon EC2 Windows and Linux instances. For more information, see Using Amazon Elastic Container Service with FSx for ONTAP.
- Amazon Elastic Kubernetes Service – To learn more, see Amazon FSx for NetApp ONTAP CSI driver in the *Amazon EKS User Guide*.
- Red Hat OpenShift Service on AWS (ROSA) – To learn more, see What is Red Hat OpenShift Service on AWS? in the Red Hat OpenShift Service on AWS User Guide.
- Amazon WorkSpaces instances. For more information, see Using Amazon WorkSpaces with FSx for ONTAP.
- Amazon AppStream 2.0 instances.

- AWS Lambda – For more information, see the AWS blog post Enabling SMB access for server-less workloads with Amazon FSx.
- Virtual machines (VMs) running in VMware Cloud on AWS environments. For more information, see Configure Amazon FSx for NetApp ONTAP as External Storage and VMware Cloud on AWS with Amazon FSx for NetApp ONTAP Deployment Guide.

Once mounted, FSx for ONTAP file systems appear as a local directory or drive letter over NFS and SMB, providing fully managed, shared network file storage that can be simultaneously accessed by up to thousands of clients. iSCSI LUNS are accessible as block devices when mounted over iSCSI.

Using block storage protocols

Amazon FSx for NetApp ONTAP supports the Internet Small Computer Systems Interface (iSCSI) and Non-Volatile Memory Express (NVMe) over TCP (NVMe/TCP) block storage protocols. In Storage Area Network (SAN) environments, storage systems are targets that have storage target devices. For iSCSI, the storage target devices are referred to as logical units (LUNs). For NVMe/TCP, the storage target devices are referred to as namespaces.

You use an SVM's iSCSI logical interface (LIF) to connect to both NVMe and iSCSI block storage.

You configure storage by creating LUNs for iSCSI and by creating namespaces for NVMe. LUNs and namespaces are then accessed by hosts using iSCSI or TCP protocols.

For more information about configuring iSCSI and NVMe/TCP block storage, see:

- Provisioning iSCSI for Linux
- Provisioning iSCSI for Windows
- Provisioning NVMe/TCP for Linux

Accessing data from within the AWS Cloud

Each Amazon FSx file system is associated with a Virtual Private Cloud (VPC). You can access your FSx for ONTAP file system from anywhere in the file system's VPC, regardless of Availability Zone. You can also access your file system from other VPCs that can be in different AWS accounts or AWS Regions. In addition to the requirements described in the following sections for accessing FSx for ONTAP resources, you also need to ensure that your file system's VPC security group is configured

so that data and management traffic can flow between your file system and clients. For more information about configuring security groups with the required ports, see Amazon VPC security groups.

Accessing data from within the same VPC

When you create your Amazon FSx for NetApp ONTAP file system, you select the Amazon VPC in which it is located. All SVMs and volumes associated with the Amazon FSx for NetApp ONTAP file system are also located in the same VPC. When mounting a volume, if the file system and the client mounting the volume are located in the same VPC and AWS account, you can use the SVM's DNS name and volume junction or SMB share, depending on the client.

You can achieve optimal performance if the client and the volume are located in the in the same Availability Zone as the file system's subnet, or preferred subnet for Multi-AZ file systems. To identify a file system's subnet or preferred subnet, in the Amazon FSx console, choose **File systems**, then choose the ONTAP file system whose volume you are mounting, and the subnet or preferred subnet (Multi-AZ) is displayed in the **Subnet** or **Preferred subnet** panel.

Accessing data from outside the deployment VPC

This section describes how to access an FSx for ONTAP file system's endpoints from AWS locations outside of the file system's deployment VPC.

Accessing NFS, SMB, and ONTAP management endpoints on Multi-AZ file systems

The NFS, SMB, and ONTAP management endpoints on Amazon FSx for NetApp ONTAP Multi-AZ file systems use floating internet protocol (IP) addresses so that connected clients seamlessly transition between the preferred and standby file servers during a failover event. For more information about failovers, see Failover process for FSx for ONTAP.

These floating IP addresses are created in the VPC route tables that you associate with your file system, and are within the file system's `EndpointIPv4AddressRange` or `EndpointIPv6AddressRange` which you specify during creation. The endpoint IP address range uses the following address ranges, depending on how a file system is created:

- Multi-AZ dual-stack file systems created with the Amazon FSx console or Amazon FSx API by default use an available /118 IP address range selected by Amazon FSx from one of the VPC's CIDR ranges. You can have overlapping endpoint IP addresses for file systems deployed in the same VPC/route tables, as long as they don't overlap with any subnet.

- Multi-AZ IPv4-only file systems created using the Amazon FSx console use the last 64 IP addresses in the VPC's primary CIDR range for the file system's endpoint IP address range by default.

  Multi-AZ IPv4-only file systems created using the AWS CLI or Amazon FSx API use an IP address range within the `198.19.0.0/16` address block for the endpoint IP address range by default.
- For either network type, you can also specify your own IP address range when you use the **Standard create** option. The IP address range that you choose can either be inside or outside the VPC's IP address range, as long as it doesn't overlap with any subnet, and as long as it isn't already used by another file system with the same VPC and route tables. For this option we recommend using a range that is inside the VPC's IP address range.

Only AWS Transit Gateway supports routing to floating IP addresses, which is also known as transitive peering. VPC Peering, Direct Connect, and Site-to-Site VPN don't support transitive peering. Therefore, you are required to use Transit Gateway in order to access these interfaces from networks that are outside of your file system's VPC.

The following diagram illustrates using Transit Gateway for NFS, SMB, or management access to a Multi-AZ file system that is in a different VPC than the clients that are accessing it.



> **Note**
>
> Ensure that all of the route tables you're using are associated with your Multi-AZ file system. Doing so helps prevent unavailability during a failover. For information about associating your Amazon VPC route tables with your file system, see Updating file systems.

For information about when you need to use Transit Gateway to access your FSx for ONTAP file system, see When is Transit Gateway required?.

Amazon FSx manages VPC route tables for Multi-AZ file systems using tag-based authentication. These route tables are tagged with `Key: AmazonFSx; Value: ManagedByAmazonFSx`. When creating or updating FSx for ONTAP Multi-AZ file systems using CloudFormation we recommend that you add the `Key: AmazonFSx; Value: ManagedByAmazonFSx` tag manually.

Accessing NFS, SMB, or the ONTAP CLI and API for Single-AZ file systems

The endpoints used to access FSx for ONTAP Single-AZ file systems over NFS or SMB, and for administering file systems using the ONTAP CLI or REST API, are secondary IP addresses on the ENI of the active file server. The secondary IP addresses are within the VPC's CIDR range, so clients can access data and management ports using VPC Peering, AWS Direct Connect, or Site-to-Site VPN without requiring AWS Transit Gateway.

The following diagram illustrates using Site-to-Site VPN or Direct Connect for NFS, SMB, or management access to a Single-AZ file system that is in a different VPC than the clients accessing it.



When is Transit Gateway required?

Whether or not Transit Gateway is required for your Multi-AZ file systems depends on the method you use to access your file system data. Single-AZ file systems do not require Transit Gateway. The following table describes when you will need to use AWS Transit Gateway to access Multi-AZ file systems.

Data access	Requires Transit Gateway?
Accessing FSx over NFS, SMB, or the NetApp ONTAP REST API, CLI. or NetApp Console	Only if: • Accessing from a peered (on-premises, for example) network, and • You are not accessing FSx through a NetApp FlexCache or Global File Cache instance
Accessing data over iSCSI	No

Data access	Requires Transit Gateway?
Accessing data over NVMe	No
Joining an SVM to an Active Directory	No
SnapMirror	No
FlexCache Caching	No
Global File Cache	No

Accessing NVMe, iSCSI and inter-cluster endpoints outside of the deployment VPC

You can use either VPC Peering or AWS Transit Gateway to access your file system's NVMe, iSCSI, and inter-cluster endpoints from outside of the file system's deployment VPC. You can use VPC Peering to route NVMe, iSCSI, and inter-cluster traffic between VPCs. A VPC peering connection is a networking connection between two VPCs, and is used to route traffic between them using private IPv4 or IPv6 addresses. You can use VPC peering to connect VPCs within the same AWS Region or between different AWS Regions. For more information on VPC peering, see What is VPC peering? in the *Amazon VPC Peering Guide*.

Accessing data from on-premises

You can access your FSx for ONTAP file systems from on-premises using Site-to-Site VPN and Direct Connect; more specific use case guidelines are available in the following sections. In addition to any requirements listed below for accessing different FSx for ONTAP resources from on-premises, you also need to ensure that your file system's VPC security group allows data to flow between your file system and clients; for a list of required ports, see Amazon VPC security groups.

Accessing NFS, SMB, and ONTAP CLI and REST API endpoints from on-premises

This section describes how to access the NFS, SMB, and ONTAP management ports on FSx for ONTAP file systems from on-premises networks.

Accessing Multi-AZ file systems from on-premises

Amazon FSx requires that you use AWS Transit Gateway or that you configure remote NetApp Global File Cache or NetApp FlexCache to access Multi-AZ file systems from an on-premises network. In order to support failover across availability zones for Multi-AZ file systems, Amazon FSx uses floating IP addresses for the interfaces used for NFS, SMB, and ONTAP management endpoints.

Because the NFS, SMB, and management endpoints use floating IP addresses, you must use AWS Transit Gateway in conjunction with AWS Direct Connect or Site-to-Site VPN to access these interfaces from an on-premises network. The floating IP addresses used for these interfaces are within the `EndpointIPv4AddressRange` or `EndpointIPv6AddressRange` you specify when creating your Multi-AZ file system. The endpoint IP address range uses the following address ranges, depending on how a file system is created:

- Multi-AZ dual-stack file systems created with the Amazon FSx console or Amazon FSx API by default use an available /118 IP address range selected by Amazon FSx from one of the VPC's CIDR ranges. You can have overlapping endpoint IP addresses for file systems deployed in the same VPC/route tables, as long as they don't overlap with any subnet.
- Multi-AZ IPv4-only file systems created using the Amazon FSx console use the last 64 IP addresses in the VPC's primary CIDR range for the file system's endpoint IP address range by default.

  Multi-AZ IPv4-only file systems created using the AWS CLI or Amazon FSx API use an IP address range within the `198.19.0.0/16` address block for the endpoint IP address range by default.
- For either network type, you can also specify your own IP address range when you use the **Standard create** option. The IP address range that you choose can either be inside or outside the VPC's IP address range, as long as it doesn't overlap with any subnet, and as long as it isn't already used by another file system with the same VPC and route tables. For this option we recommend using a range that is inside the VPC's IP address range.

The floating IP addresses are used to enable a seamless transition of your clients to the standby file system in the event a failover is required. For more information, see Failover process for FSx for ONTAP.

> **Important**
>
> To access a Multi-AZ file system using a Transit Gateway, each of the Transit Gateway's attachments must be created in a subnet whose route table is associated with your file system.

For more information, see Configure routing to access Multi-AZ file systems from on-premises.

Accessing Single-AZ file systems from on-premises

The requirement to use AWS Transit Gateway to access data from an on-premises network doesn't exist for Single-AZ file systems. Single-AZ file systems are deployed in a single subnet, and a floating IP address is not required to provide failover between nodes. Instead, the IP addresses you access on Single-AZ file systems are implemented as secondary IP addresses within the file system's VPC CIDR range, enabling you to access your data from another network without requiring AWS Transit Gateway.

Accessing inter-cluster endpoints from on-premises

FSx for ONTAP's inter-cluster endpoints are dedicated to replication traffic between NetApp ONTAP file systems, including between on-premises NetApp deployments and FSx for ONTAP. Replication traffic includes SnapMirror, FlexCache, and FlexClone relationships between storage virtual machines (SVMs) and volumes across different file systems, and NetApp Global File Cache. The inter-cluster endpoints are also used for Active Directory traffic.

Because a file system's inter-cluster endpoints use IP addresses that are within the CIDR range of the VPC you provide when you create your FSx for ONTAP file system, you are not required to use a Transit Gateway for routing inter-cluster traffic between on-premises and the AWS Cloud. However, on-premises clients still must use Site-to-Site VPN or Direct Connect to establish a secure connection to your VPC.

For more information, see Configure routing to access Multi-AZ file systems from on-premises.

Configure routing to access Multi-AZ file systems from outside your VPC

If you have a Multi-AZ file system with an `EndpointIPv4AddressRange` or `EndpointIPv6AddressRange` that's outside your VPC's IP address range, you need to set up

additional routing in your AWS Transit Gateway to access your file system from peered or on-premises networks.

Important

To access a Multi-AZ file system using a Transit Gateway, each of the Transit Gateway's attachments must be created in a subnet whose route table is associated with your file system.

Note

No additional Transit Gateway configuration is required for Single-AZ file systems or Multi-AZ file systems with an endpoint IP address range that's within your VPC's IP address range.

To configure routing using AWS Transit Gateway

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. Choose the FSx for ONTAP file system for which you are configuring access from a peered network.
3. In **Network & security** copy the endpoint IP address range.
4. Add a route to Transit Gateway that routes traffic destined for this IP address range to your file system's VPC. For more information, see Work with transit gateways in the *Amazon VPC Transit Gateways*.
5. Confirm that you can access your FSx for ONTAP file system from the peered network.

To add the route table to your file system, see Updating file systems.

Note

DNS records for the management, NFS, and SMB endpoints are only resolvable from within the same VPC as the file system. In order to mount a volume or connect to a management port from another network, you need to use the endpoint's IP address. These IP addresses do not change over time.

Configure routing to access Multi-AZ file systems from on-premises

To configure AWS Transit Gateway for access to Multi-AZ file systems from on-premises

If you have a Multi-AZ file system with an `EndpointIPv4AddressRange` or `EndpointIPv6AddressRange` that's outside your VPC's CIDR range, you need to set up additional routing in your AWS Transit Gateway to access your file system from peered or on-premises networks.

> **Note**
>
> No additional Transit Gateway configuration is required for Single-AZ file systems or Multi-AZ file systems with an endpoint IP address range that's within your VPC's IP address range.

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. Choose the FSx for ONTAP file system for which you are configuring access from a peered network.
3. In **Network & security** copy the **Endpoint IPv4 or IPv6 address range**.
4. Add a route to the Transit Gateway that routes traffic destined for this IP address range to your file system's VPC. For more information, see Work with transit gateways in the *Amazon VPC Transit Gateway User Guide*.
5. Confirm that you can access your FSx for ONTAP file system from the peered network.

> **Important**
>
> To access a Multi-AZ file system using a Transit Gateway, each of the Transit Gateway's attachments must be created in a subnet whose route table is associated with your file system. Where you have separate Transit Gateway attachment subnets, you must also associate the route tables for those subnets with Amazon FSx so that they are updated with the Amazon FSx endpoint addresses.

To add a route table to your file system, see Updating file systems.

Mounting volumes on Linux clients

We recommend that the volumes you want to mount with Linux clients have a security style setting of `UNIX`. For more information, see Managing FSx for ONTAP volumes.

> **Note**
>
> By default, FSx for ONTAP NFS mounts are `hard` mounts. To ensure a smooth failover in the event that one occurs, we recommend that you use the default `hard` mount option.

To mount an ONTAP volume on a Linux client

1. Open the Amazon EC2 console at https://console.aws.amazon.com/ec2/.
2. Create or select an Amazon EC2 instance running Amazon Linux 2 that is in the same VPC as the file system.

   For more information on launching an EC2 Linux instance, see Step 1: Launch an instance in the *Amazon EC2 User Guide*.
3. Connect to your Amazon EC2 Linux instance. For more information, see Connect to your Linux instance in the *Amazon EC2 User Guide*.
4. Open a terminal on your EC2 instance using secure shell (SSH), and log in with the appropriate credentials.
5. Create a directory on the EC2 instance for mounting the SVM volume as follows:

   ```
   sudo mkdir /fsx
   ```
6. Mount the volume to the directory you just created using the following command:

   ```
   sudo mount -t nfs svm-dns-name:/volume-junction-path /fsx
   ```

   The following example uses sample values.

   ```
   sudo mount -t nfs svm-01234567890abdef0.fs-01234567890abcdef1.fsx.us-
   east-1.amazonaws.com:/vol1 /fsx
   ```

You can also use the SVM's IP address instead of its DNS name. We recommend using the DNS name to mount clients to second-generation file systems because it helps ensure that your clients are balanced across your file system's high-availability (HA) pairs.

```
sudo mount -t nfs 198.51.100.1:/vol1 /fsx
```

> **Note**
>
> For second-generation file systems, the parallel NFS (pNFS) protocol is enabled by default and is used by default for any clients mounting volumes with NFS v4.1 or greater.

Using /etc/fstab to mount automatically on instance reboot

To automatically remount your FSx for ONTAP volume when an Amazon EC2 Linux instance reboots, use the `/etc/fstab` file. The `/etc/fstab` file contains information about file systems. The command `mount -a`, which runs during instance start-up, mounts the file systems listed in `/etc/fstab`.

> **Note**
>
> FSx for ONTAP file systems do not support automatic mounting using `/etc/fstab` on Amazon EC2 Mac instances.

> **Note**
>
> Before you can update the `/etc/fstab` file of your EC2 instance, make sure that you already created your FSx for ONTAP file system. For more information, see Creating file systems.

To update the /etc/fstab file on your EC2 instance

1. Connect to your EC2 instance:

- To connect to your instance from a computer running macOS or Linux, specify the .pem file for your SSH command. To do this, use the `-i` option and the path to your private key.
- To connect to your instance from a computer running Windows, you can either use MindTerm or PuTTY. To use PuTTY, install it and convert the .pem file to a .ppk file.

For more information, see the following topics in the *Amazon EC2 User Guide*:

- Connecting to your Linux instance using SSH
- Connecting to your Linux instance from Windows using PuTTY

2. Create a local directory that will be used to mount the SVM volume.

```
sudo mkdir /fsx
```

3. Open the `/etc/fstab` file in an editor of your choice.
4. Add the following line to the `/etc/fstab` file. Insert a tab character between each parameter. It should appear as one line with no line breaks.

```
svm-dns-name:volume-junction-path /fsx nfs nfsvers=version,defaults 0 0
```

You can also use the IP address of volume's SVM. The last three parameters indicate NFS options (which we set to default), dumping of file system and filesystem check (these are typically not used so we set them to 0).

5. Save the changes to the file.
6. Now mount the file share using the following command. The next time the system starts, the folder will be mounted automatically.

```
sudo mount /fsx
sudo mount svm-dns-name:volume-junction-path
```

Your EC2 instance is now configured to mount the ONTAP volume whenever it restarts.

Mounting volumes on Microsoft Windows clients

This section describes how to access data in your FSx for ONTAP file system with clients running the Microsoft Windows operating system. Review the following requirements, regardless of the type of client you are using.

This procedure assumes that the client and the file system are located in the same VPC and AWS account. If the client is located on-premise or in a different VPC, AWS account, or AWS Region, this procedure also assumes that you've set up AWS Transit Gateway or a dedicated network connection using AWS Direct Connect or a private, secure tunnel using AWS Virtual Private Network. For more information, see Accessing data from outside the deployment VPC.

We recommend that you attach volumes to your Windows clients using the SMB protocol.

Prerequisites

To access an ONTAP storage volume using a Microsoft Windows client, you have to satisfy the following prerequisites:

- The SVM of the volume you are attaching must be joined to your organization's Active Directory, or you must be using a workgroup. For more information on joining your SVM to an Active Directory, see Managing FSx for ONTAP storage virtual machines. For more information on using workgroups, see Setting up an SMB server in a workgroup.
- The volume you are attaching should have a security style setting of NTFS. For more information, see Volume security style.

To mount a volume on a Windows client using SMB and Active Directory

1. Open the Amazon EC2 console at https://console.aws.amazon.com/ec2/.
2. Create or select an Amazon EC2 instance running Microsoft Windows that is in the same VPC as the file system, and joined to the same Microsoft Active Directory as the volume's SVM.

   For more information on launching an instance, see Step 1: Launch an instance in the *Amazon EC2 User Guide*.

   For more information about joining an SVM to an Active Directory, see Managing FSx for ONTAP storage virtual machines.

3. Connect to your Amazon EC2 Windows instance. For more information, see Connecting to your Windows instance in the *Amazon EC2 User Guide*.
4. Open a command prompt.
5. Run the following command. Replace the following:

   - Replace `Z:` with any available drive letter.
   - Replace `DNS_NAME` with the DNS name or the IP address of the SMB endpoint for the volume's SVM.
   - Replace `SHARE_NAME` with the name of an SMB share. `C$` is the default SMB share at the root of the SVM's namespace, but you shouldn't mount it as that exposes storage to the root volume and can cause security and service disruption. You should provide an SMB share name to mount instead of `C$`. For more information about creating SMB shares, see Managing SMB shares.

   ```
   net use Z: \\DNS_NAME\SHARE_NAME
   ```

   The following example uses sample values.

   ```
   net use Z: \\corp.example.com\group_share
   ```

   You can also use the IP address of the SVM instead of its DNS name. We recommend using the DNS name to mount clients to second-generation file systems because it helps ensure that your clients are balanced across your file system's high-availability (HA) pairs.

   ```
   net use Z: \\198.51.100.5\group_share
   ```

Mounting volumes on macOS clients

This section describes how to access data in your FSx for ONTAP file system with clients running the macOS operating system. Review the following requirements, regardless of the type of client you are using.

This procedure assumes that the client and the file system are located in the same VPC and AWS account. If the client is located on-premise, or in a different VPC, AWS account or AWS Region, you've set up AWS Transit Gateway or a dedicated network connection using AWS Direct Connect

or a private, secure tunnel using AWS Virtual Private Network. For more information, see Accessing data from outside the deployment VPC.

We recommend that you attach volumes to your Mac clients using the SMB protocol.

To mount an ONTAP volume on a macOS client using SMB

1. Open the Amazon EC2 console at https://console.aws.amazon.com/ec2/.
2. Create or select an Amazon EC2 Mac instance running the macOS that is in the same VPC as the file system.

   For more information on launching an instance, see Step 1: Launch an instance in the *Amazon EC2 User Guide*.
3. Connect to your Amazon EC2 Mac instance. For more information, see Connect to your Linux instance in the *Amazon EC2 User Guide*.
4. Open a terminal on your EC2 instance using secure shell (SSH), and log in with the appropriate credentials.
5. Create a directory on the EC2 instance for mounting the volume as follows:

   ```
   sudo mkdir /fsx
   ```
6. Mount the volume using the following command.

   ```
   sudo mount -t smbfs filesystem-dns-name:/smb-share-name mount-point
   ```

   The following example uses sample values.

   ```
   sudo mount -t smbfs svm-01234567890abcde2.fs-01234567890abcde5.fsx.us-
   east-1.amazonaws.com:/C$ /fsx
   ```

   You can also use the SVM's IP address instead of its DNS name. We recommend using the DNS name to mount clients to second-generation file systems because it helps ensure that your clients are balanced across your file system's high-availability (HA) pairs.

   ```
   sudo mount -t smbfs 198.51.100.10:/C$ /fsx
   ```

   C$ is the default SMB share that you can mount to see the root of the SVM's namespace. If you've created any Server Message Block (SMB) shares in your SVM, provide the SMB share

names instead of C$. For more information about creating SMB shares, see Managing SMB shares.

To mount an ONTAP volume on a macOS client using NFS

1. Open the Amazon EC2 console at https://console.aws.amazon.com/ec2/.
2. Create or select an Amazon EC2 instance running Amazon Linux 2 that is in the same VPC as the file system.

   For more information on launching an EC2 Linux instance, see Step 1: Launch an instance in the *Amazon EC2 User Guide*.
3. Connect to your Amazon EC2 Linux instance. For more information, see Connect to your Linux instance in the *Amazon EC2 User Guide*.
4. Mount your FSx for ONTAP volume on the Linux EC2 instance by either using a user-data script during instance launch, or by running the following commands:

   ```
   sudo mount -t nfs -o nfsvers=NFS_version svm-dns-name:/volume-junction-path /mount-point
   ```

   The following example uses sample values.

   ```
   sudo mount -t nfs -o nfsvers=4.1
    svm-01234567890abdef0.fs-01234567890abcdef1.fsx.us-east-1.amazonaws.com:/vol1 /
   fsxontap
   ```

   You can also use the SVM's IP address instead of its DNS name. We recommend using the DNS name to mount clients to second-generation file systems because it helps ensure that your clients are balanced across your file system's HA pairs.

   ```
   sudo mount -t nfs -o nfsvers=4.1 198.51.100.1:/vol1 /fsxontap
   ```
5. Mount the volume to the directory you just created using the following command.

   ```
   sudo mount -t nfs svm-dns-name:/volume-junction-path /fsx
   ```

   The following example uses sample values.

```
sudo mount -t nfs svm-01234567890abdef0.fs-01234567890abcdef1.fsx.us-
east-1.amazonaws.com:/vol1 /fsx
```

You can also use the SVM's IP address instead of its DNS name. We recommend using the DNS name to mount clients to second-generation file systems because it helps ensure that your clients are balanced across your file system's high-availability (HA) pairs.

```
sudo mount -t nfs 198.51.100.1:/vol1 /fsx
```

Provisioning iSCSI for Linux

FSx for ONTAP supports the iSCSI protocol. You need to provision iSCSI on both the Linux client and your file system in order to use the iSCSI protocol to transport data between clients and your file system. The iSCSI protocol is available on all file systems that have 6 or fewer high-availability (HA) pairs.

There are three main steps to process of configuring iSCSI on your Amazon FSx for NetApp ONTAP, which are covered in the following procedures:

1. Install and configure the iSCSI client on the Linux host.
2. Configure iSCSI on the file system's SVM.
   - Create an iSCSI initiator group.
   - Map the initiator group to the LUN.
3. Mount an iSCSI LUN on the Linux client.

Before you begin

Before you begin the process of configuring your file system for iSCSI, you need to have the following items completed.

- Create an FSx for ONTAP file system. For more information, see Creating file systems.
- Create an iSCSI LUN on the file system. For more information, see Creating an iSCSI LUN.
- Create an EC2 instance running the Amazon Linux 2 Amazon Machine Image (AMI) in the same VPC as the file system. This is the Linux host on which you will configure iSCSI and access your file data.

Beyond the scope of these procedures, if the host is located in another VPC, you can use VPC peering or AWS Transit Gateway to grant other VPCs access to the volume's iSCSI endpoints. For more information, see Accessing data from outside the deployment VPC.

- Configure the Linux host's VPC security groups to allow inbound and outbound traffic as described in File System Access Control with Amazon VPC.
- Obtain the credentials for the ONTAP user with `fsxadmin` privileges that you will use to access the ONTAP CLI. For more information, see ONTAP roles and users.
- The Linux host that you will configure for iSCSI and use to access the FSx for ONTAP file system are located in the same VPC and AWS account.
- We recommend that the EC2 instance be in the same availability zone as your file system's preferred subnet, as shown in the following graphic.



If your EC2 instance runs a different Linux AMI than Amazon Linux 2, some of the utilities used in these procedures and examples might already be installed, and you might use different commands to install required packages. Aside from installing packages, the commands used in this section are valid for other EC2 Linux AMIs.

Topics

- Install and configure iSCSI on the Linux host
- Configure iSCSI on the FSx for ONTAP file system
- Mount an iSCSI LUN on your Linux client

Install and configure iSCSI on the Linux host

To install the iSCSI client

1. Confirm that `iscsi-initiator-utils` and `device-mapper-multipath` are installed on your Linux device. Connect to your Linux instance using an SSH client. For more information, see Connect to your Linux instance using SSH.
2. Install `multipath` and the iSCSI client using the following command. Installing `multipath` is required if you want to automatically failover between your file servers.

```
~$ sudo yum install -y device-mapper-multipath iscsi-initiator-utils
```

3. To facilitate a faster response when automatically failing over between file servers when using `multipath`, set the replacement timeout value in the `/etc/iscsi/iscsid.conf` file to a value of 5 instead of using the default value of `120`.

```
~$ sudo sed -i 's/node.session.timeo.replacement_timeout = .*/
node.session.timeo.replacement_timeout = 5/' /etc/iscsi/iscsid.conf; sudo cat /etc/
iscsi/iscsid.conf | grep node.session.timeo.replacement_timeout
```

4. Start the iSCSI service.

```
~$ sudo service iscsid start
```

   Note that depending on your Linux version, you may have to use this command instead:

```
~$ sudo systemctl start iscsid
```

5. Confirm that the service is running using the following command.

```
~$ sudo systemctl status iscsid.service
```

   The system responds with the following output:

```
iscsid.service - Open-iSCSI
    Loaded: loaded (/usr/lib/systemd/system/iscsid.service; disabled; vendor
 preset: disabled)
    Active: active (running) since Fri 2021-09-02 00:00:00 UTC; 1min ago
    Docs: man:iscsid(8)
    man:iscsiadm(8)
    Process: 14658 ExecStart=/usr/sbin/iscsid (code=exited, status=0/SUCCESS)
    Main PID: 14660 (iscsid)
    CGroup: /system.slice/iscsid.service
    ##14659 /usr/sbin/iscsid
    ##14660 /usr/sbin/iscsid
```

To configure iSCSI on your Linux client

1. To enable your clients to automatically failover between your file servers, you must configure multipath. Use the following command:

   ```
   ~$ sudo mpathconf --enable --with_multipathd y
   ```

2. Determine the initiator name of your Linux host using the following command. The location of the initiator name depends on your iSCSI utility. If you are using `iscsi-initiator-utils`, the initiator name is located in the file `/etc/iscsi/initiatorname.iscsi`.

   ```
   ~$ sudo cat /etc/iscsi/initiatorname.iscsi
   ```

   The system responds with the initiator name.

   ```
   InitiatorName=iqn.1994-05.com.redhat:abcdef12345
   ```

Configure iSCSI on the FSx for ONTAP file system

1. Connect to the NetApp ONTAP CLI on the FSx for ONTAP file system on which you created the iSCSI LUN using the following command. For more information, see Using the NetApp ONTAP CLI.

   ```
   ~$ ssh fsxadmin@your_management_endpoint_ip
   ```

2. Create the initiator group (`igroup`) using the NetApp ONTAP CLI **lun igroup create** command. An initiator group maps to iSCSI LUNs and control which initiators (clients) have access to LUNs. Replace `host_initiator_name` with the initiator name from your Linux host that you retrieved in the previous procedure.

```
::> lun igroup create -vserver svm_name -igroup igroup_name -
initiator host_initiator_name -protocol iscsi -ostype linux
```

   If you want to make the LUNs mapped to this igroup available to multiple hosts, you can specify multiple initiator names separated with a comma. For more information, see lun igroup create in the *NetApp ONTAP Documentation Center*.

3. Confirm that the `igroup` exists using the **lun igroup show** command:

```
::> lun igroup show
```

   The system responds with the following output:

```
Vserver   Igroup       Protocol OS Type  Initiators
--------- ------------ -------- -------- ------------------------------------
svm_name  igroup_name  iscsi    linux    iqn.1994-05.com.redhat:abcdef12345
```

4. This step assumes that you have already created an iSCSI LUN. If you have not, see Creating an iSCSI LUN for step-by-step instructions to do so.

   Create a mapping from the LUN you created to the igroup you created, using the **lun mapping create**, specifying the following attributes:

   - *svm_name* – The name of the storage virtual machine providing the iSCSI target. The host uses this value to reach the LUN.
   - *vol_name* – The name of the volume hosting the LUN.
   - *lun_name* – The name that you assigned to the LUN.
   - *igroup_name* – The name of the initiator group.
   - *lun_id* – The LUN ID integer is specific to the mapping, not to the LUN itself. This is used by the initiators in the igroup as the Logical Unit Number use this value for the initiator when accessing the storage.

```
::> lun mapping create -vserver svm_name -path /vol/vol_name/lun_name -
igroup igroup_name -lun-id lun_id
```

5. Use the lun show -path command to confirm the LUN is created, online, and mapped.

```
::> lun show -path /vol/vol_name/lun_name -fields state,mapped,serial-hex
```

The system responds with the following output:

```
 Vserver    Path                            serial-hex               state    mapped
 --------- ------------------------------- ------------------------ --------
 --------
 svm_name  /vol/vol_name/lun_name          6c5742314e5d52766e796150 online   mapped
```

Save the `serial_hex` value (in this example, it is `6c5742314e5d52766e796150`), you will use it in a later step to create a friendly name for the block device.

6. Use the network interface show -vserver command to retrieve the addresses of the `iscsi_1` and `iscsi_2` interfaces for the SVM in which you've created your iSCSI LUN.

```
::> network interface show -vserver svm_name
```

The system responds with the following output:

```
            Logical               Status     Network            Current
        Current Is
Vserver     Interface             Admin/Oper Address/Mask       Node
        Port    Home
----------- ----------            ---------- ------------------ -------------
        ------- ----
svm_name
            iscsi_1               up/up      172.31.0.143/20
 FSxId0123456789abcdef8-01  e0e     true
            iscsi_2               up/up      172.31.21.81/20
 FSxId0123456789abcdef8-02  e0e     true
            nfs_smb_management_1
                                  up/up      198.19.250.177/20
 FSxId0123456789abcdef8-01  e0e     true
3 entries were displayed.
```

In this example, the IP address of `iscsi_1` is `172.31.0.143` and `iscsi_2` is `172.31.21.81`.

Mount an iSCSI LUN on your Linux client

The process of mounting the iSCSI LUN on your Linux client involves three steps:

1. Discovering the target iSCSI nodes
2. Partitioning the iSCSI LUN
3. Mounting the iSCSI LUN on the client

These are covered in the following procedures.

To discover the target iSCSI nodes

1. On your Linux client, use the following command to discover the target iSCSI nodes using `iscsi_1`'s IP address *`iscsi_1_IP`*.

   ```
   ~$ sudo iscsiadm --mode discovery --op update --type sendtargets --
   portal iscsi_1_IP
   ```

   ```
   172.31.0.143:3260,1029
    iqn.1992-08.com.netapp:sn.9cfa2c41207a11ecac390182c38bc256:vs.3
   172.31.21.81:3260,1028
    iqn.1992-08.com.netapp:sn.9cfa2c41207a11ecac390182c38bc256:vs.3
   ```

   In this example, `iqn.1992-08.com.netapp:sn.9cfa2c41207a11ecac390182c38bc256:vs.3` corresponds to the `target_initiator` for the iSCSI LUN in the preferred availability zone.

2. (Optional) To drive higher throughput than the Amazon EC2 single client maximum of 5 Gbps (~625 MBps) to your iSCSI LUN, follow the procedures described in Amazon EC2 instance network bandwidth in the Amazon Elastic Compute Cloud User Guide for Linux Instances to establish additional sessions for greater throughput.

   The following command establishes 8 sessions per initiator per ONTAP node in each availability zone, enabling the client to drive up to 40 Gbps (5,000 MBps) of aggregate throughput to the iSCSI LUN.

```
~$ sudo iscsiadm --mode node -T target_initiator --op update -n
 node.session.nr_sessions -v 8
```

3. Log into the target initiators. Your iSCSI LUNs are presented as available disks.

```
~$ sudo iscsiadm --mode node -T target_initiator --login
```

```
Logging in to [iface: default, target:
 iqn.1992-08.com.netapp:sn.9cfa2c41207a11ecac390182c38bc256:vs.3, portal:
 172.31.14.66,3260] (multiple)
Login to [iface: default, target:
 iqn.1992-08.com.netapp:sn.9cfa2c41207a11ecac390182c38bc256:vs.3, portal:
 172.31.14.66,3260] successful.
```

The output above is truncated; you should see one `Logging in` and one `Login successful` response for each session on each file server. In the case of 4 sessions per node, there will be 8 `Logging in` and 8 `Login successful` responses.

4. Use the following command to verify that `dm-multipath` has identified and merged the iSCSI sessions by showing a single LUN with multiple policies. There should be an equal number of devices that are listed as `active` and those listed as `enabled`.

```
~$ sudo multipath -ll
```

In the output, the disk name is formatted as `dm-xyz`, where `xyz` is an integer. If there are no other multipath disks, this value is `dm-0`.

```
3600a09806c5742314e5d52766e79614f dm-xyz NETAPP  ,LUN C-Mode
size=10G features='4 queue_if_no_path pg_init_retries 50 retain_attached_hw_handle'
 hwhandler='0' wp=rw
|-+- policy='service-time 0' prio=50 status=active
| |- 0:0:0:1 sda     8:0   active ready running
| |- 1:0:0:1 sdc     8:32  active ready running
| |- 3:0:0:1 sdg     8:96  active ready running
| `- 4:0:0:1 sdh     8:112 active ready running
`-+- policy='service-time 0' prio=10 status=enabled
  |- 2:0:0:1 sdb     8:16  active ready running
  |- 7:0:0:1 sdf     8:80  active ready running
  |- 6:0:0:1 sde     8:64  active ready running
```

```
  `- 5:0:0:1 sdd     8:48  active ready running
```

Your block device is now connected to your Linux client. It is located under the path `/dev/`*`dm-xyz`*. You should not use this path for administrative purposes; instead, use the symbolic link that is under the path `/dev/mapper/`*`wwid`*, where *`wwid`* is a unique identifier for your LUN that is consistent across devices. In the next step, you'll provide a friendly name for the *`wwid`* so you can distinguish it from other multipathed disks.

To assign the block device a friendly name

1. To provide your device a friendly name, create an alias in the `/etc/multipath.conf` file. To do this, add the following entry to the file using your preferred text editor, replacing the following placeholders:

   - Replace `serial_hex` with the value the you saved in the Configure iSCSI on the FSx for ONTAP file system procedure.
   - Add the prefix `3600a0980` to the `serial_hex` value as shown in the example. This is a unique preamble for the NetApp ONTAP distribution that Amazon FSx for NetApp ONTAP uses.
   - Replace `device_name` with the friendly name you want to use for your device.

   ```
   multipaths {
       multipath {
           wwid 3600a0980serial_hex
           alias device_name
       }
   }
   ```

   As an alternative, you can copy and save the following script as a bash file, such as `multipath_alias.sh`. You can run the script with sudo privileges, replacing *`serial_hex`* (without the 3600a0980 prefix) and *`device_name`* with your respective serial number and the desired friendly name. This script searches for an uncommented `multipaths` section in the `/etc/multipath.conf` file. If one exists, it appends a `multipath` entry to that section; otherwise, it will create a new `multipaths` section with a `multipath` entry for your block device.

   ```
   #!/bin/bash
   ```

```
SN=serial_hex
ALIAS=device_name
CONF=/etc/multipath.conf
grep -q '^multipaths {' $CONF
UNCOMMENTED=$?
if [ $UNCOMMENTED -eq 0 ]
then
        sed -i '/^multipaths {/a\\tmultipath {\n\t\twwid 3600a0980'"${SN}"'\n\t
\talias '"${ALIAS}"'\n\t}\n' $CONF
else
        printf "multipaths {\n\tmultipath {\n\t\twwid 3600a0980$SN\n\t\talias
 $ALIAS\n\t}\n}" >> $CONF
fi
```

2. Restart the `multipathd` service for the changes to `/etc/multipathd.conf` take effect.

```
~$ systemctl restart multipathd.service
```

To partition the LUN

The next step is to format and partition your LUN using `fdisk`.

1. Use the following command to verify that the path to your `device_name` is present.

```
~$ ls /dev/mapper/device_name
```

```
/dev/device_name
```

2. Partition the disk using `fdisk`. You'll enter an interactive prompt. Enter the options in the order shown. You can make multiple partitions by using a value smaller than the last sector (`20971519` in this example).

> **Note**
>
> The `Last sector` value will vary depending on the size of your iSCSI LUN (10GB in this example).

```
~$ sudo fdisk /dev/mapper/device_name
```

The `fsdisk` interactive prompt starts.

```
Welcome to fdisk (util-linux 2.30.2).

Changes will remain in memory only, until you decide to write them.
Be careful before using the write command.

Device does not contain a recognized partition table.
Created a new DOS disklabel with disk identifier 0x66595cb0.

Command (m for help): n
Partition type
   p primary (0 primary, 0 extended, 4 free)
   e extended (container for logical partitions)
Select (default p): p
Partition number (1-4, default 1): 1
First sector (2048-20971519, default 2048): 2048
Last sector, +sectors or +size{K,M,G,T,P} (2048-20971519, default
 20971519): 20971519

Created a new partition 1 of type 'Linux' and of size 512 B.
Command (m for help): w
The partition table has been altered.
Calling ioctl() to re-read partition table.
Syncing disks.
```

After entering `w`, your new partition `/dev/mapper/`*`partition_name`* becomes available. The *`partition_name`* has the format *`<device_name><partition_number>`*. 1 was used as the partition number used in the `fdisk` command in the previous step.

3. Create your file system using `/dev/mapper/`*`partition_name`* as the path.

```
~$ sudo mkfs.ext4 /dev/mapper/partition_name
```

The system responds with the following output:

```
mke2fs 1.42.9 (28-Dec-2013)
Discarding device blocks: done
Filesystem label=
OS type: Linux
Block size=4096 (log=2)
```

```
Fragment size=4096 (log=2)
Stride=0 blocks, Stripe width=16 blocks
655360 inodes, 2621184 blocks
131059 blocks (5.00%) reserved for the super user
First data block=0
Maximum filesystem blocks=2151677952
80 block groups
32768 blocks per group, 32768 fragments per group
8192 inodes per group
Superblock backups stored on blocks:
     32768, 98304, 163840, 229376, 294912, 819200, 884736, 1605632
Allocating group tables: done
Writing inode tables: done
Creating journal (32768 blocks): done
Writing superblocks and filesystem accounting information: done
```

To mount the LUN on the Linux client

1. Create a directory *directory_path* as the mount point for your file system.

```
~$ sudo mkdir /directory_path/mount_point
```

2. Mount the file system using the following command.

```
~$ sudo mount -t ext4 /dev/mapper/partition_name /directory_path/mount_point
```

3. (Optional) If you want to give a specific user ownership of the mount directory, replace *username* with the owner's username.

```
~$ sudo chown username:username /directory_path/mount_point
```

4. (Optional) Verify that you can read from and write data to the file system.

```
~$ echo "Hello world!" > /directory_path/mount_point/HelloWorld.txt
~$ cat directory_path/HelloWorld.txt
Hello world!
```

You have successfully created and mounted an iSCSI LUN on your Linux client.

Provisioning iSCSI for Windows

FSx for ONTAP supports the iSCSI protocol. You need to provision iSCSI on both the Windows client and the SVM and volume in order to use the iSCSI protocol to transport data between clients and your file system. The iSCSI protocol is available on all file systems that have 6 or fewer high-availability (HA) pairs.

The examples presented in these procedures show how to provision the iSCSI protocol on the client and FSx for ONTAP file system, and use the following set up:

- The iSCSI LUN that is getting mounted to a Windows host is already created. For more information, see Creating an iSCSI LUN.
- The Microsoft Windows host that is mounting the iSCSI LUN is an Amazon EC2 instance running a Microsoft Windows Server 2019 Amazon Machine Image (AMI). It has VPC security groups configured to allow inbound and outbound traffic as described in File System Access Control with Amazon VPC.

  You may be using a different Microsoft Windows AMI in your set up.
- The client and the file system are located in the same VPC and AWS account. If the client is located in another VPC, you can use VPC peering or AWS Transit Gateway to grant other VPCs access to the iSCSI endpoints. For more information, see Accessing data from outside the deployment VPC.

  We recommend that the EC2 instance be in the same availability zone as your file system's preferred subnet, as shown in the following graphic.



Topics

- Configure iSCSI on the Windows client
- Configure iSCSI on the FSx for ONTAP file system
- Mount an iSCSI LUN on the Windows client
- Validating your iSCSI configuration
- Verify Host Utilities registry settings

Configure iSCSI on the Windows client

1. Use Windows Remote Desktop to connect to the Windows client on which you want to mount the iSCSI LUN. For more information, see Connect to your Windows instance using RDP in the *Amazon Elastic Compute Cloud User Guide*.
2. Open a Windows PowerShell as an Administrator. Use the following commands to enable iSCSI on your Windows instance and configure the iSCSI service to start automatically.

```
PS C:\> Start-Service MSiSCSI
PS C:\> Set-Service -Name msiscsi -StartupType Automatic
```

3. Retrieve the initiator name of your Windows instance. You'll use this value in configuring iSCSI on your FSx for ONTAP file system using the NetApp ONTAP CLI.

   ```
   PS C:\> (Get-InitiatorPort).NodeAddress
   ```

   The system responds with the initiator port:

   ```
   iqn.1991-05.com.microsoft:ec2amaz-abc123d
   ```

4. Install `Multipath-IO` (MPIO) on your Windows instance so that the client automatically fails over between your file servers. Use the following command:

   ```
   PS C:\> Install-WindowsFeature Multipath-IO
   ```

5. Install NetApp Windows Host Utilities. The Host Utilities installer sets the recommended Windows registry values, such as disk and MPIO timeouts. These values help your Windows host handle ONTAP storage system behavior correctly during failover events.

   a. Download the Host Utilities installer from the NetApp Support downloads page. You must have a NetApp Support account to download the installer. To create an account, see Signing up for a NetApp account. Choose the version compatible with your Windows Server version.

   b. Run the installer and choose **Multipath I/O** when prompted for the supported feature.

6. Restart your Windows instance after you install `Multipath-IO` and the Host Utilities. After the restart, you can confirm that the installer applied the recommended Host Utilities registry values. For more information, see Verify Host Utilities registry settings. Keep your Windows instance open to perform the iSCSI LUN mount steps later in this guide.

Configure iSCSI on the FSx for ONTAP file system

1. To access the ONTAP CLI, establish an SSH session on the management port of the Amazon FSx for NetApp ONTAP file system or SVM by running the following command. Replace *`management_endpoint_ip`* with the IP address of the file system's management port.

   ```
   [~]$ ssh fsxadmin@management_endpoint_ip
   ```

   For more information, see Managing file systems with the ONTAP CLI.

2. Using the ONTAP CLI **lun igroup create**, create the initiator group, or `igroup`. An initiator group maps to iSCSI LUNs and controls which initiators (clients) have access to LUNs. Replace `host_initiator_name` with the initiator name from your Windows host that you retrieved in the previous procedure.

```
::> lun igroup create -vserver svm_name -igroup igroup_name -
initiator host_initiator_name -protocol iscsi -ostype windows
```

   Io make the LUNs mapped to this `igroup` available to multiple hosts, you can specify multiple comma-separated initiator names using `lun igroup create` ONTAP CLI command.

3. Confirm that the `igroup` was created successfully using the lun igroup show ONTAP CLI command:

```
::> lun igroup show
```

   The system responds with the following output:

```
Vserver    Igroup        Protocol OS Type  Initiators
---------  ------------  -------- -------- ------------------------------------
svm_name   igroup_name   iscsi    windows  iqn.1994-05.com.windows:abcdef12345
```

   With the `igroup` created, you are ready to create LUNs and map them to the `igroup`.

4. This step assumes that you have already created an iSCSI LUN. If you have not, see Creating an iSCSI LUN for step-by-step instructions to do so.

   Create a LUN mapping from the LUN to your new `igroup`.

```
::> lun mapping create -vserver svm_name -path /vol/vol_name/lun_name -
igroup igroup_name -lun-id lun_id
```

5. Confirm that the LUN is created, online, and mapped with the following command:

```
::> lun show -path /vol/vol_name/lun_name
Vserver     Path                            State   Mapped   Type     Size
---------   ------------------------------- ------- -------- -------- --------
svm_name    /vol/vol_name/lun_name          online  mapped   windows  10GB
```

   You are now ready to add the iSCSI target on your Windows instance.

6. Retrieve the IP addresses of the `iscsi_1` and `iscsi_2` interfaces for your SVM using the following command:

```
::> network interface show -vserver svm_name
```

```
            Logical    Status     Network            Current       Current Is
Vserver     Interface  Admin/Oper Address/Mask       Node          Port    Home
----------- ---------- ---------- ------------------ ------------- ------- ----
svm_name
            iscsi_1    up/up      172.31.0.143/20    FSxId0123456789abcdef8-01
                                                                   e0e     true
            iscsi_2    up/up      172.31.21.81/20    FSxId0123456789abcdef8-02
                                                                   e0e     true
            nfs_smb_management_1
                       up/up      198.19.250.177/20  FSxId0123456789abcdef8-01
                                                                   e0e     true
3 entries were displayed.
```

In this example, the IP address of `iscsi_1` is `172.31.0.143` and `iscsi_2` is `172.31.21.81`.

Mount an iSCSI LUN on the Windows client

1. On your Windows instance, open a PowerShell terminal as an Administrator.
2. You will create a `.ps1` script that does the following:

   - Connects to each of your file system's iSCSI interfaces.
   - Adds and configures MPIO for iSCSI.
   - Establishes 8 sessions for each iSCSI connection, which enables the client to drive up to 40 Gbps (5,000 MBps) of aggregate throughput to the iSCSI LUN. Having 8 sessions ensures a single client can drive the full 4,000 MBps throughput capacity for the highest-level FSx for ONTAP throughput capacity. You can optionally change the number of sessions to a higher or lower number of sessions (each session provides up to 625 MBps of throughput) by modifying the `RecommendedConnectionCount` variable. For more information, see Amazon EC2 instance network bandwidth in the *Amazon Elastic Compute Cloud User Guide for Windows Instances*.

   Copy the following set of commands into a file to create the `.ps1` script.

- Replace `iscsi_1` and `iscsi_2` with the IP addresses you retrieved in the previous step.
- Replace `ec2_ip` with the IP address of your Windows instance.

```
Write-Host "Starting iSCSI connection setup..."
     $TargetPortalAddresses = @("iscsi_1","iscsi_2"); $LocaliSCSIAddress = "ec2_ip"
     $RecommendedConnectionCount = 8

     Foreach ($TargetPortalAddress in $TargetPortalAddresses) {
         New-IscsiTargetPortal -TargetPortalAddress $TargetPortalAddress -
TargetPortalPortNumber 3260 -InitiatorPortalAddress $LocaliSCSIAddress
     }

     New-MSDSMSupportedHW -VendorId MSFT2005 -ProductId iSCSIBusType_0x9

     $currentMPIOSettings = Get-MPIOSetting
     if ($currentMPIOSettings.PathVerificationState -ne 'Enabled') {
         Write-Host "Setting MPIO path verification state to Enabled"; Set-
MPIOSetting -NewPathVerificationState Enabled
     } else { Write-Host "MPIO path verification state already Enabled" }

     $portalConnectionCounts = @{}
     foreach ($TargetPortalAddress in $TargetPortalAddresses)
 { $portalConnectionCounts[$TargetPortalAddress] = 0 }

     $sessions = Get-IscsiSession
     if ($sessions) {
         foreach ($session in $sessions) {
             if ($session.IsConnected) {
                 $targetPortal = (Get-IscsiTargetPortal -iSCSISession
 $session).TargetPortalAddress
                 if ($portalConnectionCounts.ContainsKey($targetPortal))
 { $portalConnectionCounts[$targetPortal]++ }
             }
         }
     }

     foreach ($TargetPortalAddress in $TargetPortalAddresses) {
         $existingCount = $portalConnectionCounts[$TargetPortalAddress];
 $remainingConnections = $RecommendedConnectionCount - $existingCount
```

```
        Write-Host "Portal $TargetPortalAddress has $existingCount
 existing connections, $remainingConnections remaining (max recommended:
 $RecommendedConnectionCount)"
        if ($remainingConnections -gt 0) {
            Write-Host "Creating $remainingConnections connections for portal
 $TargetPortalAddress"
            1..$remainingConnections | ForEach-Object {
                Get-IscsiTarget | Connect-IscsiTarget -IsMultipathEnabled $true -
TargetPortalAddress $TargetPortalAddress -InitiatorPortalAddress $LocaliSCSIAddress
 -IsPersistent $true
            }
        } else { Write-Host "Maximum connections (8) reached for portal
 $TargetPortalAddress" }
    }

    Set-MSDSMGlobalDefaultLoadBalancePolicy -Policy RR
```

3. Launch the Windows Disk Management application. Open the Windows Run dialog box, and enter `diskmgmt.msc` and press **Enter**. The Disk Management application opens.



4. Locate the unallocated disk This is the iSCSI LUN. In the example, Disk 1 is the iSCSI disk. It is offline.



Bring the volume online by placing the cursor over **Disk 1** and right-click then choose **Online**.

> **Note**
>
> You can modify the storage area network (SAN) policy so that new volumes are automatically brought online. For more information, see SAN policies in the *Microsoft Windows Server Command Reference*.

5. To initialize the disk, place the cursor over **Disk 1** right-click, and choose **Initialize**. The Initialize dialog appears. Choose **OK** initialize the disk.
6. Format the disk as you would normally. After formatting is complete, the iSCSI drive appears as a usable drive on the Windows client.

Validating your iSCSI configuration

We have provided a script to check that your iSCSI setup is properly configured. The script examines parameters such as session count, node distribution, and Multipath I/O (MPIO) status. The following task explains how to install and use the script.

To validate your iSCSI configuration

1. Open a Windows PowerShell window.
2. Download the script using the following command.

```
PS C:\> Invoke-WebRequest "https://docs.aws.amazon.com/fsx/latest/ONTAPGuide/
samples/CheckiSCSI.zip" -OutFile "CheckiSCSI.zip"
```

3. Expand the zip file using the following command.

```
PS C:\> Expand-Archive -Path ".\CheckiSCSI.zip" -DestinationPath "./"
```

4. Run the script using the following command.

```
PS C:\> ./CheckiSCSI.ps1
```

5. Review the output to understand your configuration's current state. The following example demonstrates a successful iSCSI configuration.

```
PS C:\> ./CheckiSCSI.ps1

This script checks the iSCSI configuration on the local instance.
It will provide information about the number of connected sessions, connected file
 servers, and MPIO status.

MPIO is installed on this server.

MPIO Load Balance Policy is set to Round Robin (RR).
Initiator: 'iqn.1991-05.com.microsoft:ec2amaz-d2cebnb'
to Target: 'iqn.1992-08.com.netapp:sn.13266b10e61411ee8bc0c76ad263d613:vs.3'
has 16 total sessions (16 active, 0 non-active)
spread across 2 node(s).
MPIO: Yes
```

Verify Host Utilities registry settings

After you install NetApp Windows Host Utilities, you can verify that the installer applied the recommended registry values. For more information about the expected registry settings for your Host Utilities version, see Windows Host Utilities configuration settings in the NetApp documentation.

For example, use the following PowerShell command to check the MPIO parameters:

```
PS C:\> Get-ItemProperty "HKLM:\SYSTEM\CurrentControlSet\Services\mpio\Parameters"
```

Provisioning NVMe/TCP for Linux

FSx for ONTAP supports the Non-Volatile Memory Express over TCP (NVMe/TCP) block storage protocol. With NVMe/TCP, you use the ONTAP CLI to provision namespaces and subsystems and then map the namespaces to subsystems, similar to the way LUNs are provisioned and mapped to initiator groups (igroups) for iSCSI. The NVMe/TCP protocol is available on second-generation file systems that have 6 or fewer high-availability (HA) pairs.

> **Note**
>
> FSx for ONTAP file systems use an SVM's iSCSI endpoints for both iSCSI and NVMe/TCP block storage protocols.

There are three main steps to process of configuring NVMe/TCP on your Amazon FSx for NetApp ONTAP, which are covered in the following procedures:

1. Install and configure the NVMe client on the Linux host.
2. Configure NVMe on the file system's SVM.
   - Create an NVMe namespace.
   - Create an NVMe subsystem.
   - Map the namespace to the subsystem.
   - Add the client NQN to the subsystem.
3. Mount an NVMe device on the Linux client.

Before you begin

Before you begin the process of configuring your file system for NVMe/TCP, you need to have the following items completed.

- Create an FSx for ONTAP file system. For more information, see Creating file systems.
- Create an EC2 instance running Red Hat Enterprise Linux (RHEL) 9.3 in the same VPC as the file system. This is the Linux host on which you will configure NVMe and access your file data using NVMe/TCP for Linux.

Beyond the scope of these procedures, if the host is located in another VPC, you can use VPC peering or AWS Transit Gateway to grant other VPCs access to the volume's iSCSI endpoints. For more information, see Accessing data from outside the deployment VPC.

- Configure the Linux host's VPC security groups to allow inbound and outbound traffic as described in File System Access Control with Amazon VPC.
- Obtain the credentials for the ONTAP user with `fsxadmin` privileges that you will use to access the ONTAP CLI. For more information, see ONTAP roles and users.
- The Linux host that you will configure for NVMe and use to access the FSx for ONTAP file system are located in the same VPC and AWS account.
- We recommend that the EC2 instance be in the same availability zone as your file system's preferred subnet.

If your EC2 instance runs a different Linux AMI than RHEL 9.3, some of the utilities used in these procedures and examples might already be installed, and you might use different commands to install required packages. Aside from installing packages, the commands used in this section are valid for other EC2 Linux AMIs.

Topics

- Install and configure NVMe on the Linux host
- Configure NVMe on the FSx for ONTAP file system
- Mount an NVMe device on your Linux client

Install and configure NVMe on the Linux host

To install the NVMe client

1. Connect to your Linux instance using an SSH client. For more information, see Connect to your Linux instance from Linux or macOS using SSH.
2. Install `nvme-cli` using the following command:

```
~$ sudo yum install -y nvme-cli
```

3. Load the `nvme-tcp` module onto the host:

```
$ sudo modprobe nvme-tcp
```

4. Get the Linux host's NVMe Qualified Name (NQN) by using the following command:

```
$ cat /etc/nvme/hostnqn
nqn.2014-08.org.nvmexpress:uuid:9ed5b327-b9fc-4cf5-97b3-1b5d986345d1
```

Record the response for use in a later step.

Configure NVMe on the FSx for ONTAP file system

To configure NVMe on the file system

Connect to the NetApp ONTAP CLI on the FSx for ONTAP file system on which you plan to create the NVMe device(s).

1. To access the ONTAP CLI, establish an SSH session on the management port of the Amazon FSx for NetApp ONTAP file system or SVM by running the following command. Replace *management_endpoint_ip* with the IP address of the file system's management port.

```
[~]$ ssh fsxadmin@management_endpoint_ip
```

For more information, see Managing file systems with the ONTAP CLI.

2. Create a new volume on the SVM that you are using to access the NVMe interface.

```
::> vol create -vserver fsx -volume nvme_vol1 -aggregate aggr1 -size 1t
     [Job 597] Job succeeded: Successful
```

3. Create the NVMe namespace ns_1 using the vserver nvme namespace create NetApp ONTAP CLI command. A namespace maps to initiators (clients) and controls which initiators (clients) have access to NVMe devices.

```
::> vserver nvme namespace create -vserver fsx -path /vol/nvme_vol1/ns_1 -size 100g
 -ostype linux
Created a namespace of size 100GB (107374182400).
```

4. Create the NVMe subsystem using the vserver nvme subsystem create NetApp ONTAP CLI command.

```
~$ vserver nvme subsystem create -vserver fsx -subsystem sub_1 -ostype linux
```

5. Map the namespace to the subsystem you just created.

```
::> vserver nvme subsystem map add -vserver fsx -subsystem sub_1 -path /vol/
nvme_vol1/ns_1
```

6. Add the client to the subsystem using the NQN that you retrieved previously.

```
::> vserver nvme subsystem host add -subsystem sub_1 -host-nqn
 nqn.2014-08.org.nvmexpress:uuid:ec21b083-1860-d690-1f29-44528e4f4e0e -vserver fsx
```

If you want to make the devices mapped to this subsystem available to multiple hosts, you can specify multiple initiator names in a comma separated list. For more information, see vserver nvme subsystem host add in the NetApp ONTAP Docs.

7. Confirm that the namespace exists using the **vserver nvme namespace show** command:

```
::> vserver nvme namespace show -vserver fsx -instance
Vserver Name: fsx
            Namespace Path: /vol/nvme_vol1/ns_1
                      Size: 100GB
                 Size Used: 90.59GB
                   OS Type: linux
                   Comment:
                Block Size: 4KB
                     State: online
         Space Reservation: false
Space Reservations Honored: false
              Is Read Only: false
             Creation Time: 5/20/2024 17:03:08
            Namespace UUID: c51793c0-8840-4a77-903a-c869186e74e3
                  Vdisk ID: 80d42c6f00000000187cca9
      Restore Inaccessible: false
   Inconsistent Filesystem: false
       Inconsistent Blocks: false
                   NVFail: false
Node Hosting the Namespace: FsxId062e9bb6e05143fcb-01
               Volume Name: nvme_vol1
                Qtree Name:
          Mapped Subsystem: sub_1
            Subsystem UUID: db526ec7-16ca-11ef-a612-d320bd5b74a9
```

```
              Namespace ID: 00000001h
              ANA Group ID: 00000001h
              Vserver UUID: 656d410a-1460-11ef-a612-d320bd5b74a9
                Vserver ID: 3
               Volume MSID: 2161388655
               Volume DSID: 1029
                 Aggregate: aggr1
            Aggregate UUID: cfa8e6ee-145f-11ef-a612-d320bd5b74a9
 Namespace Container State: online
       Autodelete Enabled: false
         Application UUID: -
              Application: -
  Has Metadata Provisioned: true

1 entries were displayed.
```

8. Use the **network interface show -vserver** command to retrieve the addresses of the block storage interfaces for the SVM in which you've created your NVMe devices.

```
::> network interface show -vserver svm_name -data-protocol nvme-tcp
            Logical               Status     Network            Current
        Current Is
Vserver     Interface             Admin/Oper Address/Mask       Node
        Port    Home
----------- ----------            ---------- ------------------ -------------
        ------- ----
svm_name
            iscsi_1               up/up      172.31.16.19/20
 FSxId0123456789abcdef8-01  e0e     true
            iscsi_2               up/up      172.31.26.134/20
 FSxId0123456789abcdef8-02  e0e     true
2 entries were displayed.
```

> **Note**
>
> The `iscsi_1` LIF is used for both iSCSI and NVMe/TCP.

In this example, the IP address of iscsi_1 is 172.31.16.19 and iscsi_2 is 172.31.26.134.

Mount an NVMe device on your Linux client

The process of mounting the NVMe device on your Linux client involves three steps:

1. Discovering the NVMe nodes
2. Partitioning the NVMe device
3. Mounting the NVMe device on the client

These are covered in the following procedures.

To discover the target NVMe nodes

1. On your Linux client, use the following command to discover the target NVMe nodes. Replace *iscsi_1_IP* with `iscsi_1`'s IP address, and *client_IP* the client's IP address.

   > **Note**
   >
   > `iscsi_1` and `iscsi_2` LIFs are used for both iSCSI and NVMe storage.

   ```
   ~$ sudo nvme discover -t tcp -w client_IP -a iscsi_1_IP
   ```

   ```
   Discovery Log Number of Records 4, Generation counter 11
   =====Discovery Log Entry 0======
   trtype:  tcp
   adrfam:  ipv4
   subtype: current discovery subsystem
   treq:    not specified
   portid:  0
   trsvcid: 8009
   subnqn:  nqn.1992-08.com.netapp:sn.656d410a146011efa612d320bd5b74a9:discovery
   traddr:  172.31.26.134
   eflags:  explicit discovery connections, duplicate discovery information
   sectype: none
   =====Discovery Log Entry 1======
   trtype:  tcp
   adrfam:  ipv4
   subtype: current discovery subsystem
   treq:    not specified
   ```

```
portid:  1
trsvcid: 8009
subnqn:  nqn.1992-08.com.netapp:sn.656d410a146011efa612d320bd5b74a9:discovery
traddr:  172.31.16.19
eflags:  explicit discovery connections, duplicate discovery information
sectype: none
```

2. (Optional) To drive higher throughput than the Amazon EC2 single client maximum of 5 Gbps (~625 MBps) to your file NVMe device, follow the procedures described in Amazon EC2 instance network bandwidth in the Amazon Elastic Compute Cloud User Guide for Linux Instances to establish additional sessions.
3. Log into the target initiators with a controller loss timeout of at least 1800 seconds, again using `iscsi_1`'s IP address for *`iscsi_1_IP`* and the client's IP address for *`client_IP`*. Your NVMe devices are presented as available disks.

```
~$ sudo nvme connect-all -t tcp -w client_IP -a iscsi_1 -l 1800
```

4. Use the following command to verify that the NVMe stack has identified and merged the multiple sessions and configured multipathing. The command returns `Y` if the configuration was successful.

```
~$ cat /sys/module/nvme_core/parameters/multipath
Y
```

5. Use the following commands to verify that the NVMe-oF setting `model` is set to `NetApp ONTAP Controller` and the load balancing `iopolicy` is set to `round-robin` for the respective ONTAP namespaces to distribute the I/O on all available paths

```
~$ cat /sys/class/nvme-subsystem/nvme-subsys*/model
Amazon Elastic Block Store
NetApp ONTAP Controller
~$ cat /sys/class/nvme-subsystem/nvme-subsys*/iopolicy
numa
round-robin
```

6. Use the following command to verify that the namespaces are created and correctly discovered on the host:

```
~$ sudo nvme list
```

```
Node                  Generic               SN                   Model
                        Namespace  Usage                        Format           FW
 Rev
--------------------- --------------------- --------------------
 ------------------------------------- ---------- -------------------------
 ---------------- --------
/dev/nvme0n1          /dev/ng0n1            vol05955547c003f0580 Amazon Elastic
 Block Store               0x1         25.77  GB /  25.77  GB    512   B +  0 B
 1.0
/dev/nvme2n1          /dev/ng2n1            lWB12JWY/XLKAAAAAAAC NetApp ONTAP
 Controller                0x1        107.37  GB / 107.37  GB      4 KiB +  0 B
 FFFFFFFF
```

The new device in the output is /dev/nvme2n1. This naming scheme may differ depending on your Linux installation.

7. Verify that the controller state of each path is live and has the correct Asymmetric Namespace Access (ANA) multipathing status:

```
~$ nvme list-subsys /dev/nvme2n1
nvme-subsys2 -
 NQN=nqn.1992-08.com.netapp:sn.656d410a146011efa612d320bd5b74a9:subsystem.rhel
               hostnqn=nqn.2014-08.org.nvmexpress:uuid:ec2a70bf-3ab2-6cb0-
f997-8730057ceb24
               iopolicy=round-robin
\
 +- nvme2 tcp
 traddr=172.31.26.134,trsvcid=4420,host_traddr=172.31.25.143,src_addr=172.31.25.143
 live non-optimized
 +- nvme3 tcp
 traddr=172.31.16.19,trsvcid=4420,host_traddr=172.31.25.143,src_addr=172.31.25.143
 live optimized
```

In this example, the NVMe stack has automatically discovered your file system's alternate LIF, iscsi_2, 172.31.26.134.

8. Verify that the NetApp plug-in displays the correct values for each ONTAP namespace device:

```
~$ sudo nvme netapp ontapdevices -o column
Device           Vserver                   Namespace Path
           NSID UUID                                   Size
```

```
---------------- -------------------------
 ------------------------------------------------ ----
 ------------------------------------ ---------
/dev/nvme2n1     fsx                         /vol/nvme_vol1/ns_1
           1    0441c609-3db1-4b0b-aa83-790d0d448ece   107.37GB
```

To partition the device

1. Use the following command to verify that the path to your device_name nvme2n1 is present.

```
~$ ls /dev/mapper/nvme2n1
/dev/nvme2n1
```

2. Partition the disk using `fdisk`. You'll enter an interactive prompt. Enter the options in the order shown. You can make multiple partitions by using a value smaller than the last sector (20971519 in this example).

> **Note**
>
> The `Last sector` value will vary depending on the size of your NVMe device (100 GiB in this example).

```
~$ sudo fdisk /dev/mapper/nvme2n1
```

The `fsdisk` interactive prompt starts.

```
Welcome to fdisk (util-linux 2.37.4).
Changes will remain in memory only, until you decide to write them.
Be careful before using the write command.

Device does not contain a recognized partition table.
Created a new DOS disklabel with disk identifier 0x66595cb0.

Command (m for help): n
Partition type
   p primary (0 primary, 0 extended, 4 free)
   e extended (container for logical partitions)
Select (default p): p
Partition number (1-4, default 1): 1
```

```
First sector (256-26214399, default 256):
Last sector, +sectors or +size{K,M,G,T,P} (256-26214399, default
 26214399): 20971519

Created a new partition 1 of type 'Linux' and of size 100 GiB.
Command (m for help): w
The partition table has been altered.
Calling ioctl() to re-read partition table.
Syncing disks.
```

After entering `w`, your new partition `/dev/nvme2n1` becomes available. The *`partition_name`* has the format *`<device_name><partition_number>`*. 1 was used as the partition number in the `fdisk` command in the previous step.

3. Create your file system using `/dev/nvme2n1` as the path.

```
~$ sudo mkfs.ext4 /dev/nvme2n1
```

The system responds with the following output:

```
mke2fs 1.46.5 (30-Dec-2021)
Found a dos partition table in /dev/nvme2n1
Proceed anyway? (y,N) y
Creating filesystem with 26214400 4k blocks and 6553600 inodes
Filesystem UUID: 372fb2fd-ae0e-4e74-ac06-3eb3eabd55fb
Superblock backups stored on blocks:
    32768, 98304, 163840, 229376, 294912, 819200, 884736, 1605632, 2654208,
    4096000, 7962624, 11239424, 20480000, 23887872

Allocating group tables: done
Writing inode tables: done
Creating journal (131072 blocks): done
Writing superblocks and filesystem accounting information: done
```

To mount the NVMe device on the Linux client

1. Create a directory *`directory_path`* as the mount point for your file system on the Linux instance.

```
~$ sudo mkdir /directory_path/mount_point
```

2. Mount the file system using the following command.

```
~$ sudo mount -t ext4 /dev/nvme2n1 /directory_path/mount_point
```

3. (Optional) If you want to give a specific user ownership of the mount directory, replace *username* with the owner's username.

```
~$ sudo chown username:username /directory_path/mount_point
```

4. (Optional) Verify that you can read from and write data to the file system.

```
~$ echo "Hello world!" > /directory_path/mount_point/HelloWorld.txt
~$ cat directory_path/HelloWorld.txt
Hello world!
```

You have successfully created and mounted an NVMe device on your Linux client.

Accessing your data via Amazon S3 access points

You can also use S3 access points to access file data stored on Amazon FSx file systems as if it were in S3, allowing you to use it with applications and services that work with S3 without application changes or moving data out of file storage. Amazon S3 access points are S3 endpoints that attach to either S3 buckets or FSx for ONTAP and FSx for OpenZFS volumes. Amazon S3 access points simplify managing data access for any application or AWS service that works with S3. With S3 access points, customers with shared datasets, including data lakes, media archives, and user-generated content, can easily control and scale data access for hundreds of applications, teams, or individuals by creating individualized access points with names and permissions customized for each.

S3 access points attached to Amazon FSx for NetApp ONTAP volumes support read and write access to your file data using S3 object operations (for example, `GetObject`, `PutObject`, and `ListObjectsV2`) against an Amazon S3 endpoint.

Each S3 access point attached to an FSx for ONTAP file system has an AWS Identity and Access Management (IAM) access point policy and an associated UNIX or Windows file system user that is used to authorize all requests made through the access point. For each request, S3 first evaluates all the relevant policies, including those on the user, access point, S3 VPC Endpoint, and service control policies, to authorize the request. Once the request is authorized by S3, the request is

then authorized by the file system, which evaluates whether the file system user associated with the S3 access point has permission to access to the data on the file system. You can configure an access point to accept requests only from a virtual private cloud (VPC) to restrict Amazon S3 data access to a private network. Amazon S3 enforces Block public access by default for all access points attached to an FSx for ONTAP volume, and you cannot modify or disable this setting.

You use the Amazon FSx console, CLI, and API to create an S3 access point and attach it to an FSx for ONTAP volume. The access point allows you to access your file data using the S3 API, though your data continues to reside on your FSx for ONTAP file system and you can continue using the NFS and SMB protocols to access your data alongside the S3 API.

Amazon S3 access points for FSx for ONTAP file systems deliver latency in the tens of milliseconds range, consistent with S3 bucket access. The throughput and requests per second you can drive to an Amazon FSx file system via the S3 API depends on the file system's provisioned throughput. For more information about file system performance capabilities, see Amazon FSx for NetApp ONTAP performance

Topics

- AWS Regions with Amazon S3 access points for FSx for ONTAP
- Access points naming rules, restrictions, and limitations
- Referencing access points with ARNs, access point aliases, or virtual-hosted-style URIs
- Access point compatibility
- Managing access point access
- Creating an access point
- Configuring network access for Amazon S3 access points
- Managing Amazon S3 access points
- Using access points
- Using access points with AWS services
- Troubleshooting S3 access point issues

AWS Regions with Amazon S3 access points for FSx for ONTAP

Amazon S3 access points for FSx for ONTAP are supported in the following AWS Regions: Africa (Cape Town), Asia Pacific (Hong Kong, Hyderabad, Jakarta, Melbourne, Mumbai, Osaka, Seoul,

Singapore, Sydney, Tokyo), Canada (Central), Canada West (Calgary), Europe (Frankfurt, Ireland, London, Milan, Paris, Spain, Stockholm, Zurich), Israel (Tel Aviv), Middle East (Bahrain, UAE), South America (São Paulo), US East (N. Virginia, Ohio), and US West (N. California, Oregon).

Access points naming rules, restrictions, and limitations

When creating an S3 access point you choose a name for it. The following topics provide information about S3 access point naming rules and restrictions and limitations.

Topics

- Access points naming rules
- Access points restrictions and limitations

Access points naming rules

When you create an S3 access point you choose its name. Access point names do not need to be unique across AWS accounts or AWS Regions. The same AWS account may create access points with the same name in different AWS Regions or two different AWS accounts may use the same access point name. However, within a single AWS Region an AWS account may not have two identically named access points.

S3 access point names can't end with the suffix `-ext-s3alias`, which is reserved for access point alias. For a complete list of access point naming rules, see Naming rules for Amazon S3 access points in the *Amazon Simple Storage Service User Guide*.

Access points restrictions and limitations

S3 access points attached to FSx for ONTAP volumes have the following restrictions, which do not apply to access points attached to S3 buckets:

- You can only create an S3 access point in the same AWS Region as the FSx for ONTAP volume that you are attaching it to.
- The same AWS account must own the FSx for ONTAP file system and the S3 access point. You can only create S3 access points that are attached to FSx for ONTAP volumes that you own. You cannot create an S3 access point that is attached to a volume owned by another AWS account.
- You can only create and attach S3 access points to FSx for ONTAP file systems running NetApp ONTAP version 9.17.1 and later.

For a complete list of all access point restrictions and limitations, see Restrictions and limitations for access points in the *Amazon Simple Storage Service User Guide*.

Referencing access points with ARNs, access point aliases, or virtual-hosted-style URIs

After you create an access point attached to an FSx for ONTAP volume, you can access your data via the AWS CLI and S3 API, as well as S3-compatible AWS and third-party services and applications. When referring to an access point in an AWS service or application you can use the Amazon Resource Name (ARN), the access point alias, or virtual-hosted–style URI.

Topics

- Access point ARNs
- Access point aliases
- Virtual-hosted–style URI

Access point ARNs

Access points have Amazon Resource Names (ARNs). Access point ARNs are similar to S3 bucket ARNs, but they are explicitly typed and encode the access point's AWS Region and the AWS account ID of the access point's owner. For more information about ARNs, see Identify AWS resources with Amazon Resource Names (ARNs) in the *AWS Identity and Access Management User Guide*.

Access point ARNs have the following format:

```
arn:aws::s3:region:account-id:accesspoint/resource
```

`arn:aws:s3:us-west-2:777777777777:accesspoint/test` represents the access point named *`test`*, owned by account 777777777777 in the Region *`us-west-2`*.

ARNs for objects and files accessed through an access point use the following format:

```
arn:aws::s3:region:account-id:accesspoint/access-point-name/object/resource
```

`arn:aws:s3:us-west-2:111122223333:accesspoint/test/object/lions.jpg` represents the file *`lions.jpg`*, accessed through the access point named *`test`*, owned by account 111122223333 in the Region *`us-west-2`*.

For more information about access point ARNs, see Access point ARNs in the *Amazon Simple Storage Service User Guide*.

Access point aliases

When you create an access point, Amazon S3 automatically generates an access point alias that you can use anywhere you can use S3 bucket names to access data.

An access point alias cannot be changed. For an access point attached to an FSx for ONTAP volume, the access point alias consists of the following parts:

```
access point prefix-metadata-ext-s3alias
```

The following shows the ARN and access point alias for an S3 access point attached to an FSx for ONTAP volume, returned as part of the response to a `describe-s3-access-point-attachments` FSx CLI command. The access point in this example is named `my-ontap-ap`.

```
...
        "S3AccessPoint": {
            "ResourceARN": "arn:aws:s3:us-east-1:111122223333:accesspoint/my-ontap-ap",
            "Alias": "my-ontap-ap-aqfqprnstn7aefdfbarligizwgyfouse1a-ext-s3alias",
...
```

> **Note**
>
> The `-ext-s3alias` suffix is reserved for the aliases of S3 access points attached to an FSx for ONTAP volume, and can't be used for access point names.

You can use the access point alias instead of an Amazon S3 access point ARN in some S3 data plane operations. For a list of the supported operations, see Access point compatibility.

For a full set of access point alias limitations, see Access point alias limitations in the *Amazon Simple Storage Service User Guide*.

Virtual-hosted–style URI

Access points only support virtual-host-style addressing. In a virtual-hosted–style URI, the access point name, AWS account, and AWS Region is part of the domain name in the URL. To view the S3 URI for an access point attached to an FSx for ONTAP volume, in the access point details page

under **S3 access point details**, choose the access point name listed for **S3 access point**. This takes you to the access point details page in the Amazon S3 console. You can find the **S3 URI** under **Properties**.

For more information, see Virtual-hosted–style URI in the *Amazon Simple Storage Service User Guide*.

Access point compatibility

You can use access points to access data stored on an FSx for ONTAP volume using the following Amazon S3 APIs for data acccess. All the operations listed below can accept either access point ARNs or access point aliases.

The following table is a partial list of Amazon S3 operations and if they are compatible with access points. The table shows which operations are supported by access points using an FSx for ONTAP volume as a data source.

S3 operation	Access point attached to an FSx for ONTAP volume
`AbortMultipartUpload`	Supported
`CompleteMultipartUpload`	Supported
`CopyObject` (same-Region copies only)	Supported, if source and destination are within the same access point. The `x-amz-object-annotation-directive` header is not supported.
`CreateMultipartUpload`	Supported
`DeleteObject`	Supported
`DeleteObjects`	Supported
`DeleteObjectTagging`	Supported
`DeleteObjectAnnotation`	Not supported
`GetBucketAcl`	Not supported

S3 operation	Access point attached to an FSx for ONTAP volume
GetBucketCors	Not supported
GetBucketLocation	Supported
GetBucketNotificationConfiguration	Not supported
GetBucketPolicy	Not supported
GetObject	Supported
GetObjectAcl	Not supported
GetObjectAnnotation	Not supported
GetObjectAttributes	Supported
GetObjectLegalHold	Not supported
GetObjectRetention	Not supported
GetObjectTagging	Supported
HeadBucket	Supported
HeadObject	Supported
ListMultipartUploads	Supported
ListObjects	Supported
ListObjectsV2	Supported
ListObjectVersions	Not supported
ListObjectAnnotations	Not supported
ListParts	Supported

S3 operation	Access point attached to an FSx for ONTAP volume
Presign	Supported
PutObject	Supported
PutObjectAnnotation	Not supported
PutObjectAcl	Not supported
PutObjectLegalHold	Not supported
PutObjectRetention	Not supported
PutObjectTagging	Supported
RestoreObject	Not supported
UploadPart	Supported
UploadPartCopy (same-Region copies only)	Supported, if source and destination are within the same access point

Limitations to using Amazon S3 operations are the following:

- Maximum object size is 50 GiB for uploads, but you can download objects larger than that
- FSX_ONTAP is the only supported storage class
- SSE-FSX is the only supported server-side encryption mode
- The following Amazon S3 features are not supported: access control lists (ACLs) other than `bucket-owner-full-control`, Object Annotations, Requester Pays, Object Versioning, Object Lock, Object Lifecycle, Static Website Hosting (e.g., website redirection), multi-factor authentication (MFA), and conditional writes

For examples of using access points to perform data access operations on file data, see Using access points.

Object ETag

The entity tag is a hash of the object. The ETag reflects changes only to the contents of an object, not its metadata. The ETag is not an MD5 digest of the object data.

Object Checksums

You can use checksum values to verify the integrity of the data that you upload. When you upload data and specify a checksum algorithm, the AWS SDK uses your chosen checksum algorithm to compute a checksum value before data transmission. Amazon S3 then independently calculates a checksum of your data and validates it against the provided checksum value. Objects are accepted only after confirming data integrity was maintained during transit to Amazon S3. Unlike with checksums for objects in Amazon S3 General Purpose buckets, the checksum value is not stored in the FSx for NetApp ONTAP volume as object metadata and the object itself. This means that the checksum values are not returned in the response and are not used to verify object integrity on download.

Server-side encryption with Amazon FSx (SSE-FSX)

All Amazon FSx file systems have encryption configured by default and are encrypted at rest with keys managed using AWS Key Management Service. Data is automatically encrypted and decrypted on the file system as data is being written to and read from the file system. These processes are handled transparently by Amazon FSx.

Multipart upload

Multipart upload allows you to upload a single object as a set of parts. Each part is a contiguous portion of the object's data. You can upload these object parts independently, and in any order. Multipart upload has the following considerations when using S3 access points with FSx for ONTAP:

- The parts associated with in-progress multipart uploads (i.e. incomplete uploads) are not included in FSx for ONTAP volume backups.
- The used storage associated with in-progress multipart upload (i.e. incomplete upload) parts is not reflected in the destination volume's `StorageUsed` storage capacity CloudWatch metric but is reflected in the parent file system's `StorageUsed` storage capacity CloudWatch metric.
- Once a multipart upload operation is complete, the associated part metadata is no longer stored with the object. This means you cannot retrieve object part metdata using `GetObjectAttributes` or download a single part of an object by the part number of the object being read.

Access Control List (ACL)

Amazon S3 access control lists (ACLs) enable you to manage access to buckets and objects. S3 access points for FSx only support the `bucket-owner-full-control` ACL value. Using any other ACL value will result in a `InvalidArgument` exception.

Managing access point access

You can configure each S3 access point with distinct permissions and network controls that S3 applies for any request that is made using that access point. S3 access points support AWS Identity and Access Management (IAM) resource policies that you can use to control the use of the access point by resource, user, or other conditions. For an application or user to access files through an access point, both the access point and the underlying volume must permit the request. For more information, see IAM access point policies.

Amazon S3 access points for FSx for ONTAP use a dual-layer authorization model that combines AWS IAM permissions with file system-level permissions. This approach ensures that data access requests are properly authorized at both the AWS service level and the underlying file system level.

For an application or user to successfully access data through an access point, both the S3 access point policy and the underlying FSx for ONTAP volume must permit the request.

Topics

- File system user identity and authorization
- S3 API request authorization
- S3 Block Public Access
- IAM access point policies

File system user identity and authorization

When you create an S3 access point for an FSx for ONTAP volume, you specify a file system identity that will be used to authorize all file system requests made through that access point. This file system identity determines what level of access is granted to the underlying files and directories based on the file system's permission model. The file system user is a user account on the underlying Amazon FSx file system. If the file system user has *read-only* access, then only read requests made using the access point are authorized, and write requests are blocked. If the file system user has read-write access, then both read and write requests to the attached volume made using the access point are authorized.

The file system identity can be one of two types:

- **UNIX identity** – Use a UNIX identity (username) when accessing volumes with UNIX security style
- **Windows Identity** – Use a Windows identity (domain and username) when accessing volumes with NTFS security style.

When you specify a UNIX or Windows identity, all S3 API operations performed through the access point are authorized using that user's permissions on the file system.

The file system identity you associate with the access point determines the level of access to files and directories. For example, if you associate the access point with the root UNIX identity (UID 0), which typically has full file access permissions on the file system, then all file operations would be authorized. Conversely, if you associate the access point with a restricted user identity, file operations would be limited to what that user can access based on the file system's permission model.

You should use the UNIX file system identity type for volumes with UNIX security style and the Windows identity type for volumes with NTFS security style. This alignment ensures that the authorization model matches the volume's security configuration.

For UNIX security style volumes, the file system uses mode-bits or NFSv4 ACLs to control access. For NTFS security style volumes, the file system uses Windows ACLs to control access.

Important

Attaching an S3 access point to an FSx for ONTAP volume doesn't change the volume's behavior when the volume is accessed directly via NFS or SMB. All existing operations against the volume will continue to work as before. Restrictions that you include in an S3 access point policy apply only to requests made using the access point.

Note

An S3 access point can transition to the `MISCONFIGURED` state if the file system identity associated with the access point can no longer be resolved on the file system, or if the attached volume becomes offline or unmounted. While in this state, S3 requests made through the access point may fail. Amazon FSx periodically checks for these conditions and

automatically returns the access point to `AVAILABLE` when the issue is resolved. For more information, see S3 access point is in MISCONFIGURED state.

S3 API request authorization

When you make an S3 API request through an access point attached to an FSx for NetApp ONTAP volume, Amazon S3 evaluates the IAM permissions of the calling principal against the access point's IAM resource policy. The IAM principal caller must have the necessary permissions granted through their identity-based policies, and the access point's resource policy must also permit the requested action.

Amazon S3 evaluates all relevant policies—including user policies, the access point policy, VPC endpoint policies, and service control policies—to determine whether to authorize the request.

You can also configure an S3 access point to only accept requests from a specific virtual private cloud (VPC) to restrict data access. For more information, see Creating access points restricted to a virtual private cloud.

S3 Block Public Access

Amazon S3 access points attached to an FSx for ONTAP volume are automatically configured with block public access enabled, which you cannot change.

IAM access point policies

Amazon S3 access points support AWS Identity and Access Management (IAM) resource policies that allow you to control the use of the access point by resource, user, or other conditions. For an application or user to be able to access objects through an access point, both the access point and the underlying data source must permit the request.

The `s3:PutAccessPointPolicy` permission is required to create an optional access point policy.

After you attach an S3 access point to an Amazon FSx volume, all existing operations against the volume will continue to work as before. Restrictions that you include in an access point policy apply only to requests made through that access point. For more information, see Configuring IAM policies for using access points in the *Amazon Simple Storage Service User Guide*.

You can configure an access point policy when you create an access point attached to an FSx for ONTAP volume using the Amazon FSx console. To add, modify, or delete an access point policy on an existing S3 access point, you can use the S3 console, CLI, or API.

Creating an access point

You can create and manage S3 access point that attach to Amazon FSx volumes using the Amazon FSx console, CLI, API, and supported SDKs.

> **Note**
>
> Because you might want to publicize your S3 access point name so that other users can use the access point, avoid including sensitive information in the S3 access point name. Access point names are published in a publicly accessible database known as the Domain Name System (DNS). For more information about access point names, see Access points naming rules.

Required permissions

The following permissions are required to create an S3 access point attached to an Amazon FSx volume:

- `fsx:CreateAndAttachS3AccessPoint`
- `s3:CreateAccessPoint`
- `s3:GetAccessPoint`

The `s3:PutAccessPointPolicy` permission is required to create an optional Access Point policy using either the Amazon FSx or S3 console. For more information, see IAM access point policies.

To create an access point, see the following topics.

Topics

- Creating access points
- Creating access points restricted to a virtual private cloud

Creating access points

> **Important**
>
> To attach an S3 access point to an FSx for ONTAP volume, the volume must be mounted (have a junction path). See ONTAP documentation for more details.

The FSx for ONTAP volume must already exist in your account when creating an S3 access point for your volume.

To create the S3 access point attached to an FSx for ONTAP volume, you specify the following properties:

- The access point name. For information about access point naming rules, see Access points naming rules.
- The file system user identity to use for authorizing file access requests made using the access point. Specify either the UNIX or Windows the POSIX username that you want to include. For more information, see File system user identity and authorization.
- The access point's network configuration determines whether the access point is accessible from the internet or if access is restricted to a specific virtual private cloud (VPC). For more information, see Creating access points restricted to a virtual private cloud.

To create an S3 access point attached to an FSx volume (FSx console)

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. In the navigation bar on the top of the page, choose the AWS Region in which you want to create an access point. The access point must be created in the same Region as the associated volume.
3. In the left navigation pane, choose **Volumes**.
4. On the **Volumes** page, choose the FSx for ONTAP volume that you want to attach the access point to.
5. Display the **Create S3 access point** page by choosing **Create S3 access point** from the **Actions** menu.
6. For **Access point name**, enter the name for the access point. For more information about guidelines and restrictions for access point names, see Access points naming rules.

The **Data source details** are populated with the information of the volume you chose in Step 3.

7. The file system user identity is used by Amazon FSx for authenticating file access requests that are made using this access point. Be sure that the file system user you specify has the correct permissions on the FSx for ONTAP volume.

   For **File system user identity type**, select either UNIX or Windows.

8. For **Username** enter the user's username.

9. In the **Network configuration** panel you choose whether the access point is accessible from the Internet, or access is restricted to a specific virtual private cloud.

   For **Network origin**, choose **Internet** to make the access point accessible from the internet, or choose **Virtual private cloud (VPC)**, and enter the **VPC ID** that you want to limit access to the access point from.

   For more information about network origins for access points, see Creating access points restricted to a virtual private cloud.

10. (Optional) Under **Access Point Policy - *optional***, specify an optional access point policy. Be sure to resolve any policy warnings, errors, and suggestions. For more information about specifying an access point policy, see Configuring IAM policies for using access points in the *Amazon Simple Storage Service User Guide*.

11. Choose **Create access point** to review the access point attachment configuration.

To create an S3 access point attached to an FSx volume (CLI)

The following example command creates an access point named *my-ontap-ap* that is attached to the FSx for ONTAP volume *fsvol-0123456789abcdef9* in the account *111122223333*.

```
$ aws fsx create-and-attach-s3-access-point --name my-ontap-ap --type ONTAP --ontap-configuration \
   VolumeId=fsvol-0123456789abcdef9,FileSystemIdentity='{Type=UNIX,UnixUser={Name=ec2-user}}' \
   --s3-access-point VpcConfiguration='{VpcId=vpc-0123467},Policy=access-point-policy-json
```

For a successful request, the system responds by returning the new S3 access point attachment.

```
$ {
  {
     "S3AccessPointAttachment": {
        "CreationTime": 1728935791.8,
        "Lifecycle": "CREATING",
        "LifecycleTransitionReason": {
            "Message": "string"
        },
        "Name": "my-ontap-ap",
        "OntapConfiguration": {
            "VolumeId": "fsvol-0123456789abcdef9",
            "FileSystemIdentity": {
                "Type": "UNIX",
                "UnixUser": {
                    "Name": "ec2-user"
                }
            }
        },
        "S3AccessPoint": {
            "ResourceARN": "arn:aws:s3:us-east-1:111122223333:accesspoint/my-ontap-ap",
            "Alias": "my-ontap-ap-aqfqprnstn7aefdfbarligizwgyfouse1a-ext-s3alias",
            "VpcConfiguration": {
                "VpcId": "vpc-0123467"
        }
     }
  }
}
```

Note

After an S3 access point is created and in the `AVAILABLE` state, it can transition to `MISCONFIGURED` if the file system identity associated with the access point can no longer be resolved on the file system, or if the attached volume becomes offline or unmounted. Amazon FSx periodically checks for these conditions and automatically returns the access point to `AVAILABLE` when the underlying issue is resolved. While in the `MISCONFIGURED` state, S3 requests made through the access point may fail. For more information, see S3 access point is in MISCONFIGURED state.

Creating access points restricted to a virtual private cloud

When you create an access point, you can choose to make the access point accessible from the internet, or you can specify that all requests made through that access point must originate from a specific Amazon Virtual Private Cloud. An access point that's accessible from the internet is said to have a network origin of `Internet`. It can be used from anywhere on the internet, subject to any other access restrictions in place for the access point, underlying bucket or Amazon FSx volume, and related resources, such as the requested objects. An access point that's only accessible from a specified Amazon VPC has a network origin of `VPC`, and Amazon S3 rejects any request made to the access point that doesn't originate from that Amazon VPC.

> **Important**
>
> You can only specify an access point's network origin when you create the access point. After you create the access point, you can't change its network origin.

To restrict an access point to Amazon VPC-only access, you include the `VpcConfiguration` parameter with the request to create the access point. In the `VpcConfiguration` parameter, you specify the Amazon VPC ID that you want to be able to use the access point. If a request is made through the access point, the request must originate from the Amazon VPC or Amazon S3 will reject it.

You can retrieve an access point's network origin using the AWS CLI, AWS SDKs, or REST APIs. If an access point has a Amazon VPC configuration specified, its network origin is `VPC`. Otherwise, the access point's network origin is `Internet`.

Example

Example: Create an access point that's restricted to Amazon VPC access

The following example creates an access point named `example-vpc-ap` for bucket `amzn-s3-demo-bucket` in account `123456789012` that allows access only from the `vpc-1a2b3c` Amazon VPC. The example then verifies that the new access point has a network origin of `VPC`.

AWS CLI

```
$ aws fsx create-and-attach-s3-access-point --name example-vpc-ap --type ONTAP --
ontap-configuration \
```

```
 VolumeId=fsvol-0123456789abcdef9,FileSystemIdentity='{Type=UNIX,UnixUser={Name=ec2-
user}}' \
   --s3-access-point VpcConfiguration='{VpcId=vpc-id},Policy=access-point-policy-
json
```

```
$ {
  {
     "S3AccessPointAttachment": {
        "Lifecycle": "CREATING",
        "CreationTime": 1728935791.8,
        "Name": "example-vpc-ap",
        "OntapConfiguration": {
            "VolumeId": "fsvol-0123456789abcdef9",
            "FileSystemIdentity": {
                "Type": "UNIX",
                "UnixUser": {
                    "Name": "my-unix-user"
                }
            }
        },
        "S3AccessPoint": {
            "ResourceARN": "arn:aws:s3:us-east-1:111122223333:accesspoint/example-
vpc-ap",
            "Alias": "access-point-abcdef0123456789ab12jj77xy51zacd4-ext-s3alias",
            "VpcConfiguration": {
                "VpcId": "vpc-1a2b3c"
            }
        }
     }
  }
```

To use an access point with a Amazon VPC, you must modify the access policy for your Amazon VPC endpoint. Amazon VPC endpoints allow traffic to flow from your Amazon VPC to Amazon S3. They have access control policies that control how resources within the Amazon VPC are allowed to interact with Amazon S3. Requests from your Amazon VPC to Amazon S3 only succeed through an access point if the Amazon VPC endpoint policy grants access to both the access point and the underlying bucket.

Note

To make resources accessible only within a Amazon VPC, make sure to create a private hosted zone for your Amazon VPC endpoint. To use a private hosted zone, modify your Amazon VPC settings so that the Amazon VPC network attributes `enableDnsHostnames` and `enableDnsSupport` are set to `true`.

The following example policy statement configures an Amazon VPC endpoint to allow calls to `GetObject` and an access point named `example-vpc-ap`.

JSON

```
{
    "Version":"2012-10-17",
    "Statement": [
    {
        "Principal": "*",
        "Action": [
            "s3:GetObject"
        ],
        "Effect": "Allow",
        "Resource": [
            "arn:aws:s3:us-east-1:123456789012:accesspoint/example-vpc-ap/object/
*"
        ]
    }]
}
```

Note

The `Resource` declaration in this example uses an Amazon Resource Name (ARN) to specify the access point.

For more information about Amazon VPC endpoint policies, see Gateway endpoints for Amazon S3 in the *Amazon VPC User Guide*.

Configuring network access for Amazon S3 access points

When you create an Amazon S3 access point for an FSx for ONTAP volume, you configure how the access point can be reached over the network and who is authorized to use it. This section helps you choose the right network and access control configuration for your environment.

This section covers the network and IAM authorization layers — specifically, the access point's network origin, VPC endpoints, access point policies, VPC endpoint policies, IAM identity policies, and service control policies. For information about file system-level authorization (UNIX and Windows user permissions), see File system user identity and authorization.

Topics

- How Amazon S3 evaluates access point requests
- Choosing a network origin
- How VPC origin enforcement works
- Using VPC endpoints with Amazon S3 access points
- Access point policies
- Example scenarios
- Troubleshooting network access issues

How Amazon S3 evaluates access point requests

When a request is made through an Amazon S3 access point attached to an FSx for ONTAP volume, the request must be authorized by all of the following layers:

- **Network origin check** — If the access point has a VPC network origin, the request must arrive through a VPC endpoint in the bound VPC. If not, the request is denied before any policy evaluation occurs.
- **VPC endpoint policy** — If the request traverses a VPC endpoint, the endpoint's policy must allow the action on the access point resource.
- **access point policy** — The access point's IAM resource policy is evaluated. For same-account access, either the access point policy or the caller's identity policy can grant access. For cross-account access, both must allow.
- **IAM identity policy** — The requesting principal's identity-based policy is evaluated against the access point resource.

- **Service control policies (SCPs)** — If the account is part of an AWS Organizations organization, any applicable SCPs must allow the action.

The network origin check occurs before policy evaluation. The remaining layers are evaluated together as part of the standard IAM authorization decision — an explicit Deny in **any** layer overrides Allow statements in other layers.

Choosing a network origin

When you create an Amazon S3 access point, you choose a **network origin** that determines how the access point can be reached. You cannot change the network origin after creation.

Internet origin

An access point with an internet network origin is similar to how S3 buckets are accessed by default. **All requests still require valid IAM credentials and authorization** — internet origin does not mean public or anonymous access. Amazon S3 enforces Block Public Access on all access points attached to FSx for ONTAP volumes, and you cannot disable this setting.

With internet origin, authenticated requests can come from anywhere — VPCs, on-premises networks, other AWS accounts, or the public internet. You control which authenticated callers are allowed using the access point policy and IAM identity policies.

With internet origin, you control access using the access point policy and IAM identity policies. For same-account callers, use explicit Deny statements in the access point policy to restrict access — an Allow-only policy is not sufficient because the caller's IAM identity policy can independently grant access. For cross-account callers, the access point policy must explicitly Allow the request, so omitting an Allow is sufficient to block access.

VPC origin

An access point with a VPC network origin is bound to a specific VPC and effectively behaves as an explicit Deny policy statement that rejects any request where `aws:SourceVpc` does not match the bound VPC. Because an explicit Deny always overrides any Allow, even a completely permissive access point policy or IAM identity policy cannot grant access to requests from outside the bound VPC.

Callers outside the bound VPC can still access the access point if their traffic is routed through a VPC endpoint in the bound VPC — for example, via VPC peering or Transit Gateway to an Amazon S3 Interface endpoint deployed in the bound VPC.

Key differences

	Internet origin	VPC origin
Network enforcement	None — access controlled by policy only	Effectively an explicit Deny for requests not arriving through a VPC endpoint in the bound VPC
Multi-VPC access	Supported via policy conditions	Supported if callers route through an Interface endpoint in the bound VPC (via VPC peering or Transit Gateway)
Change access scope	Update the policy	Must recreate the access point to change the bound VPC
VPC endpoint required	Only if using `aws:SourceVpc` conditions	Yes — requests must traverse an endpoint in the bound VPC

How VPC origin enforcement works

When an access point has a VPC network origin, it effectively behaves as if there is an explicit Deny policy statement that denies all requests where `aws:SourceVpc` does not equal the VPC ID specified in the access point's `VpcConfiguration`. This Deny applies to all principals, all Amazon S3 actions, and all resources within the access point.

Because this is an explicit Deny, it overrides any Allow statements — whether in the access point policy, the caller's IAM identity policy, or any other policy.

In practice, this means:

- Requests must arrive through a VPC endpoint (Gateway or Interface) deployed in the bound VPC, because only VPC endpoints populate the `aws:SourceVpc` attribute on the request.
- Requests from other VPCs are denied, because their VPC endpoints populate `aws:SourceVpc` with a different VPC ID.
- Requests from the internet are denied, because `aws:SourceVpc` is not present on the request.

This is also why the error message for denied requests says "explicit deny in a resource-based policy."

> **Important**
>
> You cannot change an access point's network origin after creation. If you need to change from VPC origin to internet origin (or vice versa), you must delete the access point and create a new one.

VPC origin vs. internet origin with an explicit Deny

A VPC-origin access point and an internet-origin access point with a manually written `StringNotEquals aws:SourceVpc` Deny achieve a similar result — both deny requests not from the specified VPC. The key difference is:

- **VPC origin**: The Deny is built into the access point's VPC configuration. You cannot accidentally remove it or misconfigure it.
- **Internet origin with Deny**: You write and manage the Deny yourself. This gives you more flexibility (for example, allowing multiple VPCs) but also more responsibility — if the Deny is missing or misconfigured, the restriction is not enforced.

Using VPC endpoints with Amazon S3 access points

Amazon S3 access points work with both types of VPC endpoints for Amazon S3. The endpoint type you need depends on where your callers are located.

Gateway endpoints

Gateway endpoints are free and route-table based. When you create a Gateway endpoint, a route is added to the specified route tables that directs Amazon S3 traffic through the endpoint. This route applies only to traffic **originating within the VPC**.

Use Gateway endpoints for:

- Amazon EC2 instances, Lambda functions, Amazon ECS tasks, and other compute resources **within the VPC**

Gateway endpoints **do not** route traffic that enters the VPC from:

- On-premises networks via VPN or Direct Connect
- Peered VPCs
- Transit Gateway connections

For more information, see Gateway endpoints for Amazon S3 in the *Amazon VPC User Guide*.

Interface endpoints

Interface endpoints create an elastic network interface (ENI) with a private IP address in your subnet. Traffic must be explicitly directed to the endpoint's DNS name or private IP.

Use Interface endpoints for:

- On-premises callers accessing Amazon S3 via VPN or Direct Connect
- Cross-account callers accessing Amazon S3 via VPC peering
- Any scenario where traffic enters the VPC from outside

When using an Interface endpoint, callers must either:

- Use the `--endpoint-url` parameter pointing to the Interface endpoint's DNS name, or
- Configure DNS to resolve Amazon S3 endpoints to the Interface endpoint's private IP (using Route 53 Resolver or on-premises DNS forwarding)

Interface endpoints have per-hour and per-GB charges. For more information, see AWS PrivateLink pricing.

Using both endpoint types together

You can deploy both a Gateway endpoint and an Interface endpoint in the same VPC. This configuration is useful when you have both in-VPC callers and on-premises callers:

- **Gateway endpoint**: Handles in-VPC traffic (free, transparent)
- **Interface endpoint**: Handles on-premises traffic entering via VPN or Direct Connect (requires DNS configuration or `--endpoint-url`)

Both endpoint types populate the `aws:SourceVpc` attribute with the VPC ID, so both satisfy the VPC origin Deny condition.

VPC endpoint policies

VPC endpoint policies control which Amazon S3 resources can be accessed through the endpoint. By default, a VPC endpoint allows all Amazon S3 actions on all resources. You can scope the endpoint policy to allow only specific access points:

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Effect": "Allow",
            "Principal": "*",
            "Action": "s3:*",
            "Resource": [
                "arn:aws:s3:us-east-1:123456789012:accesspoint/my-access-point",
                "arn:aws:s3:us-east-1:123456789012:accesspoint/my-access-point/object/
*"
            ]
        }
    ]
}
```

Access point policies

Amazon S3 access points support AWS Identity and Access Management (IAM) resource policies that allow you to control the use of the access point by resource, user, or other conditions. For cross-account access, both the access point policy and the caller's IAM identity policy must permit the request. For same-account access, either the access point policy or the caller's IAM identity policy can independently grant access — to restrict same-account callers, use explicit Deny statements in the access point policy. If the request traverses a VPC endpoint, the VPC endpoint policy must also permit the request.

For more information about access point policies, see Configuring IAM policies for using access points in the *Amazon Simple Storage Service User Guide*.

Condition keys for network-based access control

IAM provides global condition keys that you can use in access point policies to control access based on network properties of the request. These condition keys are included in the request context only under specific circumstances, as described in the following table.

Condition key	Availability	Description
`aws:SourceVpc`	Included in the request context only if the requester uses a VPC endpoint to make the request.	Checks whether the request travels through the VPC that the VPC endpoint is attached to. Use this key to allow access to only a specific VPC.
`aws:SourceVpce`	Included in the request context only if the requester uses a VPC endpoint to make the request.	The ID of the VPC endpoint through which the request was made.
`aws:VpcSourceIp`	Included in the request context only if the request is made using a VPC endpoint.	Compares the IP address from which a request was made with the IP address that you specify in the policy. Matches only if the request originates from the specified IP address and goes through a VPC endpoint.
`aws:SourceIp`	Included in the request context only if the request does **not** traverse a VPC endpoint.	The public IP address of the caller. Not available for requests made through a VPC endpoint.

Important

`aws:SourceIp` and `aws:VpcSourceIp` are mutually exclusive. When a request traverses a VPC endpoint, `aws:SourceIp` is not available — use `aws:VpcSourceIp` instead. When a request comes from the internet (no VPC endpoint), `aws:VpcSourceIp` is not available — use `aws:SourceIp` instead.

Important

The condition key `aws:VpcSourceIp` is case-sensitive.

For more information about IAM global condition keys, see AWS global condition context keys in the *IAM User Guide*.

Example scenarios

The following example scenarios show common configurations for Amazon S3 access points attached to FSx for ONTAP volumes. Each scenario includes the recommended network origin, VPC endpoint type, and access point policy.

Single VPC access

Use case: Amazon EC2 instances, Lambda functions, or Amazon ECS tasks within a single VPC access the access point. No external access needed.

With VPC network origin:



The VPC origin configuration effectively denies requests where `aws:SourceVpc` does not match the bound VPC. Requests from other VPCs, the internet, or on-premises networks are denied. You can use either a Gateway or Interface Amazon S3 VPC endpoint.

Example access point policy (VPC origin): With VPC origin, the network restriction is built in. The access point policy only needs to grant the desired permissions.

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Effect": "Allow",
```

```
            "Principal": {"AWS": "arn:aws:iam::123456789012:role/my-app-role"},
            "Action": [
                "s3:GetObject",
                "s3:PutObject",
                "s3:ListBucket"
            ],
            "Resource": [
                "arn:aws:s3:us-east-1:123456789012:accesspoint/my-access-point",
                "arn:aws:s3:us-east-1:123456789012:accesspoint/my-access-point/object/
*"
            ]
        }
    ]
}
```

With Internet network origin:



With internet origin, you restrict access to the VPC using `aws:SourceVpc` conditions in the access point policy (with an explicit Deny). A VPC endpoint is required so that `aws:SourceVpc` is populated on the request.

Example access point policy (internet origin): The policy includes both an Allow with a VPC condition and a Deny for requests not from the VPC.

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Effect": "Allow",
```

```
            "Principal": {"AWS": "arn:aws:iam::123456789012:role/my-app-role"},
            "Action": [
                "s3:GetObject",
                "s3:PutObject",
                "s3:ListBucket"
            ],
            "Resource": [
                "arn:aws:s3:us-east-1:123456789012:accesspoint/my-access-point",
                "arn:aws:s3:us-east-1:123456789012:accesspoint/my-access-point/object/
*"
            ],
            "Condition": {
                "StringEquals": {"aws:SourceVpc": "vpc-1a2b3c4d"}
            }
        },
        {
            "Effect": "Deny",
            "Principal": "*",
            "Action": "s3:*",
            "Resource": [
                "arn:aws:s3:us-east-1:123456789012:accesspoint/my-access-point",
                "arn:aws:s3:us-east-1:123456789012:accesspoint/my-access-point/object/
*"
            ],
            "Condition": {
                "StringNotEquals": {"aws:SourceVpc": "vpc-1a2b3c4d"}
            }
        }
    ]
}
```

Note

Both the Allow and Deny statements are required in the access point policy. Without the Deny statement, the VPC restriction may not be enforced for all callers.

	VPC origin	Internet origin
Network enforcement	Built-in Deny	Policy-based (Allow + Deny)

	VPC origin	Internet origin
VPC endpoint	Required (Gateway or Interface)	Required (for `aws:SourceVpc`)
access point policy	Minimal — built-in Deny handles restriction	Must include `aws:SourceVpc` Allow + Deny

On-premises and VPC access

Use case: Both on-premises users (via VPN or Direct Connect) and in-VPC compute resources access the access point. All traffic stays private.

> **Important**
>
> Gateway endpoints do not route traffic entering the VPC from VPN, Direct Connect, or Transit Gateway connections. On-premises callers must use an Amazon S3 Interface endpoint. See Using VPC endpoints with Amazon S3 access points for details.



Both the Gateway endpoint (in-VPC traffic) and Interface endpoint (on-prem traffic) are in the same VPC, so both satisfy the VPC origin Deny condition.

	VPC origin	Internet origin
In-VPC endpoint	Gateway (free)	Gateway (for `aws:SourceVpc`)
On-prem endpoint	Interface (required)	Interface (required)
On-prem DNS	Resolve Amazon S3 to Interface endpoint IP	Resolve Amazon S3 to Interface endpoint IP

Multi-VPC access

Use case: Callers in multiple VPCs need to access the same access point. For example, applications in separate VPCs within the same account, or VPCs in different accounts that are connected through VPC peering or Transit Gateway.

There are two approaches for multi-VPC access, depending on whether you want to use policy-based controls or the VPC origin network enforcement.

Option 1: Internet origin with a Gateway endpoint in each VPC

Each VPC has its own Amazon S3 Gateway endpoint. Callers in each VPC access the access point through their local Gateway endpoint, which populates `aws:SourceVpc` on the request. The access point policy restricts access to the allowed VPC IDs.



- **Network origin:** Internet

- **VPC endpoints:** Amazon S3 Gateway endpoint in each VPC (free, no additional configuration needed)
- **access point policy:** Allow with `aws:SourceVpc` listing all VPC IDs, plus a Deny with `StringNotEquals`

> **Note**
>
> Both the Allow and Deny statements are required in the access point policy. Without the Deny statement, the VPC restriction may not be enforced for all callers.

This option is simpler to set up because each VPC operates independently — no VPC peering or Transit Gateway is required. To add or remove VPCs, update the access point policy.

Option 2: VPC origin with a centralized Interface endpoint



One VPC hosts an Amazon S3 Interface endpoint, and the access point is created with VPC origin bound to that VPC. Other VPCs route their Amazon S3 traffic to the Interface endpoint through VPC peering or Transit Gateway. Because all requests arrive through an endpoint in the bound VPC, they satisfy the VPC origin enforcement.

- **Network origin:** VPC (bound to the VPC hosting the Interface endpoint)
- **VPC endpoints:** Amazon S3 Interface endpoint in the bound VPC
- **Connectivity:** VPC peering or Transit Gateway between the other VPCs and the bound VPC
- **access point policy:** Minimal — the VPC origin enforcement handles the network restriction

- **Caller configuration:** Callers in other VPCs must use `--endpoint-url` or DNS configuration to route requests through the Interface endpoint

This option provides stronger enforcement because the VPC origin restriction cannot be bypassed through policy changes. However, it requires VPC peering or Transit Gateway connectivity, and the Interface endpoint has per-hour and per-GB charges. For more information about Interface endpoints, see AWS PrivateLink for Amazon S3 in the *Amazon Simple Storage Service User Guide*.

Troubleshooting network access issues

When an Amazon S3 access point request fails, the error message often does not indicate which authorization layer denied the request. Use the following guidance to diagnose common issues.

AccessDenied with "explicit deny in a resource-based policy"

This error can come from multiple sources. Work through the following checks in order:

1. Check the VPC origin Deny (VPC-origin access points only)

If the access point has a VPC network origin, it effectively denies requests where `aws:SourceVpc` does not match the bound VPC. Verify that:

- A VPC endpoint (Gateway or Interface) exists in the bound VPC.
- The caller's traffic is routing through that endpoint. For in-VPC callers, verify the Gateway endpoint's route table is associated with the caller's subnet. For on-premises callers, verify they are using an Interface endpoint (Gateway endpoints do not route VPN or Direct Connect traffic).
- The caller is in the bound VPC, not a peered VPC. Requests from peered VPCs are denied unless routed through an Interface endpoint in the bound VPC.

2. Check the VPC endpoint policy

If the request traverses a VPC endpoint, the endpoint's policy must allow the action on the access point resource. The default endpoint policy allows all actions on all resources. If you have scoped the policy, verify it includes the access point ARN.

3. Check the access point policy

Verify that the access point policy allows the requesting principal. Check for Deny statements with conditions that might match the request.

4. Check the caller's IAM identity policy

The caller's IAM role or user must have permissions to perform the Amazon S3 action on the access point ARN.

5. Check service control policies (SCPs)

If the account is part of an AWS Organizations organization, verify that no SCPs deny Amazon S3 actions on the access point.

On-premises callers get AccessDenied but in-VPC callers succeed

This typically means on-premises traffic is not routing through a VPC endpoint:

- **Gateway endpoints do not route on-premises traffic.** Traffic entering the VPC from VPN, Direct Connect, or Transit Gateway connections is not affected by Gateway endpoint routes. Create an Amazon S3 Interface endpoint for on-premises callers.
- Verify the Interface endpoint's security group allows inbound HTTPS (port 443) from the on-premises CIDR.
- Verify on-premises DNS resolves Amazon S3 endpoints to the Interface endpoint's private IP, or that callers use `--endpoint-url`.

Access point policy conditions appear to have no effect

- **Allow-only policies do not restrict access.** If you use conditions (such as `aws:SourceVpc`) only in an Allow statement without a corresponding Deny, the caller's IAM identity policy can independently grant access. Add an explicit Deny statement with the inverse condition.
- **Case sensitivity.** The condition key `aws:VpcSourceIp` is case-sensitive.
- **Mutually exclusive condition keys.** `aws:SourceIp` and `aws:VpcSourceIp` are mutually exclusive. `aws:SourceIp` is not available when the request traverses a VPC endpoint — use `aws:VpcSourceIp` instead. Conversely, `aws:VpcSourceIp` is not available for internet requests — use `aws:SourceIp`. This applies to all policies that use these condition keys, including access point policies, VPC endpoint policies, and IAM identity policies.

Managing Amazon S3 access points

This section explains how to manage and use your Amazon S3 access points using the AWS Management Console, AWS Command Line Interface, or API.

S3 access point attachment lifecycle

You can view the status of an S3 access point attachment by using the Amazon FSx console, AWS CLI, or API. The following table describes the possible lifecycle states for an S3 access point attachment.

Lifecycle state	Description
AVAILABLE	The access point attachment is available for use.
CREATING	Amazon FSx is creating the access point attachment.
DELETING	Amazon FSx is deleting the access point attachment.
UPDATING	The access point attachment is undergoing an update.
MISCONFIGURED	The access point attachment has a configuration issue that prevents it from serving requests. Common causes include the file system identity associated with the access point not being resolvable on the file system, or the attached volume being offline or unmounted. Amazon FSx periodically checks for these conditions and automatically returns the access point to `AVAILABLE` when the issue is resolved. For more information, see S3 access point is in MISCONFIGURED state.
FAILED	The access point attachment is in a terminal failure state. This can occur if the access point creation failed (for example, due to an unresolvable file system identity or a disabled S3 protocol on the SVM), or if the underlying S3 access point was deleted directly through Amazon S3 rather than through Amazon FSx. Delete the access point attachment and create a new one.

Topics

- Listing S3 access point attachments
- Viewing access point details
- Deleting an S3 access point attachment

Listing S3 access point attachments

This section explains how to list S3 access point using the AWS Management Console, AWS Command Line Interface, or REST API.

To list all the S3 access points attached to an FSx for ONTAP volume (Amazon FSx console)

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. In the navigation pane on the left side of the console, choose **Volumes**.
3. On the **Volumes** page, choose the **ONTAP** volume that you want to view the access point attachments for.
4. On the Volume details page, choose **S3** to view a list of all the S3 access points attached to the volume.

To list all the S3 access points attached to an FSx for ONTAP volume (AWS CLI)

The following `describe-s3-access-point-attachments` example command shows how you can use the AWS CLI to list S3 access point attachments.

The following command lists all the S3 access points attached to volumes on the FSx for ONTAP file system fs-0abcdef123456789.

```
aws fsx describe-s3-access-point-attachments --filter {[Name: file-system-id, Values:
{[fs-0abcdef123456789]}}
```

The following command lists S3 access points attached to an FSx for ONTAP volume vol-9abcdef123456789].

```
aws fsx describe-s3-access-point-attachments --filter {[Name: volume-id, Values:
{[vol-9abcdef123456789]}}
```

For more information and examples, see list-access-points in the *AWS CLI Command Reference*.

Viewing access point details

This section explains how to view the details of S3 access points using the AWS Management Console, AWS Command Line Interface, or REST API.

To view the details of S3 access points attached to an FSx for ONTAP volume (Amazon FSx console)

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. Navigate to the volume that is attached to the access point whose details you want to view.
3. Choose **S3** to display the list of access points attached to the volume.
4. Choose the access point whose details you want to view.
5. Under **S3 access point attachment summary**, view configuration details and properties for the selected access point.

   The **File system user identity** configuration and the **S3 access point permissions** policy are also listed for the access point attachment.
6. To view the access point's S3 configuration in the Amazon S3 console, choose the S3 access point name displayed under **S3 access point**. It takes you to the access point's detail page in the Amazon S3 console.

Deleting an S3 access point attachment

This section explains how to delete S3 access points using the AWS Management Console, AWS Command Line Interface, or REST API.

The `fsx:DetatchAndDeleteS3AccessPoint` and `s3control:DeleteAccessPoint` permissions are required to delete an S3 access point attachment.

To delete an S3 access point attached to an FSx for ONTAP volume (Amazon FSx console)

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. Navigate to the volume that the S3 access point attachment that you want to delete is attached to.
3. Choose **S3** to display the list of S3 access points attached to the volume.
4. Select the S3 access point attachment that you want to delete.
5. Choose **Delete**.
6. Confirm that you want to delete the S3 access point, and choose **Delete**.

To delete an S3 access point attached to an FSx for ONTAP volume (AWS CLI)

- To delete an S3 access point attachments, use the detach-and-delete-s3-access-point CLI command (or the equivalent DetachAndDeleteS3AccessPoint API operation), as shown in the following example. Use the `--name` property to specify the name of the S3 access point attachment that you want to delete.

```
aws fsx detach-and-delete-s3-access-point \
    --region us-east-1 \
    --name my-ontap-ap
```

Using access points

The following examples demonstrate how to use access points to access file data stored on an FSx for ONTAP volume using the S3 API. For a full list of the Amazon S3 API operations supported by access points attached to an FSx for ONTAP volume, see Access point compatibility.

> **Note**
>
> Files on FSx for ONTAP volumes are identified with a `StorageClass` of `FSX_ONTAP`.

Topics

- Downloading a file using an S3 access point
- Uploading a file using an S3 access point
- Listing files using an S3 access point
- Tagging a file using an S3 access point
- Deleting a file using an S3 access point

Downloading a file using an S3 access point

The following `get-object` example command shows how you can use the AWS CLI to download a file through an access point. You must include an outfile, which is a file name for the downloaded object.

The example requests the file *`my-image.jpg`* through the access point *`my-ontap-ap`* and saves the downloaded file as *`download.jpg`*.

```
$ aws s3api get-object --key my-image.jpg --bucket my-ontap-ap-
hrzrlukc5m36ft7okagglf3gmwluquse1b-ext-s3alias download.jpg
{
    "AcceptRanges": "bytes",
    "LastModified": "Mon, 14 Oct 2024 17:01:48 GMT",
    "ContentLength": 141756,
    "ETag": "\"00751974dc146b76404bb7290f8f51bb-1\"",
    "ContentType": "binary/octet-stream",
    "ServerSideEncryption": "SSE_FSX",
    "Metadata": {},
    "StorageClass": "FSX_ONTAP"
}
```

You can also use the REST API to download an object through an access point. For more information, see GetObject in the *Amazon Simple Storage Service API Reference*.

Uploading a file using an S3 access point

The following `put-object` example command shows how you can use the AWS CLI to upload a file through an access point. You must include an outfile, which is a file name for the uploaded object.

The example uploads the file *my-new-image.jpg* through the access point *my-ontap-ap* and saves the uploaded file as *my-new-image.jpg*.

```
$ aws s3api put-object --bucket my-ontap-ap-hrzrlukc5m36ft7okagglf3gmwluquse1b-ext-
s3alias --key my-new-image.jpg --body  my-new-image.jpg
```

You can also use the REST API to upload an object through an access point. For more information, see PutObject in the *Amazon Simple Storage Service API Reference*.

Listing files using an S3 access point

The following example lists files through the access point alias *my-ontap-ap-hrzrlukc5m36ft7okagglf3gmwluquse1b*`-ext-s3alias` owned by account ID *111122223333* in Region *us-east-2*.

```
$ aws s3api list-objects-v2 --bucket my-ontap-ap-hrzrlukc5m36ft7okagglf3gmwluquse1b-
ext-s3alias
{
    "Contents": [
```

```
        {
            "Key": ".hidden-dir-with-data/file.txt",
            "LastModified": "2024-10-29T14:22:05.4359",
            "ETag": "\"88990077ab44cd55ef66aa77-1\"",
            "Size": 18,
            "StorageClass": "FSX_ONTAP"
        },
        {
            "Key": "documents/report.rtf",
            "LastModified": "2024-11-02T10:18:15.6621",
            "ETag": "\"ab12cd34ef56a89219zg6aa77-1\"",
            "Size": 1048576,
            "StorageClass": "FSX_ONTAP"
        },
    ]
}
```

You can also use the REST API to list your files. For more information, see ListObjectsV2 in the *Amazon Simple Storage Service API Reference*.

Tagging a file using an S3 access point

The following `put-object-tagging` example command shows how you can use the AWS CLI to add a tag-set through an access point. Each tag is a key-value pair. For more information, see Categorizing your storage using tags in the *Amazon Simple Storage Service User Guide*.

The example adds a tag-set to the existing file `my-image.jpg` using the access point *`my-ontap-ap`*.

```
$ aws s3api put-object-tagging --bucket my-ontap-ap-hrzrlukc5m36ft7okagglf3gmwluquse1b-ext-s3alias --key my-image.jpg --tagging TagSet=[{Key="finance",Value="true"}]
```

You can also use the REST API to add a tag-set to an object through an access point. For more information, see PutObjectTagging in the *Amazon Simple Storage Service API Reference*.

Deleting a file using an S3 access point

The following `delete-object` example command shows how you can use the AWS CLI to delete a file through an access point.

```
$ aws s3api delete-object --bucket my-ontap-ap-hrzrlukc5m36ft7okagglf3gmwluquse1b-ext-s3alias --key my-image.jpg
```

You can also use the REST API to delete an object through an access point. For more information, see DeleteObject in the *Amazon Simple Storage Service API Reference*.

Using access points with AWS services

You can use Amazon S3 access points attached to FSx for ONTAP volumes with AWS services that integrate with Amazon S3. This lets you analyze, process, and build Amazon S3-based applications on file data stored in FSx for ONTAP without copying it to an Amazon S3 bucket.

The following sample use cases walk through common integrations step by step. Each tutorial uses an Amazon S3 access point attached to an FSx for ONTAP volume so that AWS services can read and write your file data without having to copy and synchronize data to an Amazon S3 bucket.

- **Query files with SQL using Amazon Athena** — Run ad-hoc SQL queries against files on your FSx for ONTAP volume using Amazon Athena and the AWS Glue Data Catalog. For data analysts who need SQL access to data that lands on an NFS or SMB file share.
- **Process files serverlessly using Lambda** — Trigger Lambda functions against files on your FSx for ONTAP volume to run serverless processing workloads. Examples include generating image thumbnails, extracting text from documents, and transcribing audio.
- **Build ETL pipelines using AWS Glue** — Read, transform, enrich, or partition data on your FSx for ONTAP volume using AWS Glue with Apache Spark, Python shell, or Ray, and write the results back to the same volume. For data engineering teams building curated datasets from files produced by legacy or on-premises systems.
- **Build a RAG application using Amazon Bedrock Knowledge Bases** — Build a retrieval-augmented generation (RAG) application that grounds foundation model responses in documents stored on your FSx for ONTAP volume. For teams building generative AI experiences over an existing document repository.
- **Run Spark jobs using Amazon EMR Serverless** — Run PySpark and Spark SQL workloads against files on your FSx for ONTAP volume without provisioning clusters. For data engineering teams running heavy Spark workloads that exceed the scope of AWS Glue.
- **Stream video using CloudFront** — Deliver HLS adaptive-bitrate video from your FSx for ONTAP volume using CloudFront, with edge caching for performance. For media and entertainment teams whose production workflows write finished content to a file share.
- **Transfer files using AWS Transfer Family** — Expose your FSx for ONTAP volume to external partners as an SFTP, FTPS, or FTP endpoint using AWS Transfer Family over an Amazon S3 access point. For setup instructions, see Access your FSx for ONTAP file systems with Transfer Family in the *AWS Transfer Family User Guide*.

Topics

- Query files with SQL using Amazon Athena
- Process files serverlessly using Lambda
- Build ETL pipelines using AWS Glue
- Build a RAG application using Amazon Bedrock Knowledge Bases
- Run Spark jobs using Amazon EMR Serverless
- Stream video using CloudFront

Query files with SQL using Amazon Athena

Enterprise systems frequently produce file-based output — log exports, transaction extracts, inventory snapshots, inter-system file drops — that lands on an NFS or SMB file share.

With an Amazon S3 access point attached to the FSx for ONTAP volume, Amazon Athena queries the files in place. Your applications and users continue to write to the volume over NFS or SMB the way they always have, and analysts run standard SQL against that data through the access point. Because an FSx for ONTAP volume is simultaneously accessible over NFS, SMB, and the Amazon S3 API, the same file can be produced by one protocol and consumed by another without a copy.

In this tutorial, you upload a sample dataset to your FSx for ONTAP volume through an Amazon S3 access point, register it in the AWS Glue Data Catalog, and query it with Amazon Athena.

> **Note**
>
> This tutorial takes approximately **20 to 30 minutes** to complete. The AWS services used incur charges for the resources you create. If you complete all the steps, including the **Clean up** section promptly, the expected cost is less than **$1** in the US East (N. Virginia) AWS Region. This estimate does not include ongoing charges for the FSx for ONTAP volume itself.

Prerequisites

Before you begin, make sure you have the following:

- An FSx for ONTAP volume with an Amazon S3 access point attached. The access point must have an **internet** network origin. For instructions on creating an access point, see Creating an access point.

- An Athena workgroup configured with a query results location. Athena writes query results to an Amazon S3 bucket, not to the FSx for ONTAP volume. If you do not have a workgroup, you can use the `primary` workgroup and configure a results location in the Athena console under **Settings**. For more information, see Managing workgroups in the *Amazon Athena User Guide*.
- An IAM role for AWS Glue with the `AWSGlueServiceRole` managed policy attached and an inline policy that grants access to your Amazon S3 access point. If you do not have one, use the following steps.

  1. Save the following trust policy as `glue-trust-policy.json`. It allows AWS Glue to assume the role.

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Effect": "Allow",
            "Principal": {"Service": "glue.amazonaws.com"},
            "Action": "sts:AssumeRole"
        }
    ]
}
```

  2. Save the following permissions policy as `glue-s3-policy.json`. It grants access to the access point. Replace *`region`*, *`account-id`*, and *`access-point-name`* with your values.

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Effect": "Allow",
            "Action": [
                "s3:GetObject",
                "s3:ListBucket"
            ],
            "Resource": [
                "arn:aws:s3:region:account-id:accesspoint/access-point-name",
                "arn:aws:s3:region:account-id:accesspoint/access-point-name/
object/*"
            ]
        }
    ]
```

```
}
```

3. Create the role and attach the policies.

```
$ aws iam create-role \
    --role-name fsxn-tutorial-glue-role \
    --assume-role-policy-document file://glue-trust-policy.json

aws iam attach-role-policy \
    --role-name fsxn-tutorial-glue-role \
    --policy-arn arn:aws:iam::aws:policy/service-role/AWSGlueServiceRole

aws iam put-role-policy \
    --role-name fsxn-tutorial-glue-role \
    --policy-name s3-access-point-policy \
    --policy-document file://glue-s3-policy.json
```

- IAM permissions to run Athena queries and access the AWS Glue Data Catalog.

> **Important**
>
> The Amazon S3 access point must use an internet network origin. Athena accesses Amazon S3 from managed infrastructure, not from your VPC. access points with a VPC network origin deny requests from Athena.

Step 1: Upload sample data to your FSx for ONTAP volume

This tutorial uses the NYC Taxi and Limousine Commission (TLC) Trip Record Data, a publicly available dataset of taxi trips in New York City. The data is in Apache Parquet format, a columnar format that Athena can query efficiently.

Download one month of yellow taxi trip data and upload it to your FSx for ONTAP volume through the Amazon S3 access point.

```
$ curl -O https://d37ci6vzurychx.cloudfront.net/trip-data/
yellow_tripdata_2024-01.parquet
```

Upload the file to your FSx for ONTAP volume using the access point alias. Replace *my-ap-alias-ext-s3alias* with your access point alias.

```
$ aws s3 cp yellow_tripdata_2024-01.parquet \
    s3://my-ap-alias-ext-s3alias/taxi-data/yellow_tripdata_2024-01.parquet
```

Verify the file is accessible through the access point.

```
$ aws s3 ls s3://my-ap-alias-ext-s3alias/taxi-data/
2024-01-23 02:18:13   49961641 yellow_tripdata_2024-01.parquet
```

Step 2: Create a database in the AWS Glue Data Catalog

Create a database in the AWS Glue Data Catalog to hold the table metadata. You can create the database using the AWS Glue console, the Athena query editor, or the AWS CLI.

AWS Glue console

1. Open the AWS Glue console at https://console.aws.amazon.com/glue/.
2. In the navigation pane, under **Data Catalog**, choose **Databases**.
3. Choose **Add database**.
4. For **Name**, enter *fsxn_taxi_demo*.
5. Choose **Create database**.

Athena query editor or AWS CLI

```
$ aws athena start-query-execution \
    --query-string "CREATE DATABASE IF NOT EXISTS fsxn_taxi_demo" \
    --work-group primary
```

Step 3: Register the data in the AWS Glue Data Catalog

You can register your data using either a AWS Glue crawler (recommended) or a manual CREATE EXTERNAL TABLE statement in Athena.

Option A: Use a AWS Glue crawler (recommended)

A AWS Glue crawler automatically discovers the schema of your data and creates a table in the AWS Glue Data Catalog. This is the recommended approach because the crawler infers the correct column types from the Parquet file metadata.

1. Create a crawler that points to the access point alias. Replace *my-ap-alias-ext-s3alias* with your access point alias and *my-glue-role-arn* with the ARN of your AWS Glue IAM role.

```
$ aws glue create-crawler \
    --name fsxn-taxi-crawler \
    --role my-glue-role-arn \
    --database-name fsxn_taxi_demo \
    --targets '{"S3Targets": [{"Path": "s3://my-ap-alias-ext-s3alias/taxi-
data/"}]}'
```

2. Run the crawler.

```
$ aws glue start-crawler --name fsxn-taxi-crawler
```

3. Check the crawler status. The crawler typically completes in one to two minutes.

```
$ aws glue get-crawler --name fsxn-taxi-crawler \
    --query "Crawler.{State:State,Status:LastCrawl.Status}"
```

   When the crawler finishes, the state is `READY` and the status is `SUCCEEDED`. The crawler creates a table named `taxi_data` (derived from the folder name) in the `fsxn_taxi_demo` database.

Option B: Create a table manually in Athena

If you already know the schema of your data, you can create the table directly in Athena using a `CREATE EXTERNAL TABLE` statement. Use the access point alias in the `LOCATION` clause.

```
CREATE EXTERNAL TABLE fsxn_taxi_demo.yellow_taxi_trips (
    VendorID bigint,
    tpep_pickup_datetime timestamp,
    tpep_dropoff_datetime timestamp,
    passenger_count bigint,
    trip_distance double,
    RatecodeID bigint,
    store_and_fwd_flag string,
    PULocationID bigint,
    DOLocationID bigint,
    payment_type bigint,
    fare_amount double,
    extra double,
    mta_tax double,
```

```
    tip_amount double,
    tolls_amount double,
    improvement_surcharge double,
    total_amount double,
    congestion_surcharge double,
    Airport_fee double
)
STORED AS PARQUET
LOCATION 's3://my-ap-alias-ext-s3alias/taxi-data/'
```

> **Note**
>
> The column types must match the types in the Parquet file. For this dataset, fields like `passenger_count` and `VendorID` are stored as `bigint` (INT64) in the Parquet file, not `double`. If the types do not match, Athena returns a `HIVE_BAD_DATA` error. Using a AWS Glue crawler (Option A) avoids this issue because the crawler infers the correct types automatically.

Step 4: Query your data

Open the Athena query editor or use the AWS CLI to run SQL queries against your FSx for ONTAP data. The following examples use the table created by the AWS Glue crawler (`taxi_data`). If you created the table manually, replace `taxi_data` with `yellow_taxi_trips`.

Count total trips and calculate averages

```
SELECT
    COUNT(*) AS total_trips,
    ROUND(AVG(trip_distance), 2) AS avg_distance_miles,
    ROUND(AVG(total_amount), 2) AS avg_total_usd,
    ROUND(AVG(passenger_count), 1) AS avg_passengers
FROM fsxn_taxi_demo.taxi_data
```

Example output:

total_trips	avg_distance_miles	avg_total_usd	avg_passengers
2964624	3.65	26.80	1.3

Find the busiest pickup hours

```
SELECT
    HOUR(tpep_pickup_datetime) AS pickup_hour,
    COUNT(*) AS trip_count,
    ROUND(AVG(total_amount), 2) AS avg_fare
FROM fsxn_taxi_demo.taxi_data
GROUP BY HOUR(tpep_pickup_datetime)
ORDER BY trip_count DESC
LIMIT 5
```

Find the highest-revenue pickup locations

```
SELECT
    PULocationID AS pickup_location,
    COUNT(*) AS trip_count,
    ROUND(SUM(total_amount), 2) AS total_revenue
FROM fsxn_taxi_demo.taxi_data
GROUP BY PULocationID
ORDER BY total_revenue DESC
LIMIT 10
```

Considerations

- **Read-only access.** Athena reads data from your FSx for ONTAP volume through the access point. Athena query results are written to the Amazon S3 results bucket, not back to the FSx for ONTAP volume.
- **Internet origin required.** Athena accesses Amazon S3 from managed infrastructure outside your VPC. The `aws:SourceVpc` and `aws:SourceVpce` condition keys are not available for Athena requests. You must use an internet-origin access point.
- **File format.** Athena supports Parquet, ORC, JSON, CSV, and other formats. Columnar formats like Parquet and ORC provide the best query performance because Athena reads only the columns referenced in your query.
- **File system user permissions.** The file system user associated with the access point must have read permission on the files being queried.
- **AWS Glue Data Catalog table is reusable.** Once you register a table in the AWS Glue Data Catalog, it is available to other AWS analytics services that integrate with the AWS Glue Data Catalog, such as Amazon Redshift Spectrum, Amazon EMR, and AWS Glue ETL jobs.

Clean up

To avoid ongoing charges, delete the resources you created in this tutorial.

1. Drop the Athena tables and database.

```
DROP TABLE IF EXISTS fsxn_taxi_demo.taxi_data;
DROP TABLE IF EXISTS fsxn_taxi_demo.yellow_taxi_trips;
DROP DATABASE IF EXISTS fsxn_taxi_demo CASCADE;
```

2. Delete the AWS Glue crawler.

```
$ aws glue delete-crawler --name fsxn-taxi-crawler
```

3. Delete the sample data from your FSx for ONTAP volume.

```
$ aws s3 rm s3://my-ap-alias-ext-s3alias/taxi-data/yellow_tripdata_2024-01.parquet
```

Process files serverlessly using Lambda

File processing workflows often start with files that arrive on an NFS or SMB file share — scanned documents from branch offices, images uploaded by field teams, audio captured from contact centers, or data files delivered by partners.

With an Amazon S3 access point attached to the FSx for ONTAP volume, AWS Lambda functions read and write the files directly using the Amazon S3 API. File-level operations can be processed serverlessly against the same data your users and applications access over NFS and SMB.

This tutorial shows three common file processing patterns. Each example reads a file from the volume through the access point, processes it with an AWS service or library, and writes the result back to the volume.

Example	Input	Processing	Output
the section called "Example 1: Generate	JPEG image	Pillow (image library)	Resized thumbnail

Example	Input	Processing	Output
image thumbnails"			
the section called "Example 2: Extract text from documents"	PDF document	Amazon Textract	Extracted text (JSON)
the section called "Example 3: Transcribe audio files"	MP3 audio	Amazon Transcribe	Transcript (JSON)

> **Note**
>
> This tutorial takes approximately **40 to 60 minutes** to complete. The AWS services used incur charges for the resources you create. If you complete all the steps, including the **Clean up** section promptly, the expected cost is less than **$1** in the US East (N. Virginia) AWS Region. This estimate does not include ongoing charges for the FSx for ONTAP volume itself.

Prerequisites

Before you begin, make sure you have the following:

- An FSx for ONTAP volume with an Amazon S3 access point attached. For instructions on creating an access point, see Creating an access point.
- The access point alias for your access point. You can find this in the Amazon FSx console or by running `aws fsx describe-s3-access-point-attachments`.
- AWS CLI version 1 or version 2 installed and configured. The `aws lambda invoke` commands in this tutorial include the `--cli-binary-format raw-in-base64-out` option, which is

required in AWS CLI version 2 so that raw JSON payloads are not interpreted as base64. If you use AWS CLI version 1, omit that option.

- IAM permissions for the caller (the user or role running this tutorial) to invoke Lambda functions (`lambda:CreateFunction`, `lambda:InvokeFunction`), access the Amazon S3 access point (`s3:GetObject`, `s3:PutObject`), and pass the Lambda execution role (`iam:PassRole`).

> **Note**
>
> This tutorial uses the default Lambda configuration, where functions run in a managed network outside your VPC. In that case, the access point must have an **internet** network origin so the function can reach it. If you attach your Lambda function to a VPC, you can instead use a VPC network origin on the access point; the VPC must have an Amazon S3 Gateway or Interface endpoint. For more information, see Configuring network access for Amazon S3 access points.

Step 1: Upload sample files

Download the following sample files and upload them to your FSx for ONTAP volume through the access point. Replace *`my-ap-alias-ext-s3alias`* with your access point alias throughout this tutorial.

- **Sample image:** Download the NASA Blue Marble image (public domain, 2.4 MB) and save it as `sample-image.jpg`.
- **Sample audio:** Download the sample audio file from the Amazon Transcribe getting started tutorial (410 KB) and save it as `sample-audio.mp3`.

Upload the sample files to your FSx for ONTAP volume through the access point.

```
$ aws s3 cp sample-image.jpg s3://my-ap-alias-ext-s3alias/samples/images/sample-
image.jpg
aws s3 cp sample-audio.mp3 s3://my-ap-alias-ext-s3alias/samples/audio/sample-audio.mp3
```

> **Note**
>
> The sample image is a NASA Blue Marble photograph (public domain, 2.4 MB). The sample audio is from the Amazon Transcribe getting started tutorial (410 KB). The sample PDF is generated in the section called "Example 2: Extract text from documents".

Step 2: Create the Lambda execution role

Lambda functions assume an execution role to interact with other AWS services. For this tutorial, attach the AWS-managed `AWSLambdaBasicExecutionRole` policy for CloudWatch Logs logging, then add an inline policy that grants access to the Amazon S3 access point and to the Textract and Transcribe APIs the examples use.

To create the Lambda execution role

Replace *`region`*, *`account-id`*, and *`access-point-name`* with your values.

1. Save the following trust policy as `trust-policy.json`.

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Effect": "Allow",
            "Principal": {"Service": "lambda.amazonaws.com"},
            "Action": "sts:AssumeRole"
        }
    ]
}
```

2. Save the following inline permissions policy as `permissions-policy.json`. It grants access to the access point and to the additional services the examples use.

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Effect": "Allow",
            "Action": ["s3:GetObject", "s3:PutObject", "s3:ListBucket"],
            "Resource": [
                "arn:aws:s3:region:account-id:accesspoint/access-point-name",
```

```
                "arn:aws:s3:region:account-id:accesspoint/access-point-name/object/
*"
            ]
        },
        {
            "Effect": "Allow",
            "Action": ["textract:DetectDocumentText"],
            "Resource": "*"
        },
        {
            "Effect": "Allow",
            "Action": [
                "transcribe:StartTranscriptionJob",
                "transcribe:GetTranscriptionJob"
            ],
            "Resource": "*"
        }
    ]
}
```

3. Create the role, attach the managed logging policy, and attach the inline policy.

```
$ aws iam create-role \
    --role-name fsxn-lambda-file-processor \
    --assume-role-policy-document file://trust-policy.json

aws iam attach-role-policy \
    --role-name fsxn-lambda-file-processor \
    --policy-arn arn:aws:iam::aws:policy/service-role/AWSLambdaBasicExecutionRole

aws iam put-role-policy \
    --role-name fsxn-lambda-file-processor \
    --policy-name fsxn-access-point-policy \
    --policy-document file://permissions-policy.json
```

Integrating into your workflow

The examples in this tutorial use manual invocation with a test event. In production, you can trigger these functions automatically using the following approaches:

- **Amazon EventBridge schedule.** Run the function on a recurring schedule (for example, every hour or daily) to process new files. The function can list files through the access point and

process any that have not been processed yet. For more information, see Schedule Lambda functions using EventBridge in the *Amazon EventBridge User Guide*.

- **Amazon API Gateway.** Expose the function as an HTTP API so that users or applications can request processing of a specific file on demand. For more information, see Build an API Gateway REST API with Lambda integration in the *Amazon API Gateway Developer Guide*.
- **Step Functions.** Orchestrate multi-step file processing pipelines that combine multiple Lambda functions. For example, a workflow that extracts text from a document, translates it, and writes the result back to the volume. For more information, see Call Lambda with Step Functions in the *AWS Step Functions Developer Guide*.

Example 1: Generate image thumbnails

This example reads a JPEG image from your FSx for ONTAP volume, resizes it to a 200-pixel thumbnail using the Pillow image library, and writes the thumbnail back to the volume.

Lambda function code

Save the following code as `lambda_function.py`.

```
import boto3
from io import BytesIO
from PIL import Image

s3 = boto3.client('s3')

def lambda_handler(event, context):
    bucket = event['access_point_alias']
    key = event['key']

    # Read the image from FSx through the access point
    response = s3.get_object(Bucket=bucket, Key=key)
    image_data = response['Body'].read()

    # Resize to thumbnail
    img = Image.open(BytesIO(image_data))
    img.thumbnail((200, 200))

    # Write the thumbnail back to FSx
    buffer = BytesIO()
    img.save(buffer, format='JPEG', quality=85)
    buffer.seek(0)
```

```
    thumbnail_key = key.rsplit('.', 1)[0] + '_thumbnail.jpg'
    s3.put_object(
        Bucket=bucket,
        Key=thumbnail_key,
        Body=buffer.getvalue(),
        ContentType='image/jpeg'
    )

    return {
        'original_size': len(image_data),
        'thumbnail_size': len(buffer.getvalue()),
        'thumbnail_key': thumbnail_key
    }
```

Create and invoke the function

This function requires the Pillow library. Create a deployment package that includes Pillow built for the Lambda Linux runtime.

```
$ # Create a deployment package with Pillow for Lambda (Linux)
mkdir package && pip install Pillow -t package/ \
    --platform manylinux2014_x86_64 --only-binary=:all:
cd package && zip -r ../thumbnail-function.zip .
cd .. && zip thumbnail-function.zip lambda_function.py

# Create the function
aws lambda create-function \
    --function-name fsxn-thumbnail-generator \
    --runtime python3.12 \
    --handler lambda_function.lambda_handler \
    --role arn:aws:iam::account-id:role/fsxn-lambda-file-processor \
    --zip-file fileb://thumbnail-function.zip \
    --timeout 30 \
    --memory-size 256

# Invoke with a test event
aws lambda invoke \
    --function-name fsxn-thumbnail-generator \
    --cli-binary-format raw-in-base64-out \
    --payload '{"access_point_alias": "my-ap-alias-ext-s3alias", "key": "samples/
images/sample-image.jpg"}' \
    response.json
```

```
cat response.json
```

Verify the result

```
$ aws s3 ls s3://my-ap-alias-ext-s3alias/samples/images/
2024-01-23 12:19:32    2566770 sample-image.jpg
2024-01-23 12:25:49       7065 sample-image_thumbnail.jpg
```

The original 2.4 MB image (5400 × 2700 pixels) was resized to a 7 KB thumbnail (200 × 100 pixels).

Example 2: Extract text from documents

This example reads a PDF document from your FSx for ONTAP volume, sends it to Amazon Textract to extract the text, and writes the extracted text as a JSON file back to the volume.

Create and upload a sample PDF

For this example, you need a PDF document on your FSx for ONTAP volume. The following Python script generates a simple invoice PDF and uploads it through the access point. Run this script on your local machine (not in Lambda).

```
$ pip install fpdf2 boto3
```

```
# create_invoice.py — run locally to generate and upload a sample PDF
from fpdf import FPDF
import boto3

pdf = FPDF()
pdf.add_page()
pdf.set_font("Helvetica", "B", 24)
pdf.cell(0, 15, "INVOICE", new_x="LMARGIN", new_y="NEXT", align="C")
pdf.set_font("Helvetica", "", 12)
pdf.cell(0, 8, "Invoice Number: INV-2024-00142", new_x="LMARGIN", new_y="NEXT")
pdf.cell(0, 8, "Date: January 15, 2024", new_x="LMARGIN", new_y="NEXT")
pdf.cell(0, 8, "Customer: Example Corp", new_x="LMARGIN", new_y="NEXT")
pdf.ln(5)
pdf.set_font("Helvetica", "B", 12)
pdf.cell(80, 8, "Description", border=1)
pdf.cell(30, 8, "Qty", border=1, align="C")
pdf.cell(40, 8, "Unit Price", border=1, align="R")
```

```
pdf.cell(40, 8, "Amount", border=1, align="R")
pdf.ln()
pdf.set_font("Helvetica", "", 12)
for desc, qty, price, amt in [
    ("Cloud Storage Service", "1", "$2,400.00", "$2,400.00"),
    ("Data Transfer (TB)", "5", "$90.00", "$450.00"),
    ("Technical Support", "1", "$500.00", "$500.00"),
]:
    pdf.cell(80, 8, desc, border=1)
    pdf.cell(30, 8, qty, border=1, align="C")
    pdf.cell(40, 8, price, border=1, align="R")
    pdf.cell(40, 8, amt, border=1, align="R")
    pdf.ln()

s3 = boto3.client('s3')
s3.put_object(
    Bucket='my-ap-alias-ext-s3alias',
    Key='samples/documents/invoice.pdf',
    Body=pdf.output(),
    ContentType='application/pdf'
)
print("Uploaded invoice.pdf")
```

```
$ python3 create_invoice.py
```

Lambda function code

Save the following code as `lambda_function.py`.

```
import boto3
import json

s3 = boto3.client('s3')
textract = boto3.client('textract')

def lambda_handler(event, context):
    bucket = event['access_point_alias']
    key = event['key']

    # Read the PDF from FSx through the access point
    response = s3.get_object(Bucket=bucket, Key=key)
    document_bytes = response['Body'].read()
```

```
    # Extract text with Textract
    textract_response = textract.detect_document_text(
        Document={'Bytes': document_bytes}
    )

    lines = [
        block['Text']
        for block in textract_response['Blocks']
        if block['BlockType'] == 'LINE'
    ]

    # Write extracted text as JSON back to FSx
    result = {
        'source_file': key,
        'total_lines': len(lines),
        'extracted_text': lines
    }

    output_key = key.rsplit('.', 1)[0] + '_extracted.json'
    s3.put_object(
        Bucket=bucket,
        Key=output_key,
        Body=json.dumps(result, indent=2),
        ContentType='application/json'
    )

    return {
        'lines_extracted': len(lines),
        'output_key': output_key
    }
```

Create and invoke the function

```
$ zip textract-function.zip lambda_function.py

aws lambda create-function \
    --function-name fsxn-text-extractor \
    --runtime python3.12 \
    --handler lambda_function.lambda_handler \
    --role arn:aws:iam::account-id:role/fsxn-lambda-file-processor \
    --zip-file fileb://textract-function.zip \
    --timeout 30 \
    --memory-size 256
```

```
aws lambda invoke \
    --function-name fsxn-text-extractor \
    --cli-binary-format raw-in-base64-out \
    --payload '{"access_point_alias": "my-ap-alias-ext-s3alias", "key": "samples/
documents/invoice.pdf"}' \
    response.json

cat response.json
```

Example output:

```
{"lines_extracted": 22, "output_key": "samples/documents/invoice_extracted.json"}
```

Example 3: Transcribe audio files

This example starts an Amazon Transcribe job for an audio file stored on your FSx for ONTAP volume. Amazon Transcribe reads the audio file directly from the access point using the access point alias in the media file URI. When the job completes, the function writes the transcript back to the volume.

Lambda function code

Save the following code as `lambda_function.py`.

```
import boto3
import json
import time
import urllib.request

s3 = boto3.client('s3')
transcribe = boto3.client('transcribe')

def lambda_handler(event, context):
    bucket = event['access_point_alias']
    key = event['key']
    media_format = key.rsplit('.', 1)[-1]  # mp3, wav, etc.

    # Start a Transcribe job pointing to the file on FSx
    job_name = f"fsxn-{int(time.time())}"
    transcribe.start_transcription_job(
        TranscriptionJobName=job_name,
        Media={'MediaFileUri': f's3://{bucket}/{key}'},
```

```
        MediaFormat=media_format,
        LanguageCode='en-US'
    )

    # Wait for the job to complete
    while True:
        status = transcribe.get_transcription_job(
            TranscriptionJobName=job_name
        )
        state = status['TranscriptionJob']['TranscriptionJobStatus']
        if state in ('COMPLETED', 'FAILED'):
            break
        time.sleep(5)

    if state == 'FAILED':
        raise Exception(
            status['TranscriptionJob'].get('FailureReason', 'Unknown error')
        )

    # Download the transcript
    transcript_uri = status['TranscriptionJob']['Transcript']['TranscriptFileUri']
    with urllib.request.urlopen(transcript_uri) as resp:
        transcript_data = json.loads(resp.read())

    transcript_text = transcript_data['results']['transcripts'][0]['transcript']

    # Write the transcript back to FSx
    result = {
        'source_file': key,
        'job_name': job_name,
        'transcript': transcript_text
    }

    output_key = key.rsplit('.', 1)[0] + '_transcript.json'
    s3.put_object(
        Bucket=bucket,
        Key=output_key,
        Body=json.dumps(result, indent=2),
        ContentType='application/json'
    )

    return {
        'transcript_length': len(transcript_text),
        'output_key': output_key
```

```
    }
```

Create and invoke the function

```
$ zip transcribe-function.zip lambda_function.py

aws lambda create-function \
    --function-name fsxn-audio-transcriber \
    --runtime python3.12 \
    --handler lambda_function.lambda_handler \
    --role arn:aws:iam::account-id:role/fsxn-lambda-file-processor \
    --zip-file fileb://transcribe-function.zip \
    --timeout 120

aws lambda invoke \
    --function-name fsxn-audio-transcriber \
    --cli-binary-format raw-in-base64-out \
    --payload '{"access_point_alias": "my-ap-alias-ext-s3alias", "key": "samples/audio/
sample-audio.mp3"}' \
    --cli-read-timeout 180 \
    response.json

cat response.json
```

> **Note**
>
> The Transcribe job typically takes 15 to 45 seconds to complete. The function's timeout is set to 120 seconds to allow for this.

Considerations

- **Internet origin required for default configuration.** By default, Lambda accesses Amazon S3 from managed infrastructure outside your VPC, which requires an internet-origin access point. If you attach your Lambda function to a VPC, you can use a VPC-origin access point instead. See the prerequisites for details.
- **File size limits.** Lambda functions have a maximum memory of 10 GB and a maximum execution time of 15 minutes. For large files, consider using range reads (`GetObject` with `Range` header) or streaming the response.

- **Textract limits.** The synchronous `DetectDocumentText` API accepts documents up to 10 MB and 1 page. For multi-page documents, use the asynchronous `StartDocumentTextDetection` API.
- **Transcribe reads directly from the access point.** Amazon Transcribe accepts the access point alias in the `MediaFileUri` parameter (`s3://ap-alias/key`). The Lambda function does not need to download and re-upload the audio file.
- **File system user permissions.** The file system user associated with the access point must have read permission on input files and write permission on output directories.

Clean up

To avoid ongoing charges, delete the resources you created in this tutorial.

```
$ # Delete Lambda functions
aws lambda delete-function --function-name fsxn-thumbnail-generator
aws lambda delete-function --function-name fsxn-text-extractor
aws lambda delete-function --function-name fsxn-audio-transcriber

# Delete the IAM role and policies
aws iam delete-role-policy \
    --role-name fsxn-lambda-file-processor \
    --policy-name fsxn-access-point-policy
aws iam detach-role-policy \
    --role-name fsxn-lambda-file-processor \
    --policy-arn arn:aws:iam::aws:policy/service-role/AWSLambdaBasicExecutionRole
aws iam delete-role --role-name fsxn-lambda-file-processor

# Delete sample files from your FSx volume
aws s3 rm s3://my-ap-alias-ext-s3alias/samples/ --recursive
```

Build ETL pipelines using AWS Glue

Data engineering teams often have raw data landing on an FSx for ONTAP volume from applications, daily file drops, or partner integrations over NFS or SMB. Preparing that data for downstream analytics requires reading, transforming, enriching, or repartitioning it at scale, and making the curated output available to analysts and applications.

With an Amazon S3 access point attached to the FSx for ONTAP volume, AWS Glue reads the source data, transforms it with your choice of runtime (Apache Spark, Python shell, or Ray), and writes the curated output back to the same volume. Both the raw and curated datasets stay on FSx

for ONTAP, so the volume's snapshot, backup, and retention policies apply uniformly across the pipeline. Because an FSx for ONTAP volume is simultaneously accessible over NFS, SMB, and the Amazon S3 API, the raw data can be produced by NFS or SMB clients and the curated output can be consumed by any of those protocols.

In this tutorial, you use the NYC Taxi trip dataset from the Query files with SQL using Amazon Athena tutorial. A AWS Glue ETL job reads the raw Parquet data, adds computed columns, filters invalid records, and writes the transformed output back to the volume partitioned by time of day.

> **Note**
>
> This tutorial takes approximately **25 to 35 minutes** to complete. The AWS services used incur charges for the resources you create. If you complete all the steps, including the **Clean up** section promptly, the expected cost is less than **$1** in the US East (N. Virginia) AWS Region. This estimate does not include ongoing charges for the FSx for ONTAP volume itself.

Prerequisites

Before you begin, make sure you have the following:

- Complete Steps 1 through 3 of the Query files with SQL using Amazon Athena tutorial. That procedure uploads the NYC Taxi dataset to the access point, creates the `fsxn_taxi_demo` database in the AWS Glue Data Catalog, and registers the `taxi_data` table. This tutorial builds on those resources, so do not run the Athena tutorial's **Clean up** section until you have finished this tutorial.
- An IAM role for AWS Glue with an inline policy that grants write access to CloudWatch Logs, read/write access to the access point, and access to the AWS Glue Data Catalog database used by this tutorial. The following steps create a role with the minimum permissions needed for this tutorial.

  1. Save the following trust policy as `glue-trust-policy.json`. It allows AWS Glue to assume the role.

     ```
     {
         "Version": "2012-10-17",
         "Statement": [
             {
     ```

```
            "Effect": "Allow",
            "Principal": {"Service": "glue.amazonaws.com"},
            "Action": "sts:AssumeRole"
        }
    ]
}
```

2. Save the following permissions policy as `glue-permissions.json`. Replace *`region`*, *`account-id`*, and *`access-point-name`* with your values.

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Sid": "Logs",
            "Effect": "Allow",
            "Action": [
                "logs:CreateLogGroup",
                "logs:CreateLogStream",
                "logs:PutLogEvents"
            ],
            "Resource": "arn:aws:logs:region:account-id:log-group:/aws-glue/*"
        },
        {
            "Sid": "AccessPoint",
            "Effect": "Allow",
            "Action": [
                "s3:GetObject",
                "s3:PutObject",
                "s3:ListBucket",
                "s3:DeleteObject"
            ],
            "Resource": [
                "arn:aws:s3:region:account-id:accesspoint/access-point-name",
                "arn:aws:s3:region:account-id:accesspoint/access-point-name/
object/*"
            ]
        },
        {
            "Sid": "DataCatalog",
            "Effect": "Allow",
            "Action": [
                "glue:GetDatabase",
```

```
                "glue:GetTable",
                "glue:GetTables",
                "glue:CreateTable",
                "glue:UpdateTable",
                "glue:DeleteTable",
                "glue:BatchCreatePartition",
                "glue:BatchDeletePartition",
                "glue:CreatePartition",
                "glue:UpdatePartition",
                "glue:GetPartition",
                "glue:GetPartitions"
            ],
            "Resource": [
                "arn:aws:glue:region:account-id:catalog",
                "arn:aws:glue:region:account-id:database/fsxn_taxi_demo",
                "arn:aws:glue:region:account-id:table/fsxn_taxi_demo/*"
            ]
        }
    ]
}
```

3. Create the role and attach the inline policy.

```
$ aws iam create-role \
    --role-name fsxn-tutorial-glue-etl-role \
    --assume-role-policy-document file://glue-trust-policy.json

aws iam put-role-policy \
    --role-name fsxn-tutorial-glue-etl-role \
    --policy-name glue-fsxn-access \
    --policy-document file://glue-permissions.json
```

This tutorial stores the ETL script on the access point itself, so no separate Amazon S3 bucket is required. The `AccessPoint` statement covers both the script and the taxi data; the `DataCatalog` statement scopes AWS Glue catalog access to the `fsxn_taxi_demo` database that the crawler in Step 4 updates.

Important

The Amazon S3 access point must use an internet network origin. AWS Glue jobs access Amazon S3 from managed infrastructure, not from your VPC.

Step 1: Create the ETL script

The following PySpark script reads the raw taxi trip data from your FSx for ONTAP volume, applies transformations, and writes the results back to the volume. Save this script as `taxi_transform.py`.

```
import sys
from awsglue.transforms import *
from awsglue.utils import getResolvedOptions
from pyspark.context import SparkContext
from awsglue.context import GlueContext
from awsglue.job import Job
from pyspark.sql.functions import col, hour, dayofweek, when, round as spark_round

args = getResolvedOptions(sys.argv, ['JOB_NAME', 'AP_ALIAS'])
sc = SparkContext()
glueContext = GlueContext(sc)
spark = glueContext.spark_session
job = Job(glueContext)
job.init(args['JOB_NAME'], args)

ap_alias = args['AP_ALIAS']

# Read raw taxi data from FSx through the access point
df = spark.read.parquet(f"s3://{ap_alias}/taxi-data/")

# Transform: filter invalid records, add computed columns
transformed = df \
    .filter(col("trip_distance") > 0) \
    .filter(col("total_amount") > 0) \
    .filter(col("passenger_count") > 0) \
    .withColumn("pickup_hour", hour(col("tpep_pickup_datetime"))) \
    .withColumn("pickup_day_of_week", dayofweek(col("tpep_pickup_datetime"))) \
    .withColumn("cost_per_mile",
        spark_round(col("total_amount") / col("trip_distance"), 2)) \
    .withColumn("time_of_day",
```

```
        when(hour(col("tpep_pickup_datetime")).between(6, 11), "morning")
        .when(hour(col("tpep_pickup_datetime")).between(12, 16), "afternoon")
        .when(hour(col("tpep_pickup_datetime")).between(17, 21), "evening")
        .otherwise("night")
    ) \
    .select(
        "tpep_pickup_datetime", "tpep_dropoff_datetime",
        "passenger_count", "trip_distance",
        "PULocationID", "DOLocationID",
        "fare_amount", "tip_amount", "total_amount",
        "pickup_hour", "pickup_day_of_week",
        "cost_per_mile", "time_of_day"
    )

# Write transformed data back to FSx, partitioned by time of day
transformed.write \
    .mode("overwrite") \
    .partitionBy("time_of_day") \
    .parquet(f"s3://{ap_alias}/taxi-data-transformed/")

job.commit()
```

The script performs the following transformations:

- **Filters** records with zero or negative trip distance, fare, or passenger count.
- **Adds computed columns:** `pickup_hour`, `pickup_day_of_week`, `cost_per_mile`, and `time_of_day` (morning, afternoon, evening, or night).
- **Selects** a subset of columns relevant for analysis.
- **Partitions** the output by `time_of_day`, which improves query performance when filtering by time period.

Step 2: Upload the script and create the job

Upload the ETL script to your FSx for ONTAP volume through the access point, and create a AWS Glue job that references it. AWS Glue loads the script from the access point at job startup, the same way it loads scripts from a standard Amazon S3 bucket.

```
$ # Upload the script to the access point
aws s3 cp taxi_transform.py \
    s3://my-ap-alias-ext-s3alias/glue-scripts/taxi_transform.py
```

```
# Create the Glue job
aws glue create-job \
    --name fsxn-taxi-transform \
    --role my-glue-role-arn \
    --command '{
        "Name": "glueetl",
        "ScriptLocation": "s3://my-ap-alias-ext-s3alias/glue-scripts/
taxi_transform.py",
        "PythonVersion": "3"
    }' \
    --default-arguments '{
        "--AP_ALIAS": "my-ap-alias-ext-s3alias",
        "--job-language": "python"
    }' \
    --glue-version "4.0" \
    --number-of-workers 2 \
    --worker-type "G.1X"
```

Step 3: Run the job

```
$ aws glue start-job-run --job-name fsxn-taxi-transform
```

Monitor the job status. The job typically completes in one to two minutes with two G.1X workers.

```
$ aws glue get-job-runs --job-name fsxn-taxi-transform \
    --query "JobRuns[0].{State:JobRunState,Duration:ExecutionTime,Error:ErrorMessage}"
```

When the job completes, verify the transformed output on your FSx for ONTAP volume.

```
$ aws s3 ls s3://my-ap-alias-ext-s3alias/taxi-data-transformed/
                           PRE time_of_day=afternoon/
                           PRE time_of_day=evening/
                           PRE time_of_day=morning/
                           PRE time_of_day=night/
```

The output is partitioned into four directories by time of day. Each partition contains Parquet files with the transformed data.

Step 4: Query the transformed data

Run a AWS Glue crawler on the transformed output to register it in the AWS Glue Data Catalog, then query it with Athena.

```
$ # Create a crawler for the transformed data
aws glue create-crawler \
    --name fsxn-taxi-transformed-crawler \
    --role my-glue-role-arn \
    --database-name fsxn_taxi_demo \
    --targets '{"S3Targets": [{"Path": "s3://my-ap-alias-ext-s3alias/taxi-data-
transformed/"}]}'

# Run the crawler
aws glue start-crawler --name fsxn-taxi-transformed-crawler
```

After the crawler completes, query the transformed data in Athena. The partitioned structure allows Athena to scan only the relevant partitions.

```
-- Average cost per mile by time of day
SELECT
    time_of_day,
    COUNT(*) AS trip_count,
    ROUND(AVG(cost_per_mile), 2) AS avg_cost_per_mile,
    ROUND(AVG(tip_amount), 2) AS avg_tip
FROM fsxn_taxi_demo.taxi_data_transformed
GROUP BY time_of_day
ORDER BY trip_count DESC
```

```
-- Busiest pickup locations during morning rush
SELECT
    PULocationID AS pickup_location,
    COUNT(*) AS trip_count,
    ROUND(AVG(trip_distance), 2) AS avg_distance
FROM fsxn_taxi_demo.taxi_data_transformed
WHERE time_of_day = 'morning'
GROUP BY PULocationID
ORDER BY trip_count DESC
LIMIT 10
```

Because the data is partitioned by `time_of_day`, the second query scans only the `morning` partition, reducing the amount of data read and improving query performance.

Considerations

- **Internet origin required.** AWS Glue jobs access Amazon S3 from managed infrastructure outside your VPC. You must use an internet-origin access point.
- **Read and write.** AWS Glue ETL jobs can both read from and write to your FSx for ONTAP volume through the access point. The access point policy and file system user must allow both `s3:GetObject` and `s3:PutObject`.
- **Worker sizing.** The number and type of AWS Glue workers affects job performance and cost. For the 48 MB sample dataset, two G.1X workers are sufficient. For larger datasets, increase the worker count or use G.2X workers.
- **Partitioning.** Writing partitioned output improves downstream query performance in Athena and other analytics services. Choose partition keys based on how the data is typically queried.
- **Script storage.** AWS Glue loads ETL scripts from Amazon S3 at job startup. This tutorial stores the script on the access point so that the script lives alongside the data, but you can also host it in a standard Amazon S3 bucket. If you use a standalone bucket, extend the role's inline policy with `s3:GetObject` on the script bucket ARN.

Clean up

To avoid ongoing charges, delete the resources you created in this tutorial.

In the Athena query editor, drop the table created by the crawler:

```
DROP TABLE IF EXISTS fsxn_taxi_demo.taxi_data_transformed;
```

```
$ # Delete the Glue job and crawler
aws glue delete-job --name fsxn-taxi-transform
aws glue delete-crawler --name fsxn-taxi-transformed-crawler

# Delete the ETL script and transformed data from the access point
aws s3 rm s3://my-ap-alias-ext-s3alias/glue-scripts/taxi_transform.py
aws s3 rm s3://my-ap-alias-ext-s3alias/taxi-data-transformed/ --recursive

# Delete the IAM role
aws iam delete-role-policy \
    --role-name fsxn-tutorial-glue-etl-role \
    --policy-name glue-fsxn-access
aws iam delete-role --role-name fsxn-tutorial-glue-etl-role
```

Build a RAG application using Amazon Bedrock Knowledge Bases

Many enterprises accumulate large repositories of documents on their NFS and SMB file shares — product manuals, policy documents, contracts, research reports, engineering specifications, and user-generated content.

With an Amazon S3 access point attached to the FSx for ONTAP volume, Amazon Bedrock Knowledge Bases ingests content directly from the volume. Foundation-model responses are grounded in the documents where your teams save them over NFS or SMB. Content that writers update on the share becomes available to the knowledge base on the next sync.

In this tutorial, you upload a small set of sample PDFs to your FSx for ONTAP volume through an Amazon S3 access point, create a Amazon Bedrock knowledge base that points to the access point, ingest the documents, and run a question through the `RetrieveAndGenerate` API.

> **Note**
>
> This tutorial takes approximately **35 to 45 minutes** to complete. The AWS services used incur charges for the resources you create. If you complete all the steps, including the **Clean up** section promptly, the expected cost is less than **$1** in the US East (N. Virginia) AWS Region. This estimate does not include ongoing charges for the FSx for ONTAP volume itself.

Prerequisites

Before you begin, make sure you have the following:

- An FSx for ONTAP volume with an Amazon S3 access point attached. The access point must have an **internet** network origin so that the Amazon Bedrock service can reach it. For instructions on creating an access point, see Creating an access point.
- Model access enabled for an embedding model supported by Amazon Bedrock Knowledge Bases and at least one text generation model (for example, `amazon.nova-lite-v1:0`) in the AWS Region where you will create the knowledge base. This tutorial uses `amazon.titan-embed-text-v2:0` (1024 dimensions) as the embedding model; Cohere Embed models are also supported. If you choose a different embedding model, adjust the vector index dimension in Step 2 to match the model's output dimension. Model access is enabled in the Amazon Bedrock console under **Model access**. For more information, see Access Amazon Bedrock foundation models in the *Amazon Bedrock User Guide*.

- AWS CLI version 2 installed and configured with credentials that can create IAM roles, Amazon S3 Vectors resources, and Amazon Bedrock Knowledge Bases.

Step 1: Upload sample documents to the access point

Download a few public PDFs to use as a sample corpus, then upload them to your access point using the Amazon S3 access point alias.

1. Create a local directory and download sample PDFs.

```
$ mkdir -p ~/kb-pdfs && cd ~/kb-pdfs
curl -sSL -o aws-overview.pdf https://d1.awsstatic.com/whitepapers/aws-overview.pdf
curl -sSL -o wellarchitected-framework.pdf https://docs.aws.amazon.com/pdfs/
wellarchitected/latest/framework/wellarchitected-framework.pdf
curl -sSL -o s3-userguide.pdf https://docs.aws.amazon.com/pdfs/AmazonS3/latest/
userguide/s3-userguide.pdf
```

2. Upload each file to the access point. Replace *access-point-alias* with your access point alias (for example, `my-kb-ap-a1b2c3d4e5f6g7h8i9j0kl1mnop2uuse1a-ext-s3alias`). You can find the alias in the Amazon FSx console under **Attached Amazon S3 access points** for your volume, or by running `aws fsx describe-s3-access-point-attachments`.

```
$ for f in *.pdf; do
    aws s3 cp "$f" "s3://access-point-alias/$f"
done
```

3. Verify the files landed on the volume.

```
$ aws s3 ls s3://access-point-alias/
```

> **Note**
>
> Amazon Bedrock Knowledge Bases enforces a maximum file size of 50 MB per document. Files larger than 50 MB are skipped during ingestion.

Step 2: Create a vector store

The knowledge base stores document embeddings in a vector store. Amazon Bedrock Knowledge Bases supports several vector stores; this tutorial uses Amazon S3 Vectors as the default because it is cost-optimized for RAG workloads and requires minimal setup. Amazon OpenSearch Serverless is also supported; see the collapsible section at the end of this step for those instructions.

To create the vector store using the console

If you use the console to create the knowledge base in Step 4: Create the knowledge base and data source, choose **Quick create a new vector store** in the **Vector database** step, and select either **Amazon S3 Vectors** (recommended) or **Amazon OpenSearch Serverless**. Amazon Bedrock creates the vector store and all required configuration automatically. Skip ahead to Step 3: Create an IAM role for the knowledge base.

To create an Amazon S3 Vectors vector store using the AWS CLI

1. Create an Amazon S3 vector bucket. Vector bucket names follow the same global-uniqueness rules as standard Amazon S3 buckets. This tutorial uses `fsxn-kb-vectors`; replace with a unique name.

   ```
   $ aws s3vectors create-vector-bucket --vector-bucket-name fsxn-kb-vectors
   ```

2. Create a vector index in the bucket. The index dimension must match the output dimension of the embedding model; Titan Text Embeddings v2 outputs 1024 dimensions. The `nonFilterableMetadataKeys` setting marks the Bedrock metadata fields as non-filterable, which keeps them out of the 2 KB per-vector filterable metadata limit.

   ```
   $ aws s3vectors create-index --vector-bucket-name fsxn-kb-vectors \
       --index-name bedrock-kb-index \
       --dimension 1024 --distance-metric cosine --data-type float32 \
       --metadata-configuration '{"nonFilterableMetadataKeys":
   ["AMAZON_BEDROCK_METADATA","AMAZON_BEDROCK_TEXT"]}'
   ```

   Note the `indexArn` in the response; you use it in Step 4: Create the knowledge base and data source.

Alternative: Create an OpenSearch Service Serverless vector store using the AWS CLI

If you prefer OpenSearch Service Serverless (for higher queries-per-second, advanced search features, or existing operational familiarity), use the following steps instead of the Amazon S3 Vectors procedure above.

1. Create encryption and network security policies for the collection.

```
$ aws opensearchserverless create-security-policy --name kb-enc --type encryption \
    --policy '{"Rules":[{"ResourceType":"collection","Resource":["collection/fsxn-
kb"]}],"AWSOwnedKey":true}'
aws opensearchserverless create-security-policy --name kb-net --type network \
    --policy '[{"Rules":[{"ResourceType":"collection","Resource":["collection/
fsxn-kb"]},{"ResourceType":"dashboard","Resource":["collection/fsxn-
kb"]}],"AllowFromPublic":true}]'
```

2. Create a data access policy that grants the knowledge base role and your current user permission to read and write the collection. Replace *account-id* and *current-user* with your values.

```
$ aws opensearchserverless create-access-policy --name kb-data --type data --policy
 '[{
    "Rules":[
        {"ResourceType":"index","Resource":["index/fsxn-kb/*"],"Permission":
["aoss:*"]},
        {"ResourceType":"collection","Resource":["collection/fsxn-
kb"],"Permission":["aoss:*"]}
    ],
    "Principal":[
        "arn:aws:iam::account-id:role/fsxn-kb-role",
        "arn:aws:iam::account-id:user/current-user"
    ]
}]'
```

3. Create the collection and wait for it to become `ACTIVE`.

```
$ aws opensearchserverless create-collection --name fsxn-kb --type VECTORSEARCH
aws opensearchserverless batch-get-collection --names fsxn-kb \
    --query 'collectionDetails[0].{status:status,endpoint:collectionEndpoint}'
```

4. Create the vector index on the collection using a Python script with signed requests. The index must use dimension 1024 (for Titan Text Embeddings v2) and field names that Amazon

Bedrock Knowledge Bases expects. For the full script and subsequent configuration steps, see Prerequisites for using OpenSearch Service Serverless in the *Amazon Bedrock User Guide*. Use the resulting collection ARN and index name in Step 4 with a `storage-configuration` of type `OPENSEARCH_SERVERLESS`.

Step 3: Create an IAM role for the knowledge base

The knowledge base needs an IAM role that it can assume to invoke the embedding model, read objects through the Amazon S3 access point, and access the vector store. The policy shown below grants access to an Amazon S3 Vectors vector store. If you use OpenSearch Service Serverless instead, replace the `S3Vectors` statement with one that grants `aoss:APIAccessAll` on the collection ARN.

To create the role using the console

When you create the knowledge base using the Amazon Bedrock console in Step 4: Create the knowledge base and data source, choose **Create and use a new service role**. Amazon Bedrock creates a role with the required trust and permissions, scoped to your knowledge base, embedding model, vector store, and data source. Skip ahead to Step 4: Create the knowledge base and data source.

To create the role using the AWS CLI

1. Save the following trust policy as `kb-trust-policy.json`. It allows Amazon Bedrock to assume the role. Replace *`account-id`* with your AWS account ID.

```
{
    "Version": "2012-10-17",
    "Statement": [{
        "Effect": "Allow",
        "Principal": {"Service": "bedrock.amazonaws.com"},
        "Action": "sts:AssumeRole",
        "Condition": {"StringEquals": {"aws:SourceAccount": "account-id"}}
    }]
}
```

2. Save the following permissions policy as `kb-permissions.json`. It grants access to the embedding model, the Amazon S3 access point, and the vector store. Replace the placeholders with your values.

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Sid": "FoundationModel",
            "Effect": "Allow",
            "Action": ["bedrock:InvokeModel"],
            "Resource": ["arn:aws:bedrock:region::foundation-model/amazon.titan-
embed-text-v2:0"]
        },
        {
            "Sid": "S3AccessPoint",
            "Effect": "Allow",
            "Action": ["s3:GetObject", "s3:ListBucket"],
            "Resource": [
                "arn:aws:s3:region:account-id:accesspoint/access-point-name",
                "arn:aws:s3:region:account-id:accesspoint/access-point-name/object/
*"
            ]
        },
        {
            "Sid": "S3Vectors",
            "Effect": "Allow",
            "Action": [
                "s3vectors:GetIndex",
                "s3vectors:PutVectors",
                "s3vectors:GetVectors",
                "s3vectors:ListVectors",
                "s3vectors:DeleteVectors",
                "s3vectors:QueryVectors"
            ],
            "Resource": [
                "arn:aws:s3vectors:region:account-id:bucket/fsxn-kb-vectors",
                "arn:aws:s3vectors:region:account-id:bucket/fsxn-kb-vectors/index/
*"
            ]
        }
    ]
}
```

3. Create the role and attach the permissions policy.

```
$ aws iam create-role --role-name fsxn-kb-role \
    --assume-role-policy-document file://kb-trust-policy.json
aws iam put-role-policy --role-name fsxn-kb-role --policy-name kb-access \
    --policy-document file://kb-permissions.json
```

Step 4: Create the knowledge base and data source

The data source points at your Amazon S3 access point alias. Amazon Bedrock Knowledge Bases accepts the access point alias in place of a bucket name.

To create the knowledge base using the console

1. Open the Amazon Bedrock console at https://console.aws.amazon.com/bedrock/.
2. In the left navigation pane, choose **Knowledge bases**, and then choose **Create knowledge base**.
3. Under **Knowledge base details**, enter a name (for example, `fsxn-kb`) and description.
4. Under **IAM permissions**, choose **Create and use a new service role**.
5. For **Data source**, choose **Amazon S3**, and then choose **Next**.
6. Enter a data source name (for example, `fsxn-s3ap-source`).
7. For **S3 URI**, enter `s3://` followed by your access point alias, for example `s3://my-kb-ap-a1b2c3d4e5f6g7h8i9j0kl1mnop2uuse1a-ext-s3alias`. The console does not distinguish between a bucket name and an access point alias in this field; the access point alias is accepted as-is.
8. Choose **Next**.
9. Under **Embeddings model**, choose **Titan Text Embeddings v2**.
10. Under **Vector database**, choose **Quick create a new vector store** and select **Amazon S3 Vectors**. Choose **Next**.
11. Review the configuration and choose **Create knowledge base**. The knowledge base can take several minutes to create.

To create the knowledge base using the AWS CLI

1. Create the knowledge base. Replace the placeholders with your values. The `indexArn` is the ARN of the Amazon S3 vector index you created in Step 2.

```
$ aws bedrock-agent create-knowledge-base --name fsxn-kb \
    --role-arn arn:aws:iam::account-id:role/fsxn-kb-role \
    --knowledge-base-configuration '{
        "type":"VECTOR",
        "vectorKnowledgeBaseConfiguration":{
            "embeddingModelArn":"arn:aws:bedrock:region::foundation-model/
amazon.titan-embed-text-v2:0"
        }
    }' \
    --storage-configuration '{
        "type":"S3_VECTORS",
        "s3VectorsConfiguration":{
            "indexArn":"index-arn"
        }
    }'
```

Note the `knowledgeBaseId` in the response.

2. Create the data source. Pass the Amazon S3 access point alias as the bucket name in the `bucketArn` field, using the form `arn:aws:s3:::access-point-alias`.

```
$ aws bedrock-agent create-data-source \
    --knowledge-base-id knowledge-base-id \
    --name fsxn-s3ap-source \
    --data-source-configuration '{
        "type":"S3",
        "s3Configuration":{"bucketArn":"arn:aws:s3:::access-point-alias"}
    }'
```

Note the `dataSourceId` in the response.

Step 5: Ingest the documents

Run an ingestion job to crawl the documents through the access point, generate embeddings, and index them in the vector store.

To run ingestion using the console

1. In the Amazon Bedrock console, open your knowledge base.
2. In the **Data source** section, select your data source, and then choose **Sync**.

3. Wait for **Sync status** to show **Ready**.

To run ingestion using the AWS CLI

1. Start the ingestion job.

```
$ aws bedrock-agent start-ingestion-job \
    --knowledge-base-id knowledge-base-id \
    --data-source-id data-source-id
```

   Note the `ingestionJobId` in the response.

2. Poll the job until it completes.

```
$ aws bedrock-agent get-ingestion-job \
    --knowledge-base-id knowledge-base-id \
    --data-source-id data-source-id \
    --ingestion-job-id ingestion-job-id
```

   The `status` field transitions from `IN_PROGRESS` to `COMPLETE`. The `statistics` field shows how many documents were scanned and indexed.

Step 6: Query the knowledge base

Ask the knowledge base a question grounded in the ingested documents. The response includes citations that reference the source documents through the Amazon S3 access point alias.

To query using the console

1. In the Amazon Bedrock console, open your knowledge base.
2. Choose **Test knowledge base**.
3. Under **Generate responses**, select a text generation model (for example, **Nova Lite**).
4. Enter a question such as `What are the pillars of the AWS Well-Architected Framework?` and choose **Run**. The answer displays with citation references that link to the source documents in the Amazon S3 access point.

To query using the AWS CLI

Use the `retrieve-and-generate` command. Replace the placeholders with your values. The `modelArn` must refer to an inference profile for a text generation model to which you have access.

```
$ aws bedrock-agent-runtime retrieve-and-generate \
    --input '{"text":"What are the pillars of the AWS Well-Architected Framework?"}' \
    --retrieve-and-generate-configuration '{
        "type":"KNOWLEDGE_BASE",
        "knowledgeBaseConfiguration":{
            "knowledgeBaseId":"knowledge-base-id",
            "modelArn":"arn:aws:bedrock:region:account-id:inference-profile/
us.amazon.nova-lite-v1:0"
        }
    }'
```

The response contains the generated answer in `output.text` and a list of citations in the `citations` array. Each citation includes an `s3Location.uri` field that points to the source document through the access point alias, in the form `s3://access-point-alias/file.pdf`.

Troubleshooting

Ingestion job reports files were ignored

Amazon Bedrock Knowledge Bases enforces a maximum file size of 50 MB per document. Files larger than 50 MB are listed in `failureReasons` and skipped. Split or compress large documents before uploading.

`ValidationException`: model marked as Legacy

The text generation model you specified has been deprecated for your account. Choose an active inference profile, such as `us.amazon.nova-lite-v1:0` or another currently supported model. Run `aws bedrock list-inference-profiles` to list available profiles.

`AccessDeniedException` during ingestion

Verify that the knowledge base IAM role has `s3:GetObject` and `s3:ListBucket` on the access point ARN (not on the underlying volume) and that the access point has an internet network origin so that the Amazon Bedrock service can reach it. If you chose the OpenSearch Service Serverless alternative in Step 2, also verify that the data access policy lists the role as a principal.

Ingestion job succeeds but queries return no relevant passages

Confirm that the vector index was created with `dimension: 1024` (for Titan Text Embeddings v2) and that the field names in the index mapping match the field names configured on the knowledge base.

Clean up

To avoid ongoing charges, delete the resources you created:

- Amazon Bedrock knowledge base and data source
- Amazon S3 vector index and vector bucket (or OpenSearch Service Serverless collection, if you used the alternative in Step 2)
- IAM role and inline policy
- Objects uploaded to the access point (if no longer needed)

```
$ aws bedrock-agent delete-data-source --knowledge-base-id knowledge-base-id --data-
source-id data-source-id
aws bedrock-agent delete-knowledge-base --knowledge-base-id knowledge-base-id
aws s3vectors delete-index --vector-bucket-name fsxn-kb-vectors --index-name bedrock-
kb-index
aws s3vectors delete-vector-bucket --vector-bucket-name fsxn-kb-vectors
aws iam delete-role-policy --role-name fsxn-kb-role --policy-name kb-access
aws iam delete-role --role-name fsxn-kb-role
```

Alternative: Clean up OpenSearch Service Serverless resources

If you chose the OpenSearch Service Serverless alternative in Step 2, replace the `s3vectors` commands above with the following. Idle OpenSearch Service Serverless collections accrue OCU-hour charges, so delete them promptly when you are done with the tutorial.

```
$ # Get the collection ID (required by delete-collection; the name is not accepted)
COLLECTION_ID=$(aws opensearchserverless batch-get-collection --names fsxn-kb \
    --query 'collectionDetails[0].id' --output text)

# Delete the collection, then the policies
aws opensearchserverless delete-collection --id "$COLLECTION_ID"
aws opensearchserverless delete-access-policy --name kb-data --type data
aws opensearchserverless delete-security-policy --name kb-net --type network
```

```
aws opensearchserverless delete-security-policy --name kb-enc --type encryption
```

Run Spark jobs using Amazon EMR Serverless

Data engineering teams that run Spark workloads — for log processing, feature engineering, complex ETL, or scientific analysis — often have source data on an FSx for ONTAP volume written by on-premises ingestion pipelines, NFS or SMB data movers, or applications that mount the volume directly.

With an Amazon S3 access point attached to the volume, Amazon EMR Serverless reads the data through the access point, runs the Spark job against it, and writes the results back to the same volume. Amazon EMR Serverless handles cluster lifecycle automatically — you submit a job and pay for the seconds it runs.

This pattern suits workloads that need a full Spark runtime (custom libraries, iterative algorithms, long-running transformations, or interactive notebooks via Amazon EMR Studio) where the lighter-weight options — Amazon Athena for SQL and AWS Glue for managed ETL — are not the right fit. For information on those alternatives, see Query files with SQL using Amazon Athena and Build ETL pipelines using AWS Glue.

In this tutorial, you simulate a meteorology team aggregating a year of NOAA Global Surface Summary of the Day (GSOD) observations staged on an FSx for ONTAP volume. You submit a PySpark job that reads the raw CSV files, computes monthly per-station aggregates (average temperature, total precipitation, and a count of days with precipitation events), and writes the results as Parquet partitioned by month — all through the access point.

> **Note**
>
> This tutorial takes approximately **30 to 40 minutes** to complete. The AWS services used incur charges for the resources you create. If you complete all the steps, including the **Clean up** section promptly, the expected cost is less than **$1** in the US East (N. Virginia) AWS Region. This estimate does not include ongoing charges for the FSx for ONTAP volume itself.

Prerequisites

- An FSx for ONTAP volume with an Amazon S3 access point attached. The access point must have an **internet** network origin so that the Amazon EMR Serverless service can reach it. For instructions, see Creating an access point.
- AWS CLI version 2 installed and configured with credentials that can create IAM roles and Amazon EMR Serverless resources.

Step 1: Upload the sample dataset to the access point

The NOAA GSOD dataset is a public dataset of daily weather observations, one CSV file per station per year. For this tutorial, you download a 100-station subset from the public `noaa-gsod-pds` Amazon S3 bucket and upload it to your access point.

1. Download the first 100 station files for 2024.

```
$ mkdir -p ~/gsod && cd ~/gsod
aws s3 ls s3://noaa-gsod-pds/2024/ --no-sign-request | head -100 | awk '{print
 $NF}' > files.txt
while read f; do
    aws s3 cp "s3://noaa-gsod-pds/2024/$f" "$f" --no-sign-request --only-show-
errors
done < files.txt
ls | wc -l
```

   The command downloads approximately 100 CSV files totaling about 7–8 MB.

2. Upload the files to the access point under the `gsod/2024/` prefix. Replace *`access-point-alias`* with your access point alias.

```
$ aws s3 cp ~/gsod/ "s3://access-point-alias/gsod/2024/" --recursive --exclude
 "files.txt" --only-show-errors
```

Step 2: Write the PySpark job

The job reads all CSV files under the input prefix, filters sentinel values that represent missing data, parses the FRSHTT bitfield (Fog, Rain, Snow, Hail, Thunder, Tornado) to count precipitation-event days, aggregates per `(station, month)`, and writes partitioned Parquet back to the access point.

1. Save the following script to a file named `gsod_monthly.py`.

```
# gsod_monthly.py
import sys
from pyspark.sql import SparkSession
from pyspark.sql import functions as F

INPUT_PATH, OUTPUT_PATH = sys.argv[1], sys.argv[2]

# GSOD sentinels for missing data
TEMP_SENTINEL = 9999.9
PRCP_SENTINEL = 99.99

spark = SparkSession.builder.appName("gsod-monthly-summary").getOrCreate()

raw = spark.read.option("header", True).csv(INPUT_PATH)

cleaned = (raw
    .select(
        F.col("STATION").alias("station"),
        F.col("NAME").alias("station_name"),
        F.col("LATITUDE").cast("double").alias("lat"),
        F.col("LONGITUDE").cast("double").alias("lon"),
        F.to_date("DATE", "yyyy-MM-dd").alias("date"),
        F.col("TEMP").cast("double").alias("temp_f"),
        F.col("PRCP").cast("double").alias("prcp_in"),
        F.col("FRSHTT").alias("frshtt"),
    )
    .filter(F.col("temp_f") != TEMP_SENTINEL)
    .withColumn("month", F.date_format("date", "yyyy-MM"))
    .withColumn(
        "prcp_in",
        F.when(F.col("prcp_in") == PRCP_SENTINEL,
 None).otherwise(F.col("prcp_in")),
    )
    # FRSHTT is a 6-char bitfield: Fog, Rain, Snow, Hail, Thunder, Tornado.
    # Check only positions 2-4 (Rain, Snow, Hail) for precipitation events.
    .withColumn(
        "had_precip_event",
        F.when(F.col("frshtt").substr(2, 3).rlike("1"), 1).otherwise(0),
    )
)
```

```
monthly = (cleaned
    .groupBy("station", "station_name", "lat", "lon", "month")
    .agg(
        F.avg("temp_f").alias("avg_temp_f"),
        F.min("temp_f").alias("min_temp_f"),
        F.max("temp_f").alias("max_temp_f"),
        F.sum("prcp_in").alias("total_prcp_in"),
        F.sum("had_precip_event").alias("precip_event_days"),
        F.count("*").alias("observation_days"),
    )
)

(monthly.write
    .mode("overwrite")
    .partitionBy("month")
    .parquet(OUTPUT_PATH))

spark.stop()
```

2. Upload the script to the access point under the `scripts/` prefix.

```
$ aws s3 cp gsod_monthly.py "s3://access-point-alias/scripts/gsod_monthly.py"
```

Step 3: Create the Amazon EMR Serverless job role

Amazon EMR Serverless assumes an IAM execution role when it runs your job. The role needs permissions to read and write the access point and to write logs to CloudWatch Logs. Expand the following section for setup steps.

To create the Amazon EMR Serverless job role

1. Save the following trust policy as `emr-trust-policy.json`. It allows Amazon EMR Serverless to assume the role.

```
{
    "Version": "2012-10-17",
    "Statement": [{
        "Effect": "Allow",
        "Principal": {"Service": "emr-serverless.amazonaws.com"},
        "Action": "sts:AssumeRole"
    }]
```

```
}
```

2. Save the following permissions policy as `emr-permissions.json`. Replace *`region`*, *`account-id`*, and *`access-point-name`* with your values.

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Sid": "Logs",
            "Effect": "Allow",
            "Action": [
                "logs:CreateLogGroup",
                "logs:CreateLogStream",
                "logs:PutLogEvents",
                "logs:DescribeLogGroups",
                "logs:DescribeLogStreams"
            ],
            "Resource": "*"
        },
        {
            "Sid": "APRead",
            "Effect": "Allow",
            "Action": ["s3:GetObject", "s3:ListBucket"],
            "Resource": [
                "arn:aws:s3:region:account-id:accesspoint/access-point-name",
                "arn:aws:s3:region:account-id:accesspoint/access-point-name/object/
*"
            ]
        },
        {
            "Sid": "APWrite",
            "Effect": "Allow",
            "Action": [
                "s3:PutObject", "s3:DeleteObject",
                "s3:AbortMultipartUpload", "s3:ListMultipartUploadParts"
            ],
            "Resource": "arn:aws:s3:region:account-id:accesspoint/access-point-
name/object/*"
        }
    ]
}
```

3. Create the role and attach the policy.

```
$ aws iam create-role --role-name fsxn-emr-job-role \
    --assume-role-policy-document file://emr-trust-policy.json
aws iam put-role-policy --role-name fsxn-emr-job-role \
    --policy-name emr-access --policy-document file://emr-permissions.json
```

Step 4: Create and start the Amazon EMR Serverless application

An Amazon EMR Serverless application is a long-lived compute environment for a specific release label and engine (Spark or Hive). You submit one or more jobs to it. Applications scale compute up and down automatically based on job demand and idle out when no jobs are running.

1. Create a Spark application using a recent Amazon EMR release.

```
$ aws emr-serverless create-application \
    --name fsxn-emr-app --type SPARK --release-label emr-7.0.0
```

   Note the `applicationId` in the response.

2. Start the application. Starting pre-warms a small pool of workers so the first job runs without a cold-start delay.

```
$ aws emr-serverless start-application --application-id application-id
```

   Wait for the state to become STARTED.

```
$ aws emr-serverless get-application --application-id application-id \
    --query 'application.state'
```

Step 5: Submit the Spark job

Submit the job using the application ID and the execution role. The job reads the raw CSVs from `gsod/2024/` and writes partitioned Parquet to `gsod-monthly/`, both through the access point.

1. Save the job driver configuration as `job-driver.json`. Replace the placeholders.

```
{
    "sparkSubmit": {
```

```
        "entryPoint": "s3://access-point-alias/scripts/gsod_monthly.py",
        "entryPointArguments": [
            "s3://access-point-alias/gsod/2024/",
            "s3://access-point-alias/gsod-monthly/"
        ],
        "sparkSubmitParameters": "--conf spark.executor.cores=2 --conf
 spark.executor.memory=4g --conf spark.driver.cores=2 --conf spark.driver.memory=4g
 --conf spark.executor.instances=2"
    }
}
```

2. Save the following monitoring configuration as `job-config.json`. It sends driver and executor logs to CloudWatch Logs.

```
{
    "monitoringConfiguration": {
        "cloudWatchLoggingConfiguration": {
            "enabled": true,
            "logGroupName": "/aws/emr-serverless/fsxn-emr-app"
        }
    }
}
```

3. Submit the job.

```
$ aws emr-serverless start-job-run \
    --application-id application-id \
    --execution-role-arn arn:aws:iam::account-id:role/fsxn-emr-job-role \
    --name gsod-monthly \
    --job-driver file://job-driver.json \
    --configuration-overrides file://job-config.json
```

Note the `jobRunId` in the response.

4. Poll the job status. The job transitions from `SCHEDULED` to `RUNNING` to `SUCCESS`.

```
$ aws emr-serverless get-job-run \
    --application-id application-id \
    --job-run-id job-run-id \
    --query 'jobRun.state'
```

> **Note**
>
> If the job fails, check the driver logs in CloudWatch Logs under the log group `/aws/emr-serverless/fsxn-emr-app`. Amazon EMR Serverless writes one log stream per job run.

Step 6: Inspect the output

Verify that the job wrote one Parquet partition per month and that the output is readable.

1. List the output partitions.

   ```
   $ aws s3 ls "s3://access-point-alias/gsod-monthly/" --recursive
   ```

   You should see one Parquet file per `month=YYYY-MM/` partition plus a _SUCCESS marker at the root.

2. Read a partition locally to verify the content.

   ```
   $ aws s3 cp "s3://access-point-alias/gsod-monthly/month=2024-06/" . \
       --recursive --exclude "_SUCCESS"
   python3 -c "import pyarrow.parquet as pq; \
       t = pq.read_table(next(__import__('glob').iglob('*.parquet'))); \
       print(t.schema); print(t.to_pandas().head())"
   ```

   The output schema includes `station`, `station_name`, `lat`, `lon`, `avg_temp_f`, `min_temp_f`, `max_temp_f`, `total_prcp_in`, `precip_event_days`, and `observation_days`.

Extending the pattern

- **Query the output with Spark SQL.** Register the partitioned output as a table with the AWS Glue Data Catalog and query it with Spark SQL, Athena, or any other tool that reads AWS Glue catalog tables. For instructions on registering an access point-backed dataset, see Query files with SQL using Amazon Athena.
- **Use Iceberg for ACID writes.** For workloads that update or merge data, configure the job to write to an Iceberg table on the access point instead of plain Parquet. Amazon EMR Serverless includes the Iceberg runtime by default on recent release labels.

- **Run interactively with Amazon EMR Studio.** Attach a Jupyter notebook to the Amazon EMR Serverless application to explore the data interactively. See Interactive workloads with Amazon EMR Serverless in the *Amazon EMR Serverless User Guide*.
- **Schedule the job.** Use Amazon EventBridge Scheduler or AWS Step Functions to run the job on a recurring schedule (for example, when a new day of data lands on the volume).

Troubleshooting

Job fails with `AccessDenied` on the access point

Verify that the job role policy grants `s3:GetObject` and `s3:ListBucket` on the access point ARN (not on a bucket), and that the access point has an internet network origin so the Amazon EMR Serverless service can reach it.

Job succeeds but the output is empty

Check the input path. Amazon S3 `ListObjectsV2` treats prefixes literally, so `s3://alias/gsod/2024` (no trailing slash) and `s3://alias/gsod/2024/` (trailing slash) can behave differently. Include the trailing slash when pointing at a directory of files.

Driver logs are not in CloudWatch Logs

The monitoring configuration must be passed through `--configuration-overrides` on `start-job-run`, not on the application. Each job run writes to its own log stream under the configured log group.

Clean up

Stop and delete the application, remove the IAM role, and delete any uploaded data you no longer need.

```
$ aws emr-serverless stop-application --application-id application-id
aws emr-serverless delete-application --application-id application-id
aws iam delete-role-policy --role-name fsxn-emr-job-role --policy-name emr-access
aws iam delete-role --role-name fsxn-emr-job-role
aws s3 rm "s3://access-point-alias/scripts/gsod_monthly.py"
aws s3 rm "s3://access-point-alias/gsod/" --recursive
aws s3 rm "s3://access-point-alias/gsod-monthly/" --recursive
```

Stream video using CloudFront

Media workflows commonly store finished content — video on demand (VOD) files, HTTP Live Streaming (HLS) packages, images, and graphics — on an FSx for ONTAP volume that editors, producers, and automation systems write to using NFS or SMB.

With an Amazon S3 access point attached to the FSx for ONTAP volume, CloudFront can serve content directly from the volume. Editors and production systems publish to the volume over NFS or SMB the way they always have, CloudFront fetches content through the access point, and viewers receive the content from the nearest CloudFront edge location.

In this tutorial, you encode a sample video as an HLS adaptive-bitrate package, upload the output to an access point attached to an FSx for ONTAP volume, configure a CloudFront distribution with origin access control so viewers cannot bypass CloudFront to reach the volume directly, and verify that the stream plays end to end.

> **Note**
>
> This tutorial takes approximately **40 to 60 minutes** to complete. The AWS services used incur charges for the resources you create. If you complete all the steps, including the **Clean up** section promptly, the expected cost is less than **$1** in the US East (N. Virginia) AWS Region. This estimate does not include ongoing charges for the FSx for ONTAP volume itself.

How the pattern works

The request flow is:

- A viewer's player (browser, mobile app, smart TV) requests the HLS master playlist from the CloudFront domain.
- CloudFront checks its edge cache. On a miss, CloudFront signs a request using Signature Version 4 (SigV4) with its origin access control (OAC) and forwards it to the Amazon S3 endpoint for the access point.
- The access point authorizes the request against its access policy, which allows the CloudFront service principal scoped to your distribution, and returns the requested object from the FSx for ONTAP volume.
- CloudFront caches the response at the edge and returns it to the viewer.

HLS packages mix two types of files that benefit from different cache policies:

- **Playlists** (`.m3u8`) describe which segments make up the stream. Use a short `Cache-Control` TTL so you can publish updated playlists quickly.
- **Segments** (`.ts`) contain the encoded video and audio. Once written, a segment's contents never change, so use a long, immutable `Cache-Control` TTL.

Prerequisites

- An FSx for ONTAP volume with an Amazon S3 access point attached. The access point must have an **internet** network origin so that CloudFront can reach it. For instructions, see Creating an access point.
- AWS CLI version 2 installed and configured with credentials that can create CloudFront distributions, origin access controls, and access point policies.
- FFmpeg installed locally, for encoding the sample video to HLS.
- A source video file. This tutorial uses the Sintel trailer from the Blender Foundation, a 52-second 1080p clip released under Creative Commons.

Step 1: Encode the source video as an HLS package

Use FFmpeg to produce a three-variant HLS package at 360p, 720p, and 1080p with realistic over-the-top (OTT) bitrates. The resulting package includes a master playlist that references per-variant playlists, each of which lists four-second transport stream segments.

1. Download the source video.

```
$ mkdir -p ~/media && cd ~/media
curl -sSL -o sintel-1080p.mp4 \
    https://download.blender.org/durian/trailer/sintel_trailer-1080p.mp4
```

2. Encode the video to HLS with three adaptive-bitrate variants.

```
$ mkdir hls && cd hls
ffmpeg -i ../sintel-1080p.mp4 \
    -filter_complex "[0:v]split=3[v1][v2][v3]; \
        [v1]scale=w=640:h=360[v1out]; \
        [v2]scale=w=1280:h=720[v2out]; \
        [v3]scale=w=1920:h=1080[v3out]" \
```

```
   -map "[v1out]" -c:v:0 libx264 -b:v:0 800k  -maxrate:v:0 856k  -bufsize:v:0
1200k \
   -map "[v2out]" -c:v:1 libx264 -b:v:1 3000k -maxrate:v:1 3200k -bufsize:v:1
4500k \
   -map "[v3out]" -c:v:2 libx264 -b:v:2 5500k -maxrate:v:2 5900k -bufsize:v:2
8250k \
   -preset veryfast -g 48 -keyint_min 48 -sc_threshold 0 \
   -map a:0 -map a:0 -map a:0 -c:a aac -b:a:0 96k -b:a:1 128k -b:a:2 128k \
   -f hls -hls_time 4 -hls_playlist_type vod -hls_flags independent_segments \
   -hls_segment_filename "stream_%v/seg_%03d.ts" \
   -master_pl_name master.m3u8 \
   -var_stream_map "v:0,a:0,name:360p v:1,a:1,name:720p v:2,a:2,name:1080p" \
   "stream_%v/playlist.m3u8"
```

The command produces a directory tree with one master playlist, three variant playlists, and the transport stream segments for each variant.

```
hls/
### master.m3u8
### stream_360p/
#   ### playlist.m3u8
#   ### seg_000.ts
#   ### ...
### stream_720p/
#   ### playlist.m3u8
#   ### seg_000.ts
#   ### ...
### stream_1080p/
    ### playlist.m3u8
    ### seg_000.ts
    ### ...
```

Step 2: Upload the HLS package to the access point

Upload the package twice — once for playlists with a short TTL, and once for segments with a long, immutable TTL. Setting the correct `Content-Type` is important: most players require `application/vnd.apple.mpegurl` for `.m3u8` and `video/mp2t` for `.ts`.

Replace *`access-point-alias`* with your access point alias.

```
$ # Playlists: short TTL, m3u8 content type
```

```
aws s3 cp ~/media/hls/ "s3://access-point-alias/content/sintel/" \
    --recursive --exclude "*" --include "*.m3u8" \
    --content-type "application/vnd.apple.mpegurl" \
    --cache-control "max-age=60"

# Segments: long immutable TTL, ts content type
aws s3 cp ~/media/hls/ "s3://access-point-alias/content/sintel/" \
    --recursive --exclude "*" --include "*.ts" \
    --content-type "video/mp2t" \
    --cache-control "max-age=31536000,immutable"
```

Verify that both files uploaded with the expected content types and cache headers.

```
$ aws s3api head-object --bucket access-point-alias \
    --key content/sintel/master.m3u8 \
    --query '{ContentType:ContentType,CacheControl:CacheControl}'
```

Step 3: Create an origin access control

An origin access control (OAC) lets CloudFront sign requests to your access point so only CloudFront can fetch objects. Without OAC, viewers could bypass CloudFront by requesting objects directly from the access point endpoint.

```
$ aws cloudfront create-origin-access-control \
    --origin-access-control-config \
    'Name=fsxn-media-
oac,SigningProtocol=sigv4,SigningBehavior=always,OriginAccessControlOriginType=s3'
```

Note the `Id` in the response. You use it in the next step.

Step 4: Create the CloudFront distribution

Create a CloudFront distribution with the access point alias as the origin domain. Use the `CachingOptimized` managed cache policy, which honors the `Cache-Control` headers you set in Step 2.

1. Save the following configuration to a file named `dist.json`, replacing the placeholders.

```
{
    "CallerReference": "fsxn-media-1",
    "Comment": "FSx for ONTAP media delivery",
```

```
    "Enabled": true,
    "DefaultRootObject": "",
    "Origins": {
        "Quantity": 1,
        "Items": [{
            "Id": "fsxn-ap",
            "DomainName": "access-point-alias.s3.region.amazonaws.com",
            "S3OriginConfig": {"OriginAccessIdentity": ""},
            "OriginAccessControlId": "oac-id",
            "ConnectionAttempts": 3,
            "ConnectionTimeout": 10
        }]
    },
    "DefaultCacheBehavior": {
        "TargetOriginId": "fsxn-ap",
        "ViewerProtocolPolicy": "redirect-to-https",
        "AllowedMethods": {
            "Quantity": 2, "Items": ["GET", "HEAD"],
            "CachedMethods": {"Quantity": 2, "Items": ["GET", "HEAD"]}
        },
        "Compress": true,
        "CachePolicyId": "658327ea-f89d-4fab-a63d-7e88639e58f6"
    },
    "PriceClass": "PriceClass_100",
    "ViewerCertificate": {"CloudFrontDefaultCertificate": true}
}
```

Note

`PriceClass_100` uses CloudFront edge locations only in North America and Europe, which keeps cost lower for this tutorial. For global edge coverage, change the value to `PriceClass_All`. For more information, see Choosing the price class for a CloudFront distribution.

2. Create the distribution.

```
$ aws cloudfront create-distribution --distribution-config file://dist.json \
    --query 'Distribution.{Id:Id,DomainName:DomainName,ARN:ARN}'
```

Note the distribution ID, ARN, and domain name in the response. The distribution takes approximately five minutes to deploy. You can continue to Step 5 while it deploys.

Step 5: Attach an access point policy that allows CloudFront

The access point policy grants the CloudFront service principal permission to read objects, scoped to your specific distribution using the `AWS:SourceArn` condition.

1. Save the following policy to a file named `ap-policy.json`, replacing the placeholders.

```
{
    "Version": "2012-10-17",
    "Statement": [{
        "Sid": "AllowCloudFrontServicePrincipal",
        "Effect": "Allow",
        "Principal": {"Service": "cloudfront.amazonaws.com"},
        "Action": "s3:GetObject",
        "Resource": "arn:aws:s3:region:account-id:accesspoint/access-point-name/
object/*",
        "Condition": {
            "StringEquals": {
                "AWS:SourceArn": "arn:aws:cloudfront::account-
id:distribution/distribution-id"
            }
        }
    }]
}
```

2. Attach the policy to the access point.

```
$ aws s3control put-access-point-policy \
    --account-id account-id \
    --name access-point-name \
    --policy file://ap-policy.json
```

Step 6: Verify playback

Wait for the distribution to reach `Deployed` status.

```
$ aws cloudfront get-distribution --id distribution-id \
    --query 'Distribution.Status'
```

Fetch the master playlist through CloudFront.

```
$ curl -sS "https://distribution-domain/content/sintel/master.m3u8"
```

The response should list the three variants.

```
#EXTM3U
#EXT-X-VERSION:6
#EXT-X-STREAM-INF:BANDWIDTH=1031744,RESOLUTION=640x360,CODECS="avc1.64001e,mp4a.40.2"
stream_360p/playlist.m3u8

#EXT-X-STREAM-INF:BANDWIDTH=3497301,RESOLUTION=1280x720,CODECS="avc1.64001f,mp4a.40.2"
stream_720p/playlist.m3u8

#EXT-X-STREAM-INF:BANDWIDTH=6311285,RESOLUTION=1920x1080,CODECS="avc1.640028,mp4a.40.2"
stream_1080p/playlist.m3u8
```

Check the response headers for correct content type, cache control, and cache status.

```
$ curl -sSI "https://distribution-domain/content/sintel/stream_1080p/seg_000.ts"
```

A successful response shows `content-type: video/mp2t`, `cache-control: max-age=31536000,immutable`, and an `x-cache` header indicating whether the response came from the edge or the origin.

Finally, play the stream end to end with FFmpeg to confirm all segments fetch and decode correctly.

```
$ ffprobe -v error \
    -show_entries stream=codec_name,width,height \
    -show_entries format=duration \
    "https://distribution-domain/content/sintel/master.m3u8"
```

You can also open the master playlist URL in Safari or VLC, or embed it in a web page using a JavaScript player such as hls.js.

Extending the pattern

- **Use a custom domain with HTTPS.** Request an ACM certificate for your domain, attach it to the distribution, and add a CNAME record pointing to the CloudFront domain. For instructions, see Using custom URLs with CloudFront.

- **Protect premium content with signed URLs or signed cookies.** For content that requires authorization (subscription services, early-access previews, geo-fenced content), use CloudFront signed URLs or signed cookies. See Serving private content with signed URLs and signed cookies.
- **Invalidate the cache when you publish new content.** When you replace a playlist or upload a new HLS package, use `aws cloudfront create-invalidation` to remove the old versions from CloudFront edges. For immutable segments with long TTLs, invalidation is usually unnecessary because segment file names are unique per package.
- **Enable CORS for browser-based players.** If a browser-based HLS player on a different domain loads your stream, add `Access-Control-Allow-Origin` headers to responses using a CloudFront response headers policy.
- **Log viewer requests.** Enable CloudFront standard logging or real-time logs to capture viewer requests for analytics, billing, or abuse detection.

Troubleshooting

403 Forbidden from CloudFront

The access point policy is missing, does not include the CloudFront service principal, or the `AWS:SourceArn` condition references the wrong distribution ARN. Verify the policy with `aws s3control get-access-point-policy` and confirm the distribution ARN matches the one in your `aws cloudfront create-distribution` response.

Player loads the master playlist but fails to play

Check that segment files have `Content-Type: video/mp2t` and playlists have `Content-Type: application/vnd.apple.mpegurl`. Some players reject segments with generic content types. Re-upload with the correct `--content-type` flag.

New playlists take time to reach viewers

CloudFront caches playlists for the TTL set by your `Cache-Control` header. If you need a shorter TTL, re-upload the playlist with a smaller `max-age` value, or create an invalidation. Segments do not have this problem because their content does not change.

`x-cache: Miss from cloudfront` on every request

This is normal the first time a viewer in a region requests a file. CloudFront fetches from the origin on a miss and caches the response for the TTL. Subsequent requests for the same file from that edge location return `Hit from cloudfront`.

Direct access to the access point is denied

This is expected. The OAC requires SigV4-signed requests from CloudFront, and the access point policy restricts access to the CloudFront service principal. Viewers can only reach the content through the distribution domain.

Clean up

Disable and delete the distribution, then delete the remaining resources. The distribution must be disabled before it can be deleted, which takes a few minutes.

Disabling requires two values from `get-distribution-config`: the `ETag` for `--if-match`, and the inner `DistributionConfig` object for `--distribution-config` (the full response also contains the ETag, which `update-distribution` does not accept).

```
$ # Capture the current ETag and the DistributionConfig body
GET_ETAG=$(aws cloudfront get-distribution-config --id distribution-id \
    --query 'ETag' --output text)
aws cloudfront get-distribution-config --id distribution-id \
    --query 'DistributionConfig' --output json \
    | jq '.Enabled = false' > dist-updated.json

# Disable the distribution. The response returns a new ETag.
UPDATE_ETAG=$(aws cloudfront update-distribution --id distribution-id \
    --if-match "$GET_ETAG" --distribution-config file://dist-updated.json \
    --query 'ETag' --output text)

# Wait for Status to reach Deployed before deleting.
aws cloudfront get-distribution --id distribution-id \
    --query 'Distribution.Status'

# Delete the distribution using the ETag from the update call.
aws cloudfront delete-distribution --id distribution-id \
    --if-match "$UPDATE_ETAG"

# Fetch the OAC ETag, then delete the OAC.
OAC_ETAG=$(aws cloudfront get-origin-access-control --id oac-id \
    --query 'ETag' --output text)
aws cloudfront delete-origin-access-control --id oac-id \
    --if-match "$OAC_ETAG"
aws s3control delete-access-point-policy \
    --account-id account-id --name access-point-name
```

```
aws s3 rm "s3://access-point-alias/content/sintel/" --recursive
```

Troubleshooting S3 access point issues

This section describes symptoms, causes, and resolutions for when you encounter issues accessing your FSx data from S3 access points.

S3 access point is in MISCONFIGURED state

An S3 access point attachment can transition to the `MISCONFIGURED` state for the following reasons:

- **File system identity cannot be resolved** – The UNIX or Windows user associated with the access point can no longer be resolved on the file system. This can happen if the user is removed from the name service (for example, local files, LDAP, or Active Directory), or if the name service becomes unreachable. To resolve this, ensure the user exists and is resolvable on the SVM. For more information, see S3 access point creation failed due to file system user identity lookup failure.
- **Attached volume is offline or unmounted** – The volume that the access point is attached to is offline or has been unmounted (no longer has a junction path). To resolve this, bring the volume back online or remount it. See ONTAP documentation for more details.

Amazon FSx periodically checks for these conditions and automatically returns the access point to `AVAILABLE` when the underlying issue is resolved.

S3 access point creation failed due to file system user identity lookup failure

When creating and attaching an S3 Access Point, a `FileSystemIdentity` must be provided. You are responsible for configuring the provided UNIX or Windows user within ONTAP.

If a `UnixUser` is provided, ONTAP must be able to map the UnixUser name to UNIX UID/GIDs. ONTAP determines how to perform this mapping using the name service switch configuration.

```
> vserver services name-service ns-switch show
```

```
Vserver         Database       Order
--------------- ------------   ---------
svm_1           hosts          files,
```

```
                                dns
svm_1           group           files,
                                ldap
svm_1           passwd          files,
                                ldap
svm_1           netgroup        nis,
                                files
```

Please ensure your UnixUser has an entry in the `passwd` and `group` databases using a valid source (`files`,`ldap`, etc). The `files` source can be configured using the `vserver services name-service unix-user` and `vserver services name-service unix-group` commands. The `ldap` source can be configured using the `vserver services name-service ldap` command.

If a `WindowsUser` is provided, ONTAP must be able to find the WindowsUser name in the joined Active Directory domain.

To confirm if a provided UnixUser or WindowsUser is mapped correctly, using `fsxadmin` you can use the following command (replace `-unix-user-name` with `-win-name` for WindowsUsers):

```
> vserver services access-check authentication show-creds -
node FsxId0fd48ff588b9d3eee-01 -vserver svm_name -unix-user-name root -show-partial-
unix-creds true
```

Example successful output:

```
 UNIX UID: root

 GID: daemon
 Supplementary GIDs:
  daemon
```

Example unsuccessful output:

```
Error: Acquire UNIX credentials procedure failed
  [  2 ms] Entry for user-name: unmapped-user not found in the
           current source: FILES. Entry for user-name: unmapped-user
           not found in any of the available sources
**[     3] FAILURE: Unable to retrieve UID for UNIX user
**         unmapped-user
```

```
Error: command failed: Failed to resolve user name to a UNIX ID. Reason: "SecD Error:
 object not found".
```

An incorrect user mapping may result in `Access Denied` errors from S3. See example failure reasons below.

`Entry for user-name not found in the current source: LDAP`

If your `ns-switch` is configured to use an `ldap` source, please ensure ONTAP is configured to use your LDAP server properly. See NetApp's Technical Report for configuring LDAP for more information.

`RESULT_ERROR_DNS_CANT_REACH_SERVER` or `RESULT_ERROR_SECD_IN_DISCOVERY`

This error indicates an issue with the vserver's DNS configuration in ONTAP. Run the following to ensure your vserver's DNS is configured properly:

```
> dns check -vserver svm_name
```

`NT_STATUS_PENDING`

This error indicates an issue communicating with the domain controller. The underlying cause may be due to a lack of SMB credits. See NetApp KB for more information.

S3 access point creation failed because the volume is not mounted.

S3 access points can only be attached to FSx for ONTAP volumes that are mounted (have junction paths). This also applies to DP (Data Protection) volumes types. See ONTAP volume mount documentation for more information.

S3 access point creation failed because the S3 protocol is disabled on the SVM

S3 access points require the S3 protocol to be enabled on the Storage Virtual Machine (SVM). To enable the S3 protocol, run the following command in the ONTAP CLI using `fsxadmin`:

```
> vserver add-protocols -vserver svm_name -protocols s3
```

To verify the protocol is enabled:

```
> vserver show -vserver svm_name -fields allowed-protocols,disallowed-protocols
```

The file system is unable to handle S3 requests

If the S3 request volume for a particular workload exceeds the file system's capacity to handle the traffic, you may experience S3 request errors (for example, `Internal Server Error`, `503 Slow Down`, and `Service Unavailable`). You can proactively monitor and alarm on the performance of your file system using Amazon CloudWatch metrics (for example, `Network throughput utilization` and `CPU utilization`). If you observe degraded performance, you can resolve this issue by increasing the file system's throughput capacity.

Access Denied with default S3 access point permissions for automatically created service roles

Some S3-integrated AWS services will create a custom service role and customize the attached permissions to your specific usecase. When specifying your S3 access point alias as the S3 resource, those attached permissions may include your access point using a bucket ARN format (for example, `arn:aws:s3:::my-fsx-ap-foo7detztxouyjpwtu8krroppxytruse1a-ext-s3alias`) rather than the access point ARN format (for example, `arn:aws:s3:us-east-1:1234567890:accesspoint/my-fsx-ap`). To resolve this, modify the policy to use the ARN of the access point.

Accessing data from other AWS services

In addition to Amazon EC2, you can use other AWS services with your volumes to access your data.

Topics

- Using Amazon WorkSpaces with FSx for ONTAP
- Using Amazon Elastic Container Service with FSx for ONTAP
- Using Amazon Elastic VMware Service with FSx for ONTAP
- Using VMware Cloud with FSx for ONTAP

Using Amazon WorkSpaces with FSx for ONTAP

FSx for ONTAP can be used with Amazon WorkSpaces to provide shared network-attached storage (NAS) or to store roaming profiles for Amazon WorkSpaces accounts. After connecting to an SMB file share with a WorkSpaces instance, the user can create and edit files on the file share.

The following procedures shows how to use Amazon FSx with Amazon WorkSpaces to provide roaming profile and home folder access a consistent experience and to provide a shared team folder for Windows and Linux WorkSpaces users. If you are new to Amazon WorkSpaces, you can create your first Amazon WorkSpaces environment with the instructions in Get started with WorkSpaces Quick Setup in the *Amazon WorkSpaces Administration Guide*.

Topics

- Provide Roaming Profile support
- Provide a shared folder to access common files

Provide Roaming Profile support

You can use Amazon FSx to provide Roaming Profile support to users in your organization. A user will have permissions to access only their Roaming Profile. The folder will be automatically connected using Active Directory Group Policies. With a Roaming Profile, users' data and desktop settings are saved when they log off an Amazon FSx file share enabling documents and settings to be shared between different WorkSpaces instances, and automatically backed up using Amazon FSx daily automatic backups.

Step 1: Create a profile folder location for domain users using Amazon FSx

1. Create an FSx for ONTAP file system using the Amazon FSx console. For more information, see To create a file system (console).

> **Important**
>
> Each FSx for ONTAP file system has an endpoint IP address range from which the endpoints associated with the file system are created. For multi-AZ file systems, FSx for ONTAP chooses a default unused IP address range from 198.19.0.0/16 as the endpoint IP address range. This IP address range is also used by WorkSpaces for management traffic range, as described in IP address and port requirements for WorkSpaces in the *Amazon WorkSpaces Administration Guide*. As a result, to access your *multi-AZ* FSx for ONTAP file system from WorkSpaces, you must select an endpoint IP address range that does not overlap with 198.19.0.0/16.

2. If you don't have a storage virtual machine (SVM) joined to an Active Directory, create one now. For example, you can provision an SVM named `fsx` and set the security style to `NTFS`. For more information, see To create a storage virtual machine (console).
3. Create a volume for your SVM. For example, you can create a volume named `fsx-vol` which inherits the security style of your SVM's root volume. For more information, see To create a FlexVol volume (console).
4. Create an SMB share on your volume. For example, you can create a share called `workspace` on your volume named `fsx-vol`, in which you create a folder named `profiles`. For more information, see Managing SMB shares.
5. Access your Amazon FSx SVM from an Amazon EC2 instance running Windows Server or from a WorkSpace. For more information, see Accessing your FSx for ONTAP data.
6. You map your share to `Z:\` on your Windows WorkSpaces instance:



Step 2: Link the FSx for ONTAP file share to User Accounts

1. On your test user's WorkSpace, choose **Windows > System > Advanced System Settings**.
2. In **System Properties**, select the **Advanced** tab and press the **Settings** button in the **User Profiles** section. The logged-in user will have a profile type of `Local`.
3. Log out the test user from the WorkSpace.
4. Set the test user to have a roaming profile located on your Amazon FSx file system. In your administrator WorkSpaces, open a PowerShell console and use a command similar to the following example (which uses the `profiles` folder you previously created in Step 1):

```
Set-ADUser username -ProfilePath \\filesystem-dns-
name\sharename\foldername\username
```

For example:

```
Set-ADUser testuser01 -ProfilePath \\fsx.fsxnworkspaces.com\workspace\profiles
\testuser01
```

5. Log on to the test user WorkSpace.
6. In **System Properties**, select the **Advanced** tab and press the **Settings** button in the **User Profiles** section. The logged-in user will have a profile type of `Roaming`.



7. Browse the FSx for ONTAP shared folder. In the `profiles` folder, you'll see a folder for the user.



8. Create a document in the test user's `Documents` folder
9. Log out the test user from their WorkSpace.
10. If you log back on as the test user and browse to their profile store, you will see the document you created.



Provide a shared folder to access common files

You can use Amazon FSx to provide a shared folder to users in your organization. A shared folder can be used to store files used by your user community, such as demo files, code examples, and instruction manuals needed by all users. Typically, you have drives mapped for shared folders; however because mapped drives use letters, there's a limit to the number of shares you can have. This procedure creates an Amazon FSx shared folder that's available without a drive letter, giving you greater flexibility in assigning shares to teams.

To mount a shared folder for cross-platform access from both Linux and Windows WorkSpaces

1. From the **Taskbar**, choose **Places > Connect to Server**.

a. For **Server**, enter *file-system-dns-name*.

b. Set **Type** to `Windows share`.

c. Set **Share** to the name of the SMB share, such as `workspace`.

d. You can leave **Folder** as `/` or set it to a folder, such as a folder named `team-shared`.

e. For a Linux WorkSpace, you don't need to enter your user details if your Linux WorkSpace is in the same domain as the Amazon FSx share.

f. Choose **Connect**.



2. After the connection is made, you can see the shared folder (named `team-shared` in this example) in the SMB share named `workspace`.



Using Amazon Elastic Container Service with FSx for ONTAP

You can access your Amazon FSx for NetApp ONTAP file systems from an Amazon Elastic Container Service (Amazon ECS) Docker container on an Amazon EC2 Linux or Windows instance.

Mounting on an Amazon ECS Linux container

1. Create an ECS cluster using the EC2 Linux + Networking cluster template for your Linux containers. For more information, see Creating a cluster in the *Amazon Elastic Container Service Developer Guide*.
2. Create a directory on the EC2 instance for mounting the SVM volume as follows:

   ```
   sudo mkdir /fsxontap
   ```

3. Mount your FSx for ONTAP volume on the Linux EC2 instance by either using a user-data script during instance launch, or by running the following commands:

   ```
   sudo mount -t nfs svm-ip-address:/vol1 /fsxontap
   ```

4. Mount the volume using the following command:

   ```
   sudo mount -t nfs -o nfsvers=NFS_version svm-dns-name:/volume-junction-path /
   fsxontap
   ```

The following example uses sample values.

```
sudo mount -t nfs -o nfsvers=4.1
 svm-01234567890abdef0.fs-01234567890abcdef1.fsx.us-east-1.amazonaws.com:/vol1 /
fsxontap
```

You can also use the SVM's IP address instead of its DNS name.

```
sudo mount -t nfs -o nfsvers=4.1 198.51.100.1:/vol1 /fsxontap
```

5. When creating your Amazon ECS task definitions, add the following `volumes` and `mountPoints` container properties in the JSON container definition. Replace the `sourcePath` with the mount point and directory in your FSx for ONTAP file system.

```
{
    "volumes": [
        {
            "name": "ontap-volume",
            "host": {
                "sourcePath": "mountpoint"
            }
        }
    ],
    "mountPoints": [
        {
            "containerPath": "containermountpoint",
            "sourceVolume": "ontap-volume"
        }
    ],
    .
    .
    .
}
```

Mounting on an Amazon ECS Windows container

1. Create an ECS cluster using the EC2 Windows + Networking cluster template for your Windows containers. For more information, see Creating a cluster in the *Amazon Elastic Container Service Developer Guide*.

2. Add a domain-joined Windows EC2 instance to the ECS Windows cluster and map an SMB share.

   Launch an ECS optimized Windows EC2 instance that is joined to your Active Directory domain and initialize the ECS agent by running the following command.

   ```
   PS C:\Users\user> Initialize-ECSAgent -Cluster windows-fsx-cluster -
   EnableTaskIAMRole
   ```

   You can also pass the information in a script to the user-data text field as follows.

   ```
   <powershell>
   Initialize-ECSAgent -Cluster windows-fsx-cluster -EnableTaskIAMRole
   </powershell>
   ```

3. Create an SMB global mapping on the EC2 instance so that you can map your SMB share to a drive. Replace the values below netbios or DNS name for your FSx file system and share name. The NFS volume vol1 that was mounted on the Linux EC2 instance is configured as a CIFS share fsxontap on the FSx file system.

   ```
   vserver cifs share show -vserver svm08 -share-name fsxontap


                                       Vserver: svm08
                                         Share: fsxontap
                       CIFS Server NetBIOS Name: FSX0NTAPDEM0
                                          Path: /vol1
                                Share Properties: oplocks
                                                  browsable
                                                  changenotify
                                                  show-previous-versions
                               Symlink Properties: symlinks
                            File Mode Creation Mask: -
                        Directory Mode Creation Mask: -
                                       Share Comment: -
                                           Share ACL: Everyone / Full Control
                      File Attribute Cache Lifetime: -
                                         Volume Name: vol1
                                       Offline Files: manual
                      Vscan File-Operations Profile: standard
                  Maximum Tree Connections on Share: 4294967295
   ```

```
                    UNIX Group for File Create: -
```

4. Create the SMB global mapping on the EC2 instance using the following command:

```
New-SmbGlobalMapping -RemotePath \\fsxontapdemo.fsxontap.com\fsxontap -LocalPath Z:
```

5. When creating your Amazon ECS task definitions, add the following `volumes` and `mountPoints` container properties in the JSON container definition. Replace the `sourcePath` with the mount point and directory in your FSx for ONTAP file system.

```
{
    "volumes": [
        {
            "name": "ontap-volume",
            "host": {
                "sourcePath": "mountpoint"
            }
        }
    ],
    "mountPoints": [
        {
            "containerPath": "containermountpoint",
            "sourceVolume": "ontap-volume"
        }
    ],
    .
    .
    .
}
```

Using Amazon Elastic VMware Service with FSx for ONTAP

You can use FSx for ONTAP as an external datastore for Amazon Elastic VMware Service (Amazon EVS) Software-Defined Data Centers (SDDCs). For more information, see Run high-performance workloads with Amazon FSx for NetApp ONTAP. For detailed instructions, see Configure Amazon FSx for NetApp ONTAP as an NFS datastore and Configure Amazon FSx for NetApp ONTAP as an iSCSI datastore.

Using VMware Cloud with FSx for ONTAP

You can use FSx for ONTAP as an external datastore for VMware Cloud on AWS Software-Defined Data Centers (SDDCs). For more information, see Configure Amazon FSx for NetApp ONTAP as External Storage and VMware Cloud on AWS with Amazon FSx for NetApp ONTAP Deployment Guide.

Availability, durability, and deployment options

Amazon FSx for NetApp ONTAP uses Single-AZ and Multi-AZ deployment types. You can choose from four options: Single-AZ 1, Single-AZ 2, Multi-AZ 1, and Multi-AZ 2. This topic describes the availability and durability features of each deployment type to help you choose the one that is right for your workloads. For information on the service's availability SLA (Service Level Agreement), see Amazon FSx Service Level Agreement.

Topics

- Choosing a file system deployment type
- Choosing a file system generation
- Failover process for FSx for ONTAP
- Network resources

Choosing a file system deployment type

The availability and durability features of Single-AZ and Multi-AZ file system deployment types are described in the following sections.

Single-AZ deployment types

You can choose between Single-AZ 1 and Single-AZ 2 for your Single-AZ file system. Single-AZ 1 is a first-generation file system with one high-availability (HA) pair, whereas Single-AZ 2 is a second-generation file system with 1–12 HA pairs. For more information, see Choosing a file system generation.

When you create a Single-AZ file system, Amazon FSx automatically provisions one to twelve pairs of file servers in an active-standby configuration, with the active and standby file servers in each pair located in separate fault domains within a single Availability Zone in the AWS Region. During planned file system maintenance or an unplanned service disruption of any active file server, Amazon FSx automatically and independently fails over that high-availability (HA) pair to the standby file server, typically within a few seconds. During a failover, you continue to have access to your data without manual intervention.

To ensure high availability, Amazon FSx continuously monitors for hardware failures, and automatically replaces infrastructure components in the event of a failure. To achieve high durability, Amazon FSx automatically replicates your data within an Availability Zone to protect it

from component failure. In addition, you have the option to configure automatic daily backups of your file system data. These backups are stored across multiple Availability Zones to provide multi-AZ resiliency for all backup data.

Single-AZ file systems are designed for use cases that do not require the data resiliency model of a Multi-AZ file system. They provide a cost-optimized solution for use cases such as development and test environments, or storing secondary copies of data that is already stored on premises or in other AWS Regions, by only replicating data within a single Availability Zone.

The following diagram illustrates the architecture for an FSx for ONTAP Single-AZ first-generation file system.



Multi-AZ deployment types

You can choose between Multi-AZ 1 and Multi-AZ 2 for your Multi-AZ file system. Multi-AZ 1 is a first-generation file system and Multi-AZ 2 is a second-generation file system. Both options have one HA pair. For more information, see Choosing a file system generation.

Multi-AZ file systems support all the availability and durability features of Single-AZ file systems. In addition, they are designed to provide continuous availability to data even when an Availability Zone is unavailable. Multi-AZ deployments have a single HA pair of file servers, the standby file

server is deployed in a different Availability Zone from the active file server in the same AWS Region. Any changes written to your file system are synchronously replicated across Availability Zones to the standby.

Multi-AZ file systems are designed for use cases such as business-critical production workloads that require high availability to shared ONTAP file data and need storage with built-in replication across Availability Zones. The following diagram illustrates the architecture for an FSx for ONTAP Multi-AZ first-generation file system.



Choosing a file system generation

The following table illustrates the differences between first and second-generation Single-AZ and Multi-AZ FSx for ONTAP file systems.

FSx for ONTAP file system generations

Dimension	First-generation	Second-generation (single HA pair)	Second-generation (multi-pair)
Deployment type	SINGLE_AZ_1 MULTI_AZ_1	SINGLE_AZ_2 MULTI_AZ_2	SINGLE_AZ_2
HA pairs	1 HA pair		1–12 HA pairs
SSD storage	Minimum: 1 TiB Maximum: 192 TiB	Minimum: 1 TiB Maximum: 512 TiB	Minimum: 1 TiB (per HA pair) Maximum: 1 PiB (total)
SSD IOPS	Minimum: 3 IOPS/GIB of SSD Maximum: 160,000	Minimum: 3 IOPS/GIB of SSD Maximum: 200,000	Minimum: 3 IOPS/GIB of SSD Maximum: 2,400,000 (200,000 per HA pair)
Throughput capacity	128 MBps; 256 MBps; 512 MBps; 1,024 MBps;2,048 MBps; 4,096 MBps	384 MBps; 768 MBps; 1,536 MBps; 3,072 MBps; 6,144 MBps	1,536 MBps (per HA pair); 3,072 MBps (per HA pair); 6,144 MBps (per HA pair)

Note

You can't change your file system's deployment type after creation. If you want to change the deployment type (for example, to move from Single-AZ 1 to Single-AZ 2), you can back up your data and restore it on a new file system. You can also migrate your data with NetApp SnapMirror, with AWS DataSync, or with a third-party data copying tool. For more information, see Migrating to FSx for ONTAP using NetApp SnapMirror and Migrating to FSx for ONTAP using AWS DataSync.

Failover process for FSx for ONTAP

Single-AZ and Multi-AZ file systems automatically fail over a given HA pair from the preferred or active file server to the standby file server if any of the following conditions occur:

- The preferred or active file server becomes unavailable
- The file system's throughput capacity is changed
- The preferred or active file server undergoes planned maintenance
- An Availability Zone outage occurs (Multi-AZ file systems only)

> **Note**
>
> For second-generation file systems with multiple HA pairs, each HA pair's failover behavior is independent. If the preferred file server for one HA pair is unavailable, only that HA pair will fail over to its standby file server.

When failing over from one file server to another, the new active file server automatically begins serving all file system read and write requests to that HA pair. For Multi-AZ file systems, when the preferred file server is fully recovered and becomes available, Amazon FSx automatically fails back to it, with failback usually completing in less than 60 seconds. For Single-AZ and Multi-AZ file systems, a failover typically completes in less than 60 seconds from the detection of the failure on the active file server to the promotion of the standby file server to active status. Because the endpoint IP address that clients use to access data over NFS or SMB remains the same, failovers are transparent to Linux, Windows, and macOS applications, which resume file system operations without manual intervention.

To ensure that failovers are transparent to clients connected to your FSx for ONTAP Single-AZ and Multi-AZ file systems, see Accessing data from within the AWS Cloud.

Testing failover on a file system

You can test failover on your file system by modifying its throughput capacity. When you modify your file system's throughput capacity, Amazon FSx switches out the file system's file servers serially. File systems automatically fail over to the secondary server while Amazon FSx replaces the preferred file server first. Once updated, the file system automatically fails back to the new primary server and Amazon FSx replaces the secondary file server.

You can monitor the progress of the throughput capacity update request in the Amazon FSx console, the CLI, and the API. For more information about modifying your file system's throughput capacity and monitoring the progress of the request, see Managing throughput capacity.

Network resources

This section describes the network resources consumed by Single-AZ and Multi-AZ file systems.

Subnets

When you create a Single-AZ file system, you specify a single subnet for the file system. The subnet you choose defines the Availability Zone in which the file system is created. When you create a Multi-AZ file system, you specify two subnets, one for the preferred file server, and one for the standby file server. The two subnets you choose must be in different Availability Zones within the same AWS Region. For more information about Amazon VPC, see What is Amazon VPC? in the *Amazon Virtual Private Cloud User Guide*.

> **Note**
>
> Regardless of the subnet that you specify, you can access your file system from any subnet within the file system's VPC.

File system elastic network interfaces

For Single-AZ file systems, Amazon FSx provisions two elastic network interfaces (ENI) in the subnet that you associate with your file system. For Multi-AZ file systems, Amazon FSx also provisions two ENIs, one in each of the subnets that you associate with your file system. Clients communicate with your Amazon FSx file system using the elastic network interface. The network interfaces are considered to be within the service scope of Amazon FSx, despite being part of your account's VPC. Multi-AZ file systems use floating internet protocol (IP) addresses so that connected clients seamlessly transition between the preferred and standby file servers during a failover event.

> **Warning**
>
> - You must not modify or delete the elastic network interfaces associated with your file system. Modifying or deleting the network interface can cause a permanent loss of connection between your VPC and your file system.

- The elastic network interfaces associated with your file system will have routes automatically created and added to your default VPC and subnet route tables. Modifying or deleting these routes may cause temporary or permanent loss of connectivity for your file system clients.

The following table summarizes the subnet, elastic network interface, and IP address resources for each of the FSx for ONTAP file system deployment types:

	First-generation Single-AZ	**Second-generation Single-AZ**	**Multi-AZ**
Number of subnets	1	1	2
Number of elastic network interfaces	2	2 per HA pair	2
Number of IP addresses per ENI	1 + the number of SVMs in the file system	HA pair count + HA pair count multiplied by the number of SVMs in the file system	1 + the number of SVMs in the file system
Number of VPC route table routes	N/A	N/A	1 + the number of SVMs in the file system

Once a file system or SVM is created, its IP addresses doesn't change until the file system is deleted.

Important

Amazon FSx doesn't support accessing file systems from, or exposing file systems to the public Internet. Amazon FSx automatically detaches any Elastic IP address which is a public IP address reachable from the Internet, that gets attached to a file system's elastic network interface.

Amazon FSx for NetApp ONTAP performance

Following is an overview of Amazon FSx for NetApp ONTAP file system performance, with a discussion of the available performance and throughput options and useful performance tips.

Topics

- How performance is measured for FSx for ONTAP file systems
- Performance details
- Impact of deployment type on performance
- Impact of storage capacity on performance
- Impact of throughput capacity on performance
- Example: storage capacity and throughput capacity

How performance is measured for FSx for ONTAP file systems

File system performance is measured by its latency, throughput, and I/O operations per second (IOPS).

Latency

Amazon FSx for NetApp ONTAP provides sub-millisecond file operation latencies with solid state drive (SSD) storage, and tens of milliseconds of latency for capacity pool storage. Above that, Amazon FSx has two layers of read caching on each file server—NVMe (non-volatile memory express) drives and in-memory—to provide even lower latencies when you access your most frequently-read data.

Throughput and IOPS

Each Amazon FSx file system provides up to tens of GBps of throughput and millions of IOPS. The specific amount of throughput and IOPS that your workload can drive on your file system depends on the total throughput capacity and storage capacity configuration of your file system, along with the nature of your workload, including the size of the active working set.

SMB Multichannel and NFS nconnect support

With Amazon FSx, you can configure SMB Multichannel to provide multiple connections between ONTAP and clients in a single SMB session. SMB Multichannel uses multiple network connections between the client and server simultaneously to aggregate network bandwidth for maximal utilization. For information on using the NetApp ONTAP CLI to configure SMB Multichannel, see Configuring SMB Multichannel for performance and redundancy.

NFS clients can use the `nconnect` mount option to have multiple TCP connections (up to 16) associated with a single NFS mount. Such an NFS client multiplexes file operations onto multiple TCP connections in a round-robin fashion and thus obtains higher throughput from the available network bandwidth. NFSv3 and NFSv4.1+ support `nconnect`. Amazon EC2 instance network bandwidth describes the full duplex 5 Gbps per network flow bandwidth limit. You can overcome this limit by using multiple network flows with `nconnect` or SMB multichannel. See your NFS client documentation to confirm whether `nconnect` is supported in your client version. For more information about NetApp ONTAP support for `nconnect`, see ONTAP support for NFSv4.1.

Jumbo frames

To achieve the maximum read or write throughput, we recommend enabling jumbo frames on all network interfaces in the data path to your Amazon FSx file system, including your client EC2 instances. The default maximum transmission unit (MTU) setting for network interfaces on your FSx for ONTAP file system is 9,001 bytes.

Performance details

To understand the Amazon FSx for NetApp ONTAP performance model in detail, you can examine the architectural components of an Amazon FSx file system. Your client compute instances, whether they exist in AWS or on-premises, access your file system through one or multiple elastic network interfaces (ENI). These network interfaces reside in the Amazon VPC that you associate with your file system. Behind each file system ENI is a NetApp ONTAP file server that is serving data over the network to the clients accessing the file system. Amazon FSx provides a fast in-memory cache and NVMe cache on each file server to enhance performance for the most frequently accessed data. Attached to each file server are the SSD disks hosting your file system data.

These components are illustrated in the following diagram.



Corresponding with these architectural components–network interface, in-memory cache, NVMe cache, and storage volumes–are the primary performance characteristics of an Amazon FSx for NetApp ONTAP file system that determine the overall throughput and IOPS performance.

- Network I/O performance: throughput/IOPS of requests between the clients and the file server (in aggregate)
- In-memory and NVMe cache size on the file server: size of active working set that can be accommodated for caching
- Disk I/O performance: throughput/IOPS of requests between the file server and the storage disks

There are two factors that determine these performance characteristics for your file system: the total amount of SSD IOPS and throughput capacity that you configure for it. The first two performance characteristics – network I/O performance and in-memory and NVMe cache size – are solely determined by throughput capacity, while the third one – disk I/O performance – is determined by a combination of throughput capacity and SSD IOPS.

File-based workloads are typically spiky, characterized by short, intense periods of high I/O with plenty of idle time between bursts. To support spiky workloads, in addition to the baseline speeds

that a file system can sustain 24/7, Amazon FSx provides the capability to burst to higher speeds for periods of time for both network I/O and disk I/O operations. Amazon FSx uses a network I/O credit mechanism to allocate throughput and IOPS based on average utilization — file systems accrue credits when their throughput and IOPS usage is below their baseline limits, and can use these credits when they perform I/O operations.

> **Note**
>
> For iSCSI and NVMe/TCP SAN protocols, sequential read client operations can achieve up to the file system's maximum network I/O burst or baseline throughput.

Write operations use twice as much network bandwidth as read operations. A write operation has to be replicated on the secondary file server, so a single write operation results in twice the amount of network throughput.

Impact of deployment type on performance

You can create Single-AZ and Multi-AZ file systems with FSx for ONTAP. First-generation file systems (both Single-AZ and Multi-AZ) and second-generation Multi-AZ file systems are powered by one high-availability (HA) pair. Second-generation Single-AZ file systems are powered by up to 12 HA pairs. For more information, see Managing high-availability (HA) pairs.

FSx for ONTAP Multi-AZ and Single-AZ file systems provide consistent sub-millisecond file operation latencies with SSD storage and tens of milliseconds of latency with capacity pool storage. Additionally, file systems that meet the following requirements provide an NVMe read cache to reduce read latencies and increase IOPS for frequently-read data:

- Multi-AZ 1 and Multi-AZ 2 file systems
- Single-AZ 1 file systems created after November 28, 2022 with at least 2 GBps of throughput capacity
- Single-AZ 2 file systems with at least 6 GBps of throughput capacity per pair

> **Note**
>
> For second-generation file systems (Single-AZ 2 and Multi-AZ 2), using an NVMe cache can result in your workload achieving less total throughput for high-throughput or large I/O

workloads. If you have a throughput-bound workload, we recommend disabling the NVMe cache. For more information, see Managing the NVMe cache.

The following tables show the amount of throughput capacity that file systems can scale up to depending on factors such as the number of high availability (HA) pairs and AWS Regions availability.

First-generation file systems

These performance specifications apply to first-generation Single-AZ and Multi-AZ file systems.

Maximum throughput from SSD storage per HA pair for first-generation file systems

	US East (Ohio) Region, US East (N. Virginia) Region, US West (Oregon) Region, and Europe (Ireland)		**All other AWS Regions where FSx for ONTAP is available**	
	Read throughput (MBps)	**Write throughput (MBps)**	**Read throughput (MBps)**	**Write throughput (MBps)**
Single-AZ	4,096[1]	1,000	2,048	750
Multi-AZ	4,096[1]	1,800	2,048	1,300

Note

[1] To provision 4 GBps of throughput capacity, your file system must be configured with a minimum of 5,120 GiB of SSD storage capacity and 160,000 SSD IOPS.

Second-generation file systems

These performance specifications apply to second-generation Single-AZ and Multi-AZ file systems. Generally, second-generation file systems can deliver the full provisioned throughout capacity for reads and up to a third of the provisioned throughput capacity for writes. The exception is the 6,144 MB/s option, which is listed in this table.

Maximum throughput from SSD storage per HA pair for second-generation file systems

	Read throughput (MBps)	Write throughput (MBps)
Single-AZ	6,144[1]	1,024[1]
Multi-AZ	6,144	2,048

Note

[1] Per HA pair (up to 12). For more information, see Managing high-availability (HA) pairs.

Impact of storage capacity on performance

The maximum disk throughput and IOPS levels your file system can achieve is the lower of:

- the disk performance level provided by your file servers, based on the throughput capacity you select for your file system
- the disk performance level provided by the number of SSD IOPS you provision for your file system

By default, your file system's SSD storage provides up to the following levels of disk throughput and IOPS:

- Disk throughput (MBps per TiB of storage): 768
- Disk IOPS (IOPs per TiB of storage): 3,072

Note

When decreasing SSD storage capacity on a second-generation file system, most workloads experience minimal performance impact. However, write-heavy workloads might experience a temporary performance degradation. You might also experience brief I/O pauses (up to 60 seconds) as client access is redirected to new disks.

To minimize performance impact, ensure that ongoing workloads don't consistently consume more than 50% CPU, 50% disk throughput, or 50% SSD IOPS before initiating an SSD decrease operation. For more information about decreasing SSD storage capacity, see When to decrease SSD storage capacity.

Impact of throughput capacity on performance

Every Amazon FSx file system has a throughput capacity that you configure when the file system is created. Your file system's throughput capacity determines the level of network I/O performance, or the speed at which each of the file servers that are hosting your file system can serve file data over the network to clients accessing it. Higher levels of throughput capacity come with more memory and non-volatile memory express (NVMe) storage for caching data on each file server, and higher levels of disk I/O performance supported by each file server.

You can optionally provision a higher level of SSD IOPS when creating your file system. The maximum level of SSD IOPS that your file system can achieve is also dictated by your file system's throughput capacity, even when provisioning additional SSD IOPS.

The following tables show the full set of specifications for throughput capacity, along with baseline and burst levels, and amount of memory for caching on the file server in the corresponding AWS Regions.

First-generation Single-AZ file system

These performance specifications apply to first-generation Single-AZ file systems created after November 28, 2022 in the specified AWS Regions.

Performance specifications for file systems in the following AWS Regions: US East (N. Virginia), US East (Ohio), US West (Oregon), and Europe (Ireland)

FSx throughput capacity (MBps)	Network throughput capacity (MBps)		Network IOPS	In-memory caching (GB)	NVMe read caching (GB)	Disk throughput (MBps)		SSD drive IOPS *	
	Baseline	Burst				Baseline	Burst	Baseline	Burst

FSx throughput capacity (MBps)	Network throughput capacity (MBps)		Network IOPS	In-memory caching (GB)	NVMe read caching (GB)	Disk throughput (MBps)		SSD drive IOPS *	
128	188	1,500	Tens of thousands baseline	16	–	128	1,250	6,000	40,000
256	375	1,500		32	–	256	1,250	12,000	40,000
512	750	1,500	Hundreds of thousands baseline	64	–	512	1,250	20,000	40,000
1,024	1,500	–		128	–	1,024	1,250	40,000	–
2,048	3,125	–		256	1,900	2,048	–	80,000	–
4,096	6,250	–		512	5,400	4,096	–	160,000	–

Note

* Your SSD IOPS are only used when you access data that is not cached in your file server's in-memory cache or NVMe cache.

These performance specifications apply to first-generation Single-AZ file systems in all other AWS Regions where FSx for ONTAP is available.

Performance specifications for file systems in all other AWS Regions where FSx for ONTAP is available

FSx throughput capacity (MBps)	Network throughput capacity (MBps)		Network IOPS	In-memory caching (GB)	Disk throughput (MBps)		SSD drive IOPS *	
	Baseline	Burst			Baseline	Burst	Baseline	Burst

FSx throughput capacity (MBps)	Network throughput capacity (MBps)		Network IOPS	In-memory caching (GB)	Disk throughput (MBps)		SSD drive IOPS *	
128	150	1,250	Tens of thousands baseline	16	128	600	6,000	18,750
256	300	1,250		32	256	600	12,000	18,750
512	625	1,250	Hundreds of thousands baseline	64	512	–	18,750	–
1,024	1,500	–		128	1,024	–	40,000	–
2,048	3,125	–		256	2,048	–	80,000	–

> **Note**
>
> * Your SSD IOPS are only used when you access data that is not cached in your file server's in-memory cache or NVMe cache.

Second-generation Single-AZ file system

These performance specifications apply to second-generation Single-AZ file systems.

Performance specifications for second-generation Single-AZ file systems

FSx throughput capacity (MBps)	Network throughput capacity (MBps)		Network IOPS	In-memory caching (GB)	NVMe caching (GB)	Disk throughput (MBps)		SSD drive IOPS *	
	Baseline	Burst				Baseline	Burst	Baseline	Burst
384**	781	6,250	Hundreds of	16	–	384	3,125	12,500	65,000
768**	1,563	6,250		32	–	768	3,125	25,000	65,000

FSx throughput capacity (MBps)	Network throughput capacity (MBps)		Network IOPS	In-memory caching (GB)	NVMe caching (GB)	Disk throughput (MBps)		SSD drive IOPS *	
1,536	3,125	6,250	thousands baseline	64	–	1,536	3,125	50,000	65,000
3,072	6,250	–		128	–	3,072	–	100,000	–
6,144	12,500	–		256	1,900	6,144	–	200,000	–

Note

* Your SSD IOPS are only used when you access data that is not cached in your file server's in-memory cache or NVMe cache.
** Second-generation Single-AZ file systems support 384 and 768 throughput capacities, but only with one HA pair. To add HA pairs, your file system must be configured with at least 1,536 MBps of throughput capacity.

First-generation Multi-AZ file system

These performance specifications apply to first-generation Multi-AZ file systems created after November 28, 2022 in the specified AWS Regions.

Performance specifications for file systems in the following AWS Regions: US East (N. Virginia), US East (Ohio), US West (Oregon), and Europe (Ireland)

FSx throughput capacity (MBps)	Network throughput capacity (MBps)		Network IOPS	In-memory caching (GB)	NVMe caching (GB)	Disk throughput (MBps)		SSD drive IOPS *	
	Baseline	Burst				Baseline	Burst	Baseline	Burst
128	188	1,500	Tens of	16	238	128	1,250	6,000	40,000

FSx throughput capacity (MBps)	Network throughput capacity (MBps)		Network IOPS	In-memory caching (GB)	NVMe caching (GB)	Disk throughput (MBps)		SSD drive IOPS *	
256	375	1,500	thousands baseline	32	475	256	1,250	12,000	40,000
512	750	1,500	Hundreds of thousands baseline	64	950	512	1,250	20,000	40,000
1,024	1,500	–		128	1,900	1,024	1,250	40,000	–
2,048	3,125	–		256	3,800	2,048	–	80,000	–
4,096	6,250	–		512	7,600	4,096	–	160,000	–

Note

* Your SSD IOPS are only used when you access data that is not cached in your file server's in-memory cache or NVMe cache.

These performance specifications apply to first-generation Multi-AZ file systems in all other AWS Regions where FSx for ONTAP is available.

Performance specifications for file systems in all other AWS Regions where FSx for ONTAP is available

FSx throughput capacity (MBps)	Network throughput capacity (MBps)		Network IOPS	In-memory caching (GB)	NVMe caching (GB)	Disk throughput (MBps)		SSD drive IOPS *	
	Baseline	Burst				Baseline	Burst	Baseline	Burst

FSx throughput capacity (MBps)	Network throughput capacity (MBps)		Network IOPS	In-memory caching (GB)	NVMe caching (GB)	Disk throughput (MBps)		SSD drive IOPS *	
128	150	1,250	Tens of thousands baseline	16	150	128	600	6,000	18,750
256	300	1,250		32	300	256	600	12,000	18,750
512	625	1,250	Hundreds of thousands baseline	64	600	512	–	18,750	–
1,024	1,500	–		128	1,200	1,024	–	40,000	–
2,048	3,125	–		256	2,400	2,048	–	80,000	–

Note

* Your SSD IOPS are only used when you access data that is not cached in your file server's in-memory cache or NVMe cache.

Second-generation Multi-AZ file systems

These performance specifications apply to second-generation Multi-AZ file systems.

Performance specifications for second-generation Multi-AZ file systems

FSx throughput capacity (MBps)	Network throughput capacity (MBps)		Network IOPS	In-memory caching (GB)	NVMe caching (GB)	Disk throughput (MBps)		SSD drive IOPS *	
	Baseline	Burst				Baseline	Burst	Baseline	Burst
384	781	6,250	Hundreds of	16	237	384	3,125	12,500	65,000

FSx throughput capacity (MBps)	Network throughput capacity (MBps)		Network IOPS	In-memory caching (GB)	NVMe caching (GB)	Disk throughput (MBps)		SSD drive IOPS *	
768	1,563	6,250	thousands baseline	32	474	768	3,125	25,000	65,000
1,536	3,125	6,250		64	950	1,536	3,125	50,000	65,000
3,072	6,250	–		128	1,900	3,072	–	100,000	–
6,144	12,500	–		256	3,800	6,144	–	200,000	–

Note

* Your SSD IOPS are only used when you access data that is not cached in your file server's in-memory cache or NVMe cache.

Example: storage capacity and throughput capacity

The following example illustrates how storage capacity and throughput capacity impact file system performance.

A first-generation file system that is configured with 2 TiB of SSD storage capacity and 512 MBps of throughput capacity has the following throughput levels:

- Network throughput – 625 MBps baseline and 1,250 MBps burst (see throughput capacity table)
- Disk throughput – 512 MBps baseline and 600 MBps burst.

Your workload accessing the file system will therefore be able to drive up to 625 MBps baseline and 1,250 MBps burst throughput for file operations performed on actively accessed data cached in the file server in-memory cache and NVMe cache.

Administering FSx for ONTAP resources

Using the AWS Management Console, AWS CLI, and ONTAP CLI and API, you can perform the following administrative actions for FSx for ONTAP resources:

- Creating, listing, updating, and deleting file systems, storage virtual machines (SVMs), volumes, backups, and tags.
- Managing access, administrative accounts and passwords, password requirements, SMB and iSCSI protocols, network accessibility for the mount targets of existing file systems

Topics

- Managing storage capacity
- Managing FSx for ONTAP file systems
- Managing FSx for ONTAP storage virtual machines
- Managing FSx for ONTAP volumes
- Creating an iSCSI LUN
- Optimizing performance with Amazon FSx maintenance windows
- Managing throughput capacity
- Managing SMB shares
- Managing FSx for ONTAP resources using NetApp applications
- Tagging Amazon FSx resources

Managing storage capacity

Amazon FSx for NetApp ONTAP provides a number of storage-related features you can use to manage storage capacity on your file system.

Topics

- FSx for ONTAP storage tiers
- Choosing the right amount of file system SSD storage
- File system storage capacity and IOPS
- Volume storage capacity

FSx for ONTAP storage tiers

Storage tiers are the physical storage media for an Amazon FSx for NetApp ONTAP file system. FSx for ONTAP offers the following storage tiers:

- *SSD tier* – The user-provisioned, high-performance solid-state drive (SSD) storage that's purpose-built for the active portion of your data set.
- *Capacity pool tier* – Fully elastic storage that automatically scales to petabytes in size, and is cost-optimized for your infrequently accessed data.

An FSx for ONTAP volume is a virtual resource that, similar to folders, doesn't consume storage capacity. The data that you store—and that consumes physical storage—lives inside volumes. When you create a volume, you specify its size—which you can modify after it's created. FSx for ONTAP volumes are thin provisioned, and file system storage is not reserved in advance. Instead, SSD and capacity pool storage are allocated dynamically, as needed. A tiering policy, which you configure at the volume level, determines if and when data that's stored in the SSD tier transitions to the capacity pool tier.

The following diagram illustrates an example of data laid out across multiple FSx for ONTAP volumes in a file system.



The following diagram illustrates how the file system's physical storage capacity is consumed by the data in the four volumes in the previous diagram.



You can reduce your storage costs by choosing the tiering policy that best meets the requirements for each volume on your file system. For more information, see Volume data tiering.

Choosing the right amount of file system SSD storage

When choosing amount of SSD storage capacity for your FSx for ONTAP file system, you need to keep in mind the following items that impact the amount of SSD storage available for storing your data:

- Storage capacity reserved for the NetApp ONTAP software overhead.
- File metadata
- Recently written data
- Files that you intend to store on SSD storage, whether it's data that hasn't hit its cooling period, or data that you recently read that was retrieved back to SSD.

How SSD storage is used

Your file system's SSD storage is used for a combination of NetApp ONTAP software (overhead), file metadata, and your data.

NetApp ONTAP software overhead

Like other NetApp ONTAP file systems, up to 16% of a file system's SSD storage capacity is reserved for ONTAP overhead, which means it's not available for storing your files. The ONTAP overhead is allocated as follows:

- 11% is reserved for NetApp ONTAP software. For file systems with over 30 tebibytes (TiB) of SSD storage capacity, 6% is reserved.
- 5% is reserved for aggregate snapshots, which are required to synchronize data between both of a file system's file servers.

File metadata

File metadata typically consumes 3-7% of the storage capacity that is consumed by the files. This percentage depends on the average file size (a smaller average file size requires more metadata), and the amount of storage efficiency savings achieved on your files. Note that file metadata doesn't benefit from storage efficiency savings. You can use the following guidelines for estimating the amount of SSD storage used for metadata on your file system.

Average file size	Size of metadata as a percentage of file data
4 KB	7%
8 KB	3.5%
32 KB or greater	1-3%

When sizing the amount of SSD storage capacity you need for the metadata of files you plan to store on the capacity pool tier, we recommend using a conservative ratio of 1 GiB of SSD storage for every 10 GiB of data you plan to store on the capacity pool tier.

File data stored on your SSD tier

In addition to your active data set and all file metadata, all data written to your file system is initially written to the SSD tier before being tiered-off to capacity pool storage. This is true regardless of the volume's tiering policy, with the exception that data is written directly to capacity pool storage when using SnapMirror on a volume configured with an **All** data tiering policy.

Random reads from the capacity pool tier are cached in the SSD tier, as long as the SSD tier is under 90% utilization. For more information, see Volume data tiering.

Recommended SSD capacity utilization

We recommend that you do not exceed 80% utilization of your SSD storage tier on an ongoing basis. For second-generation file systems, we additionally recommend that you don't exceed 80% utilization of any of your file system's aggregates on an ongoing basis. These recommendations is consistent with NetApp's recommendation for ONTAP. Because your file system's SSD tier is also used for staging writes to, and for random reads from, the capacity pool tier, any sudden changes in access patterns can quickly cause the utilization of your SSD tier to increase.

At 90% SSD utilization, data read from the capacity pool tier is no longer cached on the SSD tier so that the remaining SSD capacity is preserved for any new data that is written to the file system. This causes repeat reads of the same data from the capacity pool tier to be read from capacity pool storage instead of being cached and read from the SSD tier, which can impact the throughput capacity your file system.

All tiering functionality stops when the SSD tier is at or above 98% utilization. For more information, see Tiering thresholds.

Storage efficiency

NetApp ONTAP offers block-level storage efficiency features at the volume level that include compression, compaction, and deduplication. These features can save you up to 65% in storage capacity for general file shares, without sacrificing performance. You can enable storage efficiency on a per volume basis. These features reduce the amount of storage capacity that your data consumes, allowing you to consume less storage spaces in SSD, capacity pool, and backups storage. You can enable compression and deduplication on each volume for data in SSD storage. Storage savings from compression and deduplication in SSD storage is preserved when data is tiered to capacity pool storage. Storage efficiency is always enabled for backup data, regardless of your file system's storage efficiency configuration.

The following table shows examples of typical storage savings.

	Compression only	Deduplication only	Compression & deduplication
General-purpose file shares	50%	30%	65%

	Compression only	Deduplication only	Compression & deduplication
Virtual servers and desktops	55%	70%	70%
Databases	65-70%	0%	65-70%
Engineering data	55%	30%	75%
Geoseismic data	40%	3%	40%

For most workloads, enabling compression and deduplication will not adversely impact file system performance. For most workloads, compression increases overall performance. To provide fast reads and writes from RAM cache, FSx for ONTAP file servers are equipped with higher levels of network bandwidth on the front-end network interface cards (NICs) than is available between the file servers and storage disks. Since data compression reduces the amount of data sent between file servers and storage disks, for most workloads, you will see an increase in overall file system throughput capacity when using data compression. Increases in throughput capacity related to data compression will be capped once you saturate the front-end NIC of your file system.

Amazon FSx for NetApp ONTAP also supports other ONTAP features that save you space, including snapshots, thin provisioning, and FlexClone volumes.

Storage efficiency features are not enabled by default. You can enable them as follows:

- On an SVM's root volume when you create a file system.
- When you create a new volume.
- When you modify an existing volume.

To view the amount of storage savings on a file system with storage efficiency enabled, see Monitoring storage efficiency savings.

Calculating storage efficiency savings

You can use the `LogicalDataStored` and `StorageUsed` FSx for ONTAP CloudWatch file system metrics to calculate storage savings from compression, deduplication, compaction, snapshots, and

FlexClones. These metrics have a single dimension, `FileSystemId`. For more information, see File system metrics.

- To compute storage-efficiency savings in bytes, take the Average of `StorageUsed` over a given period and subtract it from the Average of `LogicalDataStored` over the same period.
- To compute storage-efficiency savings as a percentage of total logical data size, take the `Average` of `StorageUsed` over a given period and subtract it from the `Average` of `LogicalDataStored` over the same period. Then divide the difference by the `Average` of `LogicalDataStored` over the same period.

SSD sizing example

Assume you want to store 100 TiB of data for an application where 80% of the data is infrequently accessed. In this scenario, 80% (80 TiB) of your data is automatically tiered to the capacity pool tier and the remaining 20% (20 TiB) remains in SSD storage. Based on the typical storage efficiency savings of 65% for general-purpose file sharing workloads, that equates to 7 TiB of data. To maintain an 80% SSD utilization rate, you need 8.75 TiB of SSD storage capacity for the 20 TiB of actively-accessed data. The amount of SSD storage that you provision also needs to account for the ONTAP software storage overhead of 16%, as shown in the following calculation.

```
ssdNeeded = ssdProvisioned * (1 - 0.16)
8.75 TiB / 0.84 = ssdProvisioned
10.42 TiB = ssdProvisioned
```

So in this example, you need to provision at least 10.42 TiB of SSD storage. You will also use 28 TiB of capacity pool storage for the remaining 80 TiB of infrequently accessed data.

File system storage capacity and IOPS

When you create an FSx for ONTAP file system, you specify the storage capacity of the SSD tier. For second-generation Single-AZ file systems, the storage capacity that you specify is spread evenly among the storage pools of each high-availability (HA) pair; these storage pools are called *aggregates*.

For each GiB of SSD storage that you provision, Amazon FSx automatically provisions 3 SSD input/output operations per second (IOPS) for the file system, up to a maximum of 160,000 SSD IOPS per file system. For second-generation Single-AZ file systems, your SSD IOPS are spread evenly across each of your file system's aggregates. You have the option to specify a level of provisioned

SSD IOPS above the automatic 3 SSD IOPS per GiB. For more information about the maximum number of SSD IOPS that you can provision for your FSx for ONTAP file system, see Impact of throughput capacity on performance.

Topics

- Updating file system SSD storage and IOPS
- When to increase SSD storage capacity
- Increasing SSD storage capacity
- Considerations for increasing SSD storage capacity
- When to decrease SSD storage capacity
- Decreasing SSD storage capacity
- Considerations for decreasing SSD storage capacity
- Limitations for decreasing SSD storage capacity
- Creating a storage capacity utilization alarm for your file system
- Updating storage capacity and provisioned IOPS
- Updating storage capacity dynamically
- Monitoring SSD storage utilization
- Monitoring storage efficiency savings
- Monitoring storage capacity and IOPS updates

Updating file system SSD storage and IOPS

When you need additional storage for the active portion of your data set, you can increase the SSD storage capacity of your Amazon FSx for NetApp ONTAP file system. For second-generation file systems, you can even decrease SSD storage capacity to match your workload's changing storage needs. Use the Amazon FSx console, Amazon FSx API, or AWS Command Line Interface (AWS CLI) to increase or decrease the SSD storage capacity. For more information, see Updating storage capacity and provisioned IOPS.

When to increase SSD storage capacity

If you're running out of available SSD tier storage, we recommend that you increase the storage capacity of your file system. Running out of storage indicates that your SSD tier is undersized for the active portion of your data set.

To monitor the amount of free storage that's available on the file system, use the file system-level `StorageCapacity` and `StorageUsed` Amazon CloudWatch metrics. You can create a CloudWatch alarm on a metric and be notified when it drops below a specific threshold. For more information, see Monitoring with Amazon CloudWatch.

> **Note**
>
> We recommend that you don't exceed 80% SSD storage capacity utilization to ensure that data tiering, throughput scaling, and other maintenance activities function properly, and that there is capacity available for additional data. For second-generation file systems, this recommendation applies to both the average utilization across all of your file system's aggregates and to each individual aggregate.

For more information about how a file system's SSD storage is used and how much SSD storage is reserved for file metadata and operating software, see Choosing the right amount of file system SSD storage.

Increasing SSD storage capacity

When you increase the SSD storage capacity of your Amazon FSx file system, the new capacity is typically available for use within minutes. You're billed for the new SSD storage capacity after it becomes available to you. For more information, see Amazon FSx for NetApp ONTAP Pricing and AWS billing and usage reports for FSx for ONTAP.

After you increase your storage capacity, Amazon FSx runs a storage optimization process in the background to rebalance your data. For most file systems, storage optimization takes a few hours with minimal noticeable impact to your workload performance.

You can track the progress of the storage optimization process at any time by using the Amazon FSx console, AWS CLI, and API. For more information, see Monitoring storage capacity and IOPS updates.

Considerations for increasing SSD storage capacity

Here are a few important items to consider when increasing your file system's SSD storage capacity and IOPS:

- **(First-generation file systems only) Storage capacity increase only** – You can only increase the amount of SSD storage capacity for a file system; you can't decrease the storage capacity.

- **Storage capacity minimum increase** – Each SSD storage capacity increase must be a minimum of 10% of the file system's current SSD storage capacity, up to the maximum SSD storage capacity for your file system's configuration.
- **Time between increases** – After increasing SSD storage capacity, provisioned IOPS, or throughput capacity on a file system, you must wait at least six hours before modifying any of these configurations on the same file system again. This is sometimes referred to as a cooldown period.
- **Provisioned IOPS modes** – For a provisioned IOPS change, you must specify one of the two IOPS modes:
  - **Automatic** mode – Amazon FSx automatically scales your SSD IOPS to maintain 3 provisioned SSD IOPS per GiB of SSD storage capacity, up to the maximum SSD IOPS for your file system configuration.

    > **Note**
    >
    > For more information about the maximum number of SSD IOPS that you can provision for your FSx for ONTAP file system, see Impact of throughput capacity on performance.

  - **User-provisioned** mode – You specify the number of SSD IOPS, which must be greater than or equal to 3 IOPS per GiB of SSD storage capacity. If you choose to provision a higher level of IOPS, you pay for the average IOPS provisioned above your included rate for the month, which is measured in IOPS-months.

For more information about pricing, see Amazon FSx for NetApp ONTAP Pricing.

When to decrease SSD storage capacity

You might want to decrease your FSx for ONTAP second-generation file system's SSD storage capacity in scenarios such as the following:

- After completing project-based workloads where high-performance storage is no longer needed
- After completing large-scale data migrations where temporary extra capacity was used to accelerate data ingestion

Decreasing SSD storage capacity

When you decrease SSD storage capacity of your file system, Amazon FSx attaches a new, smaller set of disks (aggregate) to each of your file system's HA pairs. Amazon FSx then runs a storage optimization process in the background to move data on a per-volume basis from the old disks to the new disks. After data in each volume has been moved, Amazon FSx redirects client access to volumes on the new disks. Amazon FSx then detaches the old disks from your file system.

You are billed for the existing and newly requested size of your SSD tier throughout the SSD decrease operation. For example, when you decrease SSD storage capacity from 10 tebibytes (TiB) to 5 TiB, you are billed for 15 TiB during the SSD decrease operation and 5 TiB after the SSD decrease operation is complete. For more information about billing, see AWS billing and usage reports for FSx for ONTAP.

Decreasing SSD storage capacity can take between a few hours and a few weeks depending on factors such as the amount of data stored on your file system, the amount of net-new writes driven to your file system during the decrease operation, and the amount of network and disk resources available on the file system.

During the decrease operation, your data remains available for reads and writes. Most workloads experience minimal performance impact, though write-heavy workloads might experience temporary performance degradation. Brief I/O pauses (up to 60 seconds) might occur as client access is redirected to the new disks for each volume.

To minimize performance impact, you should maintain adequate headroom in your file system by ensuring that ongoing workloads don't consistently consume more than 50% CPU, 50% disk throughput, or 50% SSD IOPS before initiating an SSD decrease operation. You can monitor these utilization metrics in the **Monitoring & performance** tab of your file system in the Amazon FSx console.

> **Note**
>
> If your SSD storage tier exceeds 80% utilization during the decrease operation, Amazon FSx pauses the operation and automatically resumes it after utilization falls below 80%. To decrease SSD utilization on the new disks, you can either tier data to capacity pool or delete data from volumes for which client access has been successfully redirected to the new set of disks.

If you need additional SSD capacity during a decrease operation, you can submit a request to increase SSD capacity by calling `update-file-system` in the AWS CLI or the equivalent UpdateFileSystem API operation and providing a new target value. Amazon FSx prioritizes completing the SSD increase request, so that the new SSD capacity is available for use within minutes before resuming the SSD decrease operation.

Considerations for decreasing SSD storage capacity

Here are a few important items to consider when decreasing a file system's SSD storage capacity and provisioned IOPS:

- **Increasing storage capacity during a decrease operation** – You can increase SSD storage capacity of your file system even while a decrease operation is in progress. This flexibility allows you to ensure performance and availability in case any of your aggregates fill up during the decrease operation. If you increase SSD capacity to a size lower than the original capacity, Amazon FSx only adjusts the size of the newly requested (target) aggregate. However, if you increase the SSD capacity to a size greater than the original, Amazon FSx increases the size of both aggregates to match the new target value. For example, if you're decreasing storage capacity from 10,000 GiB to 5,000 GiB, and then request an increase to 7,000 GiB, only the target aggregate is increased to 7,000 GiB, resulting in a final SSD storage capacity of 7,000 GiB for your file system. But if you request an increase to 12,000 GiB, both aggregates are increased to 12,000 GiB. We suggest careful planning to avoid a scenario in which you have to increase SSD capacity to a size equal to or larger than the original SSD capacity.
- **Pausing SSD decrease** – Amazon FSx pauses an SSD decrease operation if you exceed 80% utilization on the new aggregate and automatically resumes the decrease operation once utilization falls below 80%.
- **(Second-generation Single-AZ file systems only) Storage capacity spread** – The new storage capacity or SSD IOPS that you select for your file system is spread evenly across each of your file system's aggregates.
- **Patching during storage capacity decrease** – Amazon FSx aborts moving data for a volume if your file system is patched during an SSD decrease operation. As a result, you may lose progress on the SSD decrease operation if a patch occurs during the operation. Amazon FSx automatically restarts the `vol move` after the patch operation is complete.
- **Provisioned IOPS modes** – For a provisioned IOPS change, you must specify one of the two IOPS modes:
  - **Automatic** mode – Amazon FSx automatically scales your SSD IOPS to maintain 3 provisioned SSD IOPS per GiB of SSD storage capacity, up to the maximum SSD IOPS for your file system

configuration. When decreasing SSD capacity, your automatic SSD IOPS will scale down proportionally.

> **Note**
>
> For more information about the maximum number of SSD IOPS that you can provision for your FSx for ONTAP file system, see Impact of throughput capacity on performance.

- **User-provisioned** mode – You must provide an IOPS value that is equal to or higher than your currently provisioned IOPS. When decreasing SSD capacity, you can retain additional user-provisioned SSD IOPS as long as they don't exceed the maximum SSD IOPS supported by the smaller aggregate (50 IOPS per GB of requested SSD capacity). If your provisioned IOPS are higher than the maximum supported by the smaller aggregate, reduce IOPS before decreasing SSD capacity.

- **Unsupported volume types** – Amazon FSx does not support decreasing storage capacity on file systems with SnapLock volumes, FlexClones, offline volumes, or data protection (DP) volumes that do not contain any snapshots.
- **Unsupported Operations During Shrink** – You cannot offline volumes, move volumes, create FlexClones, create SnapLock volumes, or modify storage efficiency settings of volumes during the decrease operation.

Limitations for decreasing SSD storage capacity

The following limitations apply while decreasing SSD storage capacity of your file system:

- **(Second-generation file systems only) Storage capacity decrease** – You can decrease the storage capacity only on second-generation file systems.
- **Storage capacity minimum decrease** – Each SSD storage capacity decrease must be a minimum of 9 percent of the file system's current SSD storage capacity. The decrease should also ensure that your file system's resulting SSD capacity does not exceed 80% utilization after the decrease operation. For example, if your file system has 10,000 GiB of storage capacity and 5,000 GiB of storage used, you can decrease storage capacity down to 6,251 GiB such that your SSD utilization remains under 80%. You can decrease SSD storage capacity down to the minimum supported size of 1,024 GiB per HA pair.

- To decrease SSD storage capacity on file systems that contain one or more volumes with more than 50 TiB of storage used, you must provision at least 1,536 MB/s of throughput capacity per HA pair. If any volume contains more than 100 TiB of storage used, you must provision at least 3,072 MB/s of throughput capacity per HA pair. For volumes with more than 200 TiB of storage used, you must provision 6,144 MB/s of throughput capacity per HA pair.
- **Time between updates** – After modifying SSD storage capacity, provisioned IOPS, or throughput capacity on a file system, you must wait at least six hours before modifying any of these configurations on the same file system again. This is sometimes referred to as a cooldown period.
- You can increase but not decrease throughput capacity for your file system
- You cannot add HA pairs to your file system
- You cannot revert a volume to a previous state (using `volume snapshot restore`) while data in that volume is being moved to the new aggregate. However, you can run `volume snapshot restore` on other volumes that aren't being moved currently.

Creating a storage capacity utilization alarm for your file system

We recommend that you do not exceed an average SSD storage capacity utilization of 80% on an ongoing basis. Occasional SSD storage utilization spikes above 80% are acceptable. Maintaining an average utilization under 80% provides you with enough capacity to increase your storage without encountering issues. The following procedure shows how to create a CloudWatch alarm that alerts you to when your file system's SSD storage utilization is approaching 80%.

To create a file system storage capacity utilization alarm

You can use the `StorageCapacityUtilization` metric to create an alarm that is triggered when one or more of your FSx for ONTAP file systems have reached a storage utilization threshold.

1. Open the CloudWatch console at https://console.aws.amazon.com/cloudwatch/.
2. In the left navigation pane, under **Alarms**, choose **All alarms**. Then, choose **Create alarm**. Within the create alarm wizard, choose **Select metric**.
3. In the **graph explorer**, choose the **Multi source query** tab.
4. In the **query builder**, choose the following:
   - For **Namespace**, select **AWS/FSx** > **Detailed File System Metrics**.
   - For **Metric name**, select **MAX(StorageCapacityUtilization)**.

- For **Filter by**, you can optionally include or exclude specific file systems by their ID. If you leave **Filter by** empty, your alarm will trigger when any of your file systems exceed your alarm's storage capacity utilization threshold.
- Leave the rest of the options empty, and choose **Graph query**.

5. Choose **Select metric**. Back in the wizard, in the **Metric** section, give your metric a **Label**. We recommend keeping the **Period** to 5 minutes.
6. Under **Conditions**, choose the **Static threshold type**, whenever your metric is **Greater/Equal to 80**.
7. Choose **Next** to go to the **Configure actions** page.

To configure alarm actions

You can configure a variety of actions for your alarm to trigger when it reaches the threshold you configure. In this example, we choose a Simple Notification Service (SNS) topic, but you can learn about other actions in Using Amazon CloudWatch alarms in the *Amazon CloudWatch User Guide*.

1. In the **Notification** section, choose an SNS topic to notify when your alarm is in the `ALARM` state. You can choose an existing topic or create a new one. You will receive a subscription notification that you need to confirm before you'll receive alarm notifications to the email address.
2. Choose **Next**.

To finish the alarm

Follow these instructions to complete the process of creating your CloudWatch alarm.

1. On the **Add name and description** page, give your alarm a name, and optionally a description, then choose **Next**.
2. Review everything you've configured in the **Preview and create** page, and then choose **Create alarm**.

Updating storage capacity and provisioned IOPS

You can increase or decrease a file system's SSD-based storage and the amount of provisioned SSD IOPS by using the Amazon FSx console, the AWS CLI, and the API.

To increase SSD storage capacity or provisioned IOPS for a file system (console)

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. In the left navigation pane, choose **File systems**. In the **File systems** list, select the FSx for ONTAP file system that you want to update SSD storage capacity and SSD IOPS for.
3. Choose **Actions** > **Update storage capacity**. Or, in the **Summary** section, choose **Update** next to the file system's **SSD storage capacity** value.
4. To increase SSD storage capacity, choose **Modify storage capacity**.
5. For **Input type**, choose one of the following:
   - To enter the new SSD storage capacity as a percentage change from the current value, choose **Percentage**.
   - To enter the new value in GiB, choose **Absolute**.
6. Depending on the input type, enter a value for **Desired % increase**.
   - For **Percentage**, enter the percentage increase value. This value must be at least 10 percent greater than the current value.
   - For **Absolute**, enter the new value in GiB, up to the maximum allowed value of 196,608 GiB.
7. For **Provisioned SSD IOPS**, you have two options to modify the number of provisioned SSD IOPS for your file system:
   - If you want Amazon FSx to automatically scale your SSD IOPS to maintain 3 provisioned SSD IOPS per GiB of SSD storage capacity (up to a maximum of 160,000), choose **Automatic**.
   - If you want to specify the number of SSD IOPS, choose **User-provisioned**. Enter an absolute number of IOPS that's at least three times the amount of GiB of your SSD storage tier, and less than or equal to 160,000.

   > **Note**
   >
   > For more information about the maximum number of SSD IOPS that you can provision for your FSx for ONTAP file system, see Impact of throughput capacity on performance.

8. Choose **Update**.

> **Note**
>
> At the bottom of the prompt, a configuration preview is shown for your new SSD storage capacity and SSD IOPS. For second-generation file systems, the per-HA-pair value is also shown.

To increase SSD storage capacity and provisioned IOPS for a file system (CLI)

To increase the SSD storage capacity and provisioned IOPS for an FSx for ONTAP file system, use the AWS CLI command update-file-system or the equivalent UpdateFileSystem API action. Set the following parameters with your values:

- Set `--file-system-id` to the ID of the file system that you are updating.
- To increase your SSD storage capacity, set `--storage-capacity` to the target storage capacity value, which must be at least 10 percent greater than the current value.
- To modify your provisioned SSD IOPS, use the `--ontap-configuration DiskIopsConfiguration` property. This property has two parameters, `Iops` and `Mode`:
  - If you want to specify the number of provisioned IOPS, use `Iops=`*`number_of_IOPS`* (up to a maximum of 160,000) and `Mode=USER_PROVISIONED`. The IOPS value must be greater than or equal to three times the requested SSD storage capacity. If you're not increasing the storage capacity, the IOPs value must be greater than or equal to three times the current SSD storage capacity.
  - If you want Amazon FSx to automatically increase your SSD IOPS, use `Mode=AUTOMATIC` and don't use the `Iops` parameter. Amazon FSx will automatically maintain 3 SSD IOPS per GiB of the provisioned SSD storage capacity (up to a maximum of 160,000).

> **Note**
>
> For more information about the maximum number of SSD IOPS that you can provision for your FSx for ONTAP file system, see Impact of throughput capacity on performance.

The following example increases the file system's SSD storage to 2000 GiB and sets amount of user provisioned SSD IOPS to 7000.

```
aws fsx update-file-system \
--file-system-id fs-0123456789abcdef0 \
--storage-capacity 2000 \
--ontap-configuration 'DiskIopsConfiguration={Iops=7000,Mode=USER_PROVISIONED}'
```

To monitor the progress of the update, use the describe-file-systems AWS CLI command. Look for the `AdministrativeActions` section in the output.

For more information, see AdministrativeAction in the *Amazon FSx for NetApp ONTAP API Reference*.

To decrease SSD storage capacity for a file system (console)

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. In the left navigation pane, choose **File systems**. In the **File systems** list, select the FSx for ONTAP file system that you want to update SSD storage capacity and SSD IOPS for.
3. Choose **Actions** > **Update file system** > **Update SSD storage capacity/IOPS**. Or, in the **Summary** section, choose **Update** next to the file system's **SSD storage capacity** value.
4. To decrease SSD storage capacity, for **Action type**, choose **Decrease**.
5. For **Input type**, choose one of the following:
   - To enter the new SSD storage capacity as a percentage change from the current value, choose **Percentage**.
   - To enter the new value in GiB, choose **Absolute**.
6. Depending on the input type, do one of the following.
   - For **Percentage**, enter the **Desired % decrease** value. This value must be at least 9 percent less than the current value.
   - For **Absolute**, enter the **Desired storage capacity** value in GiB.
7. Choose **Update**.

> **Note**
>
> At the bottom of the prompt, a configuration preview is shown for your new SSD storage capacity and SSD IOPS. For second-generation file systems, the per-HA-pair value is also shown.

To decrease SSD storage capacity and provisioned IOPS for a file system (CLI)

To decrease the SSD storage capacity and provisioned IOPS for an FSx for ONTAP file system, use the AWS CLI command update-file-system or the equivalent UpdateFileSystem API action. Set the following parameters with your values:

1. To decrease SSD capacity, use the following command:

```
aws fsx update-file-system \
--file-system-id fs-0123456789abcdef0 \
--storage-capacity 4096
```

   If you're using the user-provisioned IOPS mode and want to retain your current IOPS level, include the `DiskIopsConfiguration` parameter:

```
aws fsx update-file-system \
--file-system-id fs-0123456789abcdef0 \
--storage-capacity 4096 \
--ontap-configuration 'DiskIopsConfiguration={Iops=15000,Mode=USER_PROVISIONED}'
```

2. To monitor the progress of the decrease operation, use the **describe-file-systems** command:

```
aws fsx describe-file-systems --file-system-id fs-0123456789abcdef0
```

   The command returns information about the decrease operation in the `AdministrativeActions` section. For example:

```
{
    "FileSystem": {
        "StorageCapacity": 4096,
        "StorageType": "SSD",
        "AdministrativeActions": [
            {
                "AdministrativeActionType": "FILE_SYSTEM_UPDATE",
                "Message": "Moving data for [vol1 vol2]. 2 volume(s) remaining.
 https://docs.aws.amazon.com/fsx/latest/ONTAPGuide/troubleshooting.html",
                "ProgressPercent": 4,
                "RequestTime": 1748981251.591,
                "Status": "IN_PROGRESS",
                "TargetFileSystemValues": {
                    "StorageCapacity": 4096
```

```
                }
            }
        ]
    }
}
```

To monitor the progress of the update, use the `describe-file-systems` AWS CLI command. Look for the `AdministrativeActions` section in the output.

For more information, see `AdministrativeAction` in the Amazon FSx for NetApp ONTAP API Reference.

Updating storage capacity dynamically

You can use the following solution to dynamically increase the SSD storage capacity of an FSx for ONTAP file system when the amount of used SSD storage capacity exceeds a threshold that you specify. This AWS CloudFormation template automatically deploys all of the components that are required to define the storage capacity threshold, the Amazon CloudWatch alarm based on this threshold, and the AWS Lambda function that increases the file system's storage capacity.

The solution automatically deploys all of the components needed, and uses the following parameters:

- Your FSx for ONTAP file system ID.
- The used SSD storage capacity threshold (numerical value). This is the percentage at which the CloudWatch alarm will be triggered.
- The percentage by which to increase the storage capacity (%).
- The email address used to receive scaling notifications.

Topics

- Architecture overview
- CloudFormation template
- Automated deployment with CloudFormation

Architecture overview

Deploying this solution builds the following resources in the AWS Cloud.



The diagram illustrates the following steps:

1. The CloudFormation template deploys a CloudWatch alarm, an AWS Lambda function, an Amazon Simple Notification Service (Amazon SNS) queue, and all required AWS Identity and Access Management (IAM) roles. The IAM role gives the Lambda function permission to invoke the Amazon FSx API operations.
2. CloudWatch triggers an alarm when the file system's used storage capacity exceeds the specified threshold, and sends a message to the Amazon SNS queue. An alarm is triggered only when the file system's used capacity exceeds the threshold continuously for a 5-minute period.
3. The solution then triggers the Lambda function that is subscribed to this Amazon SNS topic.
4. The Lambda function calculates the new file system storage capacity based on the specified percent increase value and sets the new file system storage capacity.
5. The original CloudWatch alarm state and results of the Lambda function operations are sent to the Amazon SNS queue.

To receive notifications about the actions that are performed as a response to the CloudWatch alarm, you must confirm the Amazon SNS topic subscription by following the link provided in the **Subscription Confirmation** email.

CloudFormation template

This solution uses CloudFormation to automate deploying the components that are used to automatically increase the storage capacity of an FSx for ONTAP file system. To use this solution, download the FSxOntapDynamicStorageScaling CloudFormation template.

The template adjusts the storage capacity increment based on the file system's recent usage growth rate rather than applying a fixed percentage on every alarm. Scheduler automatically retries storage scaling that the cooldown window blocks.

The template uses the **Parameters** described as follows. Review the template parameters and their default values, and modify them for the needs of your file system.

FileSystemId

No default value. The ID of the file system for which you want to automatically increase the storage capacity.

LowFreeDataStorageCapacityThreshold

No default value. Specifies the used storage capacity threshold at which to trigger an alarm and automatically increase the file system's storage capacity, specified in percentage (%) of the file system's current storage capacity. The file system is considered to have low free storage capacity when the used storage exceeds this threshold.

EmailAddress

No default value. Specifies the email address to use for the SNS subscription and receives the storage capacity threshold alerts.

LambdaS3Bucket

No default value. The name of the Amazon S3 bucket in your account that hosts the Lambda deployment package (`lambda_function.zip`) for the scaling function. You must upload the Lambda code to this bucket before you deploy the stack.

LambdaS3Key

Default is **fsx/DynamicScaling/lambda_function.zip**. The Amazon S3 object key of the Lambda deployment package within `LambdaS3Bucket`.

PercentIncrease

Default is **20%** (allowed range **10%** to **100%**). Specifies the base percentage by which to increase the storage capacity, expressed as a percentage of the current storage capacity. When `EnableIntelligentScaling` is `true`, the template adjusts the increment up or down based on the file system's recent growth rate, and clamps the result to the value of `MaxIncrementPercent`.

EnableIntelligentScaling

Default is **true**. When `true`, the Lambda function computes the storage growth rate from CloudWatch metrics and scales the increment up for fast-growing file systems and down for slow-growing ones. When `false`, the template applies the flat `PercentIncrease` value on every alarm.

MaxIncrementPercent

Default is **100%** (allowed range **10%** to **500%**). Specifies the maximum percentage increment that intelligent scaling can apply. Adjusted increments are clamped between 10% and this value.

GrowthThresholds

No default value. Optional JSON array of growth-rate tiers in the form `[[threshold_percent_per_day, multiplier, "label"], ...]` that overrides the built-in defaults that intelligent scaling uses. Leave empty to use the built-in tiers.

MinHoursBetweenScaling

Default is **6** hours (allowed range **1** to **24**). Specifies the minimum time between two scaling operations on the same file system. Alarms that fire during the cooldown are deferred and retried automatically.

MaxRetryAttempts

Default is **12** (allowed range **1** to **50**). Specifies the maximum number of retries when scaling is blocked by the cooldown window.

RetryDelayMinutes

Default is **5** minutes (allowed range **1** to **60**). Specifies the delay between two consecutive retries.

RetryBufferMinutes

Default is **5** minutes (allowed range **0** to **60**). Specifies the buffer time added after the cooldown expires before the first retry runs.

ScheduleCleanupAgeDays

Default is **7** days (allowed range **1** to **30**). Specifies the age at which old Scheduler retry schedules are cleaned up.

Automated deployment with CloudFormation

The following procedure configures and deploys an CloudFormation stack to automatically increase the storage capacity of an FSx for ONTAP file system. It takes a few minutes to deploy. For more information about creating a CloudFormation stack, see Creating a stack on the AWS CloudFormation console in the *AWS CloudFormation User Guide*.

> **Note**
>
> Implementing this solution incurs billing for the associated AWS services. For more information, see the pricing details pages for those services.

Before you start, you must have the ID of the Amazon FSx file system that's running in the Amazon Virtual Private Cloud (Amazon VPC) in your AWS account. For more information about creating Amazon FSx resources, see Getting started with Amazon FSx for NetApp ONTAP.

You must also host the Lambda deployment package in an Amazon S3 bucket in your account before you deploy the stack. Download the lambda_function.zip deployment package and upload it to your bucket without unpacking it. You provide the bucket name and object key to the stack by using the `LambdaS3Bucket` and `LambdaS3Key` parameters.

To launch the automatic storage capacity increase solution stack

1. Download the FSxOntapDynamicStorageScaling CloudFormation template archive.

> **Note**
>
> Amazon FSx is currently only available in specific AWS Regions. You must launch this solution in an AWS Region where Amazon FSx is available. For more information, see Amazon FSx endpoints and quotas in the *AWS General Reference*.

2. Extract `FSxOntapDynamicStorageScaling.yaml` from the downloaded archive. You upload the extracted YAML template file to CloudFormation in the following steps.
3. From the CloudFormation console, choose **Create stack > With new resources**.
4. Choose **Template is ready**. In the **Specify template** section, choose **Upload a template file** and upload the template that you downloaded.
5. In **Specify stack details**, enter the values for your automatic storage capacity increase solution.



6. Enter a **Stack name**.
7. For **Parameters**, review the parameters for the template and modify them to meet the needs of your file system. Then choose **Next**.

> **Note**
>
> To receive email notifications when scaling is attempted by this CloudFormation template, confirm the SNS subscription email that you receive after deploying the template.

8. Enter the **Options** settings that you want for your custom solution, and then choose **Next**.
9. For **Review**, review and confirm the solution settings. You must select the check box acknowledging that the template creates IAM resources.
10. Choose **Create** to deploy the stack.

You can view the status of the stack in the CloudFormation console in the **Status** column. You should see a status of **CREATE_COMPLETE** in a few minutes.

Updating the stack

After the stack is created, you can update it by using the same template and providing new values for the parameters. For more information, see Updating stacks directly in the *AWS CloudFormation User Guide*.

Monitoring SSD storage utilization

You can monitor your file system's SSD storage capacity utilization using a variety of AWS and NetApp tools. Using Amazon CloudWatch you can monitor storage capacity utilization and set alarms to alert you when storage capacity utilization reaches a customizable threshold.

> **Note**
>
> We recommend that you don't exceed 80% storage capacity utilization of your SSD storage tier. This ensures that tiering functions properly, and provides overhead for new data.
> If your SSD storage tier is consistently above 80% storage capacity utilization, you can increase your SSD storage tier's capacity. For more information, see Updating file system SSD storage and IOPS.

You can view a file system's available SSD storage and the overall storage distribution in the Amazon FSx console. The **Available primary storage capacity** graph displays the amount of

available SSD-based storage capacity on a file system over time. The **Storage distribution** graph shows how a file system's overall storage capacity is currently distributed over 3 categories:

- Capacity pool tier
- SSD tier - available
- SSD tier - used

You can monitor your file system's SSD storage capacity utilization in the AWS Management Console, using the following procedure.

To monitor file system available SSD tier storage capacity (console)

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. Choose **File systems** in the left-hand navigation column, then choose the ONTAP file system that you want to view storage capacity information for. The file system detail page appears.
3. In the second panel, choose the **Monitoring & performance** tab, then choose **Storage**. The **Available primary storage capacity** and **Storage capacity utilization per aggregate** graphs are displayed.

Monitoring storage efficiency savings

When enabled, you can see how much storage capacity you are saving in the Amazon FSx console, the Amazon CloudWatch console, and the ONTAP CLI.

To view storage efficiency savings (console)

The storage efficiency savings displayed in the Amazon FSx console for an FSx for ONTAP file system includes the savings from FlexClones and SnapShots.

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. Choose the FSx for ONTAP file system that you want to view storage efficiency saving for from the list of **File systems**.
3. Choose **Summary** in the **Monitoring & performance** tab on the second panel in the file system details page.
4. The **Storage efficiency savings** chart shows how much space you are saving as a percentage of your logical data size and in physical bytes.

To view storage efficiency savings (ONTAP CLI)

You can see storage efficiency savings of just compaction, compression, and deduplication – without the effects of snapshots and FlexClones – by running the `storage aggregate show-efficiency` command using the ONTAP CLI. For more information, see storage aggregate show-efficiency in the NetApp ONTAP Documentation Center.

1. To access the ONTAP CLI, establish an SSH session on the management port of the Amazon FSx for NetApp ONTAP file system or SVM by running the following command. Replace *`management_endpoint_ip`* with the IP address of the file system's management port.

   ```
   [~]$ ssh fsxadmin@management_endpoint_ip
   ```

   For more information, see Managing file systems with the ONTAP CLI.

2. The **storage aggregate show-efficiency** command displays information about the storage efficiency of all the aggregates. The storage efficiency is displayed at four different levels:

   - Total
   - Aggregate
   - Volume
   - Snapshot and FlexClone volume

   ```
   ::*> aggr show-efficiency

   Aggregate: aggr1
        Node: node1

   Total Data Reduction Efficiency Ratio:  3.29:1
   Total Storage Efficiency Ratio:         4.29:1
   Aggregate: aggr2
        Node: node1

   Total Data Reduction Efficiency Ratio:  4.50:1
   Total Storage Efficiency Ratio:         5.49:1

   cluster::*> aggr show-efficiency -details

   Aggregate: aggr1
        Node: node1
   ```

```
Total Data Reduction Ratio:                    2.39:1
Total Storage Efficiency Ratio:                4.29:1

Aggregate level Storage Efficiency
(Aggregate Deduplication and Data Compaction): 1.00:1
Volume Deduplication Efficiency:               5.03:1
Compression Efficiency:                        1.00:1

Snapshot Volume Storage Efficiency:            8.81:1
FlexClone Volume Storage Efficiency:           1.00:1
Number of Efficiency Disabled Volumes:         1

Aggregate: aggr2
     Node: node1
Total Data Reduction Ratio:                    2.39:1
Total Storage Efficiency Ratio:                4.29:1

Aggregate level Storage Efficiency
(Aggregate Deduplication and Data Compaction): 1.00:1
Volume Deduplication Efficiency:               5.03:1
Compression Efficiency:                        1.00:1

Snapshot Volume Storage Efficiency:            8.81:1
FlexClone Volume Storage Efficiency:           1.00:1
Number of Efficiency Disabled Volumes:         1
```

Monitoring storage capacity and IOPS updates

You can monitor the progress of an SSD storage capacity and IOPS update by using the Amazon FSx console, CLI, and API.

To monitor storage and IOPS updates (console)

In the **Updates** tab on the **File system details** page for your FSx for ONTAP file system, you can view the 10 most recent updates for each update type.



For SSD storage capacity and IOPS updates, you can view the following information:

Update type

Supported types are **Storage capacity**, **Mode**, and **IOPS**. The **Mode** and **IOPS** values are listed for all storage capacity and IOPS scaling requests.

Target value

The value that you specified to update the file system's SSD storage capacity or IOPS to.

Status

The current status of the update. The possible values are as follows:

- **Pending** – Amazon FSx received the update request, but hasn't started processing it.
- **In progress** – Amazon FSx is processing the update request.
- **Updated; Optimizing** – Amazon FSx increased the file system's SSD storage capacity. The storage-optimization process is now rebalancing your data in the background.
- **Completed** – The update finished successfully.
- **Failed** – The update request failed. Choose the question mark (**?**) to see details.

Progress %

Displays the progress of the storage-optimization process as the percentage complete.

Request time

The time that Amazon FSx received the update action request.

To monitor storage and IOPS updates (CLI)

You can view and monitor file system SSD storage capacity increase and decrease requests by using the `describe-file-systems` AWS CLI command and the DescribeFileSystems

API operation. The `AdministrativeActions` array lists the 10 most recent update actions for each administrative action type. When you increase a file system's SSD storage capacity, two `AdministrativeActions` actions are generated: a `FILE_SYSTEM_UPDATE` and a `STORAGE_OPTIMIZATION` action. When you decrease a file system's SSD storage capacity, only one `AdministrativeActions` action is generated: a `FILE_SYSTEM_UPDATE` action.

The following example shows an excerpt of the response of a `describe-file-systems` CLI command. The file system has a pending administrative action to increase the SSD storage capacity to 2000 GiB and the provisioned SSD IOPS to 7000.

```
"AdministrativeActions": [
    {
        "AdministrativeActionType": "FILE_SYSTEM_UPDATE",
        "RequestTime": 1586797629.095,
        "Status": "PENDING",
        "TargetFileSystemValues": {
            "StorageCapacity": 2000,
            "OntapConfiguration": {
                "DiskIopsConfiguration": {
                    "Mode": "USER_PROVISIONED",
                    "Iops": 7000
                }
             }
        }
    },
    {
        "AdministrativeActionType": "STORAGE_OPTIMIZATION",
        "RequestTime": 1586797629.095,
        "Status": "PENDING"
    }
]
```

Amazon FSx processes the `FILE_SYSTEM_UPDATE` action first, adding the new larger storage disks to the file system. When the new storage is available to the file system, the `FILE_SYSTEM_UPDATE` status changes to `UPDATED_OPTIMIZING`. The storage capacity shows the new larger value, and Amazon FSx begins processing the `STORAGE_OPTIMIZATION` administrative action. This behavior is shown in the following excerpt of the response of a `describe-file-systems` CLI command.

The `ProgressPercent` property displays the progress of the storage-optimization process. After the storage-optimization process has completed successfully, the status of the

FILE_SYSTEM_UPDATE action changes to COMPLETED, and the STORAGE_OPTIMIZATION action no longer appears.

```
"AdministrativeActions": [
    {
        "AdministrativeActionType": "FILE_SYSTEM_UPDATE",
        "RequestTime": 1586799169.445,
        "Status": "UPDATED_OPTIMIZING",
        "TargetFileSystemValues": {
            "StorageCapacity": 2000,
            "OntapConfiguration": {
                "DiskIopsConfiguration": {
                    "Mode": "USER_PROVISIONED",
                    "Iops": 7000
                }
            }
        }
    },
    {
        "AdministrativeActionType": "STORAGE_OPTIMIZATION",
        "ProgressPercent": 41,
        "RequestTime": 1586799169.445,
        "Status": "IN_PROGRESS"
    }
]
```

When decreasing SSD capacity, the FILE_SYSTEM_UPDATE action includes a Message property that provides information about which volumes are currently being moved and how many volumes remain. For example:

```
"AdministrativeActions": [
    {
        "AdministrativeActionType": "FILE_SYSTEM_UPDATE",
        "Message": "Moving data for [vol1 vol2]. 2 volume(s) remaining. https://
docs.aws.amazon.com/fsx/latest/ONTAPGuide/troubleshooting.html",
        "ProgressPercent": 8,
        "RequestTime": 1748981251.591,
        "Status": "IN_PROGRESS",
        "TargetFileSystemValues": {
            "StorageCapacity": 4096,
            "OntapConfiguration": {
                "DiskIopsConfiguration": {
```

```
                    "Mode": "AUTOMATIC",
                    "Iops": 12288
                }
            }
        }
    }
]
```

If the SSD decrease operation is paused because the target aggregate has exceeded 80% utilization, the status will change to PAUSED with an appropriate message:

```
"AdministrativeActions": [
    {
        "AdministrativeActionType": "FILE_SYSTEM_UPDATE",
        "Message": "Your file system has insufficient free space in its SSD tier.
 Please free up space or increase your file system's storage capacity.",
        "ProgressPercent": 8,
        "RequestTime": 1748981251.591,
        "Status": "PAUSED",
        "TargetFileSystemValues": {
            "StorageCapacity": 4096,
            "OntapConfiguration": {
                "DiskIopsConfiguration": {
                    "Mode": "AUTOMATIC",
                    "Iops": 12288
                }
            }
        }
    }
]
```

If the storage capacity or IOPS update request fails, the status of the `FILE_SYSTEM_UPDATE` action changes to `FAILED`, as shown in the following example. The `FailureDetails` property provides information about the failure.

```
"AdministrativeActions": [
    {
        "AdministrativeActionType": "FILE_SYSTEM_UPDATE",
        "RequestTime": 1586373915.697,
        "Status": "FAILED",
        "TargetFileSystemValues": {
            "StorageCapacity": 2000,
```

```
            "OntapConfiguration": {
                "DiskIopsConfiguration": {
                    "Mode": "USER_PROVISIONED",
                    "Iops": 7000
                }
            }
        },
        "FailureDetails": {
            "Message": "failure-message"
        }
    }
]
```

Volume storage capacity

FSx for ONTAP volumes are virtual resources that you use for grouping data, determining how data is stored, and determining the type of access to your data. Volumes, like folders, don't consume file system storage capacity themselves. Only the data that's stored in a volume consumes SSD storage and, depending on the volume's tiering policy, capacity pool storage. You set a volume's size when you create it, and you can change its size later. You can monitor and manage the storage capacity of your FSx for ONTAP volumes using the AWS Management Console, AWS CLI and API, and the ONTAP CLI.

Topics

- Volume data tiering
- Snapshots and volume storage capacity
- Volume file capacity
- Managing storage efficiencies
- Enabling autosizing
- Enabling cloud write mode
- Updating storage capacity
- Updating a tiering policy
- Updating the minimum cooling days
- Updating a volume's cloud retrieval policy
- Updating the maximum number of files on a volume
- Monitoring volume storage capacity

- Monitoring a volume's file capacity

Volume data tiering

An Amazon FSx for NetApp ONTAP file system has two storage tiers: primary storage and capacity pool storage. Primary storage is provisioned, scalable, high-performance SSD storage that's purpose-built for the active portion of your data set. Capacity pool storage is a fully elastic storage tier that can scale to petabytes in size and is cost-optimized for infrequently accessed data.

The data on each volume is automatically tiered to the capacity pool storage tier based on the volume's tiering policy, cooling period, and threshold settings. The following sections describe ONTAP volume tiering policies and the thresholds used to determine when data is tiered to the capacity pool.

> **Note**
>
> FSx for ONTAP supports tiering data to the capacity pool on all SnapLock volumes, regardless of the SnapLock type. For more information, see How SnapLock works.

Volume tiering policies

You determine how to use your FSx for ONTAP file system's storage tiers by choosing the tiering policy for each of volume on the file system. You choose the tiering policy when you create a volume, and you can modify it at any time with the Amazon FSx console, AWS CLI, API, or using NetApp management tools. You can choose from one of the following policies that determine which data, if any, is tiered to the capacity pool storage.

> **Note**
>
> Tiering can move your file data and snapshot data to the capacity pool tier. However, file metadata always remains on the SSD tier. For more information, see How SSD storage is used.

- **Auto** – This policy moves all cold data—user data and snapshots—to the capacity pool tier. The cooling rate of data is determined by the policy's cooling period, which by default is 31 days, and is configurable to values between 2–183 days. When the underlying cold data blocks are read

randomly (as in typical file access), they are made hot and written to the primary storage tier. When cold data blocks are read sequentially (for example, by an antivirus scan), they remain cold and remain on the capacity pool storage tier. This is the default policy when creating a volume using the Amazon FSx console.

- **Snapshot Only** – This policy moves only snapshot data to the capacity pool storage tier. The rate at which snapshots are tiered to the capacity pool is determined by the policy's cooling period, which by default is set to 2 days, and is configurable to values between 2–183 days. When cold snapshot data are read, they are made hot and written to the primary storage tier. This is the default policy when creating a volume using the AWS CLI, Amazon FSx API, or the NetApp ONTAP CLI.
- **All** – This policy marks all user data and snapshot data as cold, and stores it in the capacity pool tier. When data blocks are read, they remain cold and are not written to the primary storage tier. When data is written to a volume with the **All** tiering policy, it is still initially written to the SSD storage tier, and is tiered to the capacity pool by a background process. If the **All** policy is applied to a volume that already contains data, the existing data is tiered from SSD to the capacity pool. Note that file metadata always remains on the SSD tier.
- **None** – This policy keeps all of your volume's data on the primary storage tier, and prevents it from being moved to capacity pool storage. If you set a volume to this policy after it uses any other policy, existing data (including snapshots) in the volume that was in capacity pool storage is moved to SSD storage by a background process. This data migration only occurs when your SSD utilization is below 90% and the cloud retrieval policy is set to `promote` or `on-read`. This background process can be sped up by intentionally reading data. For more information, see Cloud retrieval policies.

For more information about setting or modifying a volume's tiering policy, see Updating a tiering policy.

As a best practice, when migrating data that you plan to store long-term in capacity pool storage, we recommend that you use the **Auto** tiering policy on your volume. With **Auto** tiering, data is stored on the SSD storage tier for a minimum of 2 days (based on the volume's cooling period) before it's moved to the capacity pool tier. ONTAP runs post-process deduplication on data stored in the SSD storage tier periodically, automatically adjusting the frequency based on the rate of data change in the volume—higher rates trigger post-process deduplication jobs more frequently.

By default, post-process compression is disabled in ONTAP due to the performance impact it can have on ongoing workloads on the file system. You should evaluate the impact on your workload's

performance before enabling post-process compression. To enable post-process compression, assume the diagnostic privilege level in the ONTAP CLI and run the following command:

```
::> volume efficiency inactive-data-compression modify -vserver svm-name -volume vol-name -is-enabled true
```

ONTAP runs post-process compression for data that is retained on SSD storage for a minimum of 14 days. For workloads where data is unlikely to be accessed after a shorter period, you can modify the post-process compression settings to run post-process compression sooner. For example, to apply post-process compression savings to data that has not been accessed for 5 days, run the following ONTAP CLI command:

```
::> volume efficiency inactive-data-compression modify -vserver svm-name -volume vol-name -threshold-days 5 -threshold-days-min 2 -threshold-days-max 14
```

For more information about the command, see volume efficiency inactive-data-compression modify

By retaining data on SSD, you maximize the transfer speeds of volume backups that you create, as data transfer rates are higher for SSD storage.

Tiering cooling period

A volume's tiering cooling period sets the amount of time that it takes for data in the SSD tier to be marked as cold. The cooling period applies to the `Auto` and `Snapshot-only` tiering policies. You can set the cooling period to a value in the range of 2–183 days. For more information about setting the cooling period, see Updating the minimum cooling days.

Data is tiered 24–48 hours after its cooling period expires. Tiering is a background process that consumes network resources, and has a lower priority than client-facing requests. Tiering activities are throttled when there are ongoing client-facing requests.

Cloud retrieval policies

A volume's cloud retrieval policy sets the conditions that specify when data that's read from the capacity pool tier is allowed to be promoted to the SSD tier. When the cloud retrieval policy is set to anything other than `Default`, this policy overrides the retrieval behavior of your volume's tiering policy. A volume can have one of the following cloud retrieval policies:

- **Default** – This policy retrieves tiered data based on the volume's underlying tiering policy. This is the default cloud retrieval policy for all volumes.
- **Never** – This policy never retrieves tiered data, regardless of whether the reads are sequential or random. This is similar to setting the tiering policy of your volume to **All**, except that you can use it with other policies–**Auto**, **Snapshot-only**–to tier data according to the minimum cooling period instead of immediately.
- **On-read** – This policy retrieves tiered data for all client-driven data reads. This policy has no effect when using the **All** tiering policy.
- **Promote** – This policy marks all of a volume's data that's in the capacity pool for retrieval to the SSD tier. The data is marked the next time the daily background tiering scanner runs. This policy is beneficial for applications that have cyclical workloads that run infrequently, but require SSD tier performance when they do run. This policy has no effect when using the **All** tiering policy.

For information on setting a volume's cloud retrieval policy, see Updating a volume's cloud retrieval policy.

Tiering thresholds

A file system's SSD storage capacity utilization determines how ONTAP manages the tiering behavior for all of your volumes. Based on a file system's SSD storage capacity usage, the following thresholds set the tiering behavior as described. For information about how to monitor the capacity utilization of a volume's SSD storage tier, see Monitoring volume storage capacity.

> **Note**
>
> We recommend that you don't exceed 80% storage capacity utilization of your SSD storage tier. For second-generation file systems, this recommendation applies to both the total average utilization across all of your file system's aggregates and to the utilization of each individual aggregate. This ensures that tiering functions properly, and provides overhead for new data. If your SSD storage tier is consistently above 80% storage capacity utilization, you can increase your SSD storage tier's capacity. For more information, see Updating file system SSD storage and IOPS.

FSx for ONTAP uses the following storage capacity thresholds to manage tiering on volumes:

- **<=50% SSD storage tier utilization** – At this threshold, the SSD storage tier is considered to be underutilized, and only volumes that are using the **All** tiering policy have data tiered to capacity pool storage. Volumes with **Auto** and **Snapshot-only** policies don't tier data at this threshold.
- **> 50% SSD storage tier utilization** – Volumes with **Auto** and **Snapshot-only** tiering policies tier data based on the tiering minimum cooling days setting. The default setting is 31 days.
- **>=90% SSD storage tier utilization** – At this threshold, Amazon FSx prioritizes preserving space in the SSD storage tier. Cold data from the capacity pool tier is no longer moved into the SSD storage tier when read for volumes using **Auto** and **Snapshot-only** policies.
- **>=98% SSD storage tier utilization** – All tiering functionality stops when the SSD storage tier is at or above 98% utilization. You can continue to read from storage tiers, but you can't write to the tiers.

Snapshots and volume storage capacity

A *snapshot* is a read-only image of an Amazon FSx for NetApp ONTAP volume at a point in time. Snapshots offer protection against accidental deletion or modification of files in your volumes. With snapshots, your users can easily view and restore individual files or folders from an earlier snapshot.

Snapshots are stored alongside your file system's data, and they consume the file system's storage capacity. However, snapshots consume storage capacity only for the portions of files that changed since the last snapshot. Snapshots are not included in backups of your file system volumes.

Snapshots are enabled by default on your volumes, using the default snapshot policy. Snapshots are stored in the `.snapshot` directory at the root of a volume. You can manage volume storage capacity for snapshots in the following ways:

- Snapshot policies – Select a built-in snapshot policy or choose a custom policy that you created in the ONTAP CLI or REST API.
- Manually delete snapshots – Reclaim storage capacity by deleting snapshots manually.
- Create a snapshot autodelete policy – Create a policy that deletes more snapshots than the default snapshot policy.
- Turn off automatic snapshots – Conserve storage capacity by turning off automatic snapshots.

For more information, see Protecting your data with snapshots.

Volume file capacity

Amazon FSx for NetApp ONTAP volumes have file pointers that are used to store file metadata such as file name, last accessed time, permissions, size, and to serve as pointers to data blocks. These file pointers are called inodes, and each volume has a finite capacity for the number of inodes, which is called the volume file capacity. When a volume runs low on or exhausts its available files (inodes), you can't write additional data to that volume.

The number of file system objects—files, directories, Snapshot copies—a volume can contain is determined by how many inodes it has. The number of inodes in a volume increases commensurately with the volume's storage capacity (and the number of volume constituents for FlexGroup volumes). By default, FlexVol volumes (or FlexGroup constituents) with a storage capacity of 648 GiB or more all have the same number of inodes: 21,251,126. If you create a volume larger than 648 GiB and you want it to have more than 21,251,126 inodes, you must increase the maximum number of inodes (files) manually. For more information about viewing the maximum number of files for a volume, see Monitoring a volume's file capacity.

The default number of inodes on a volume is 1 inode for every 32 KiB of volume storage capacity, up to a volume size of 648 GiB. For a 1 GiB volume:

Volume_size_in_bytes × (1 file ÷ inode_size_in_bytes) = maximum_number_of_files

1,073,741,824 bytes × (1 file ÷ 32,768 bytes) = 32,768 files

You can increase the maximum number of inodes that a volume can contain, up to a maximum of 1 inode for every 4 KiB of storage capacity. For a 1 GiB volume. this increases the maximum number of inodes or files from 32,768 to 262,144:

1,073,741,824 bytes × (1 file ÷ 4096 bytes) = 262,144 files

An FSx for ONTAP volume can have a maximum of 2 billion inodes.

For information about changing the maximum number of files that a volume can store, see Updating the maximum number of files on a volume.

Managing storage efficiencies

By enabling storage efficiencies on your FSx for ONTAP volumes, you can optimize storage utilization, reduce storage costs, and improve your file system's performance overall.

> **Note**
>
> We recommend enabling storage efficiencies using the Amazon FSx console, API, or AWS CLI to ensure that the optimal storage efficiency settings are applied to your volumes.

ONTAP organizes files into 4 kibibyte (KiB) data blocks. Storage efficiencies take place at the data block level rather than at the level of individual files. When storage efficiencies are enabled, ONTAP employs a combination of data reduction techniques to eliminate duplicate data, compress the size of data, and reorganize the layout of data for optimal disk usage.

Storage efficiencies are applied in two ways. They are applied to data inline (before data is written to disk, in memory) to provide immediate storage savings. They are also applied to data in the background (after the data is written to disk) in the SSD storage tier through periodic efficiency jobs to optimize storage utilization over time. Background storage efficiencies don't run on data after it's tiered to the capacity pool. However, if the data had any storage savings while it was in SSD, these savings are preserved when the data is tiered to the capacity pool.

> **Note**
>
> ONTAP doesn't support enabling storage efficiencies on data protection (DP) volumes. However, storage savings achieved in the source read-writable (RW) volume are preserved when data is replicated to the destination DP volume.

Compression of data blocks

Compression groups are logical groupings of data that are managed and compressed together as a single block. ONTAP automatically packs data blocks into compression groups, which reduces the space consumed on disk. To optimize performance and storage utilization, ONTAP provides a balanced approach to managing data by adjusting the degree of compression that's applied to the data based on its access patterns.

By default, data is compressed inline using 8 KB compression groups to ensure optimal performance when writing data to a volume. Optionally, you can apply heavier compression to data by enabling inactive data compression on a volume to further compress data in SSD. Inactive data compression uses 32 KB compression groups on cold data for additional storage savings. For more information, see the `volume efficiency inactive-data-compression modify` command in the NetApp ONTAP Documentation Center.

Note

Inactive data compression consumes additional CPU and disk IOPS and can be a resource-intensive task. We recommend that you evaluate the performance impact of running inactive data compression on your workload before enabling this feature.

The following image illustrates the storage savings that can be achieved by compressing data blocks.



Deduplication of data blocks

ONTAP detects and eliminates duplicate data blocks to reduce redundancies in data. The duplicate blocks are replaced with references to shared unique blocks.

By default, data is deduplicated inline to reduce the storage footprint before data is written to disk. ONTAP also runs a background deduplication scanner at specified intervals to identify and eliminate duplicate data after it's been written to disk. During these scheduled scans, ONTAP processes a change log to identify new or modified data blocks since the last scan that haven't been deduplicated yet. When duplicates are found, ONTAP updates the metadata to point to a single copy of the duplicated blocks and marks the redundant blocks as free space that's ready to be reclaimed.

Note

ONTAP applies deduplication to 4 KB of incoming writes at a time, so you might see lower deduplication savings when running workloads with writes that are smaller than 4 KB in size.
FSx for ONTAP doesn't support cross-volume deduplication.

The following image illustrates the storage savings that can be achieved with deduplication.



Compaction of data blocks

ONTAP consolidates partially filled data blocks that are less than 4 KB each into a more efficiently utilized 4 KB block.

By default, data is compacted inline to optimize the layout of data as it's written to disk to minimize storage overhead, reduce fragmentation, and improve read performance.

The following image illustrates the storage savings that can be achieved with compaction.



Example: storage efficiencies

The following image illustrates how storage efficiencies are applied to data.



Storage Efficiency status

Amazon FSx reports a volume's storage efficiency as **Enabled** in the console, API, and AWS CLI only when the volume's storage efficiency configuration in ONTAP matches the settings that Amazon FSx uses. When you enable storage efficiency on a volume, Amazon FSx applies the following ONTAP settings:

- Compression: inline
- Deduplication: inline and background (both)
- Cross-volume deduplication: none
- Compaction: inline

If you modify storage efficiency settings with the ONTAP CLI or REST API, or if you migrated your volumes from an on-premises ONTAP system, the volume's configuration might not match these settings. When that happens, Amazon FSx reports storage efficiency as **Disabled**, even if efficiency features are still active on the volume.

To restore the Amazon FSx-managed configuration and have the console report **Enabled**, use one of the following methods:

- **AWS CLI:**

```
aws fsx update-volume --volume-id vol-id --ontap-configuration
 StorageEfficiencyEnabled=true
```

- **ONTAP CLI:**

```
::> volume efficiency on -vserver svm-name -volume vol-name
::> volume efficiency modify -vserver svm-name -volume vol-name -inline-dedupe true -
inline-compression true -data-compaction true -compression true
```

> **Important**
>
> For volumes migrated from Cloud Volumes ONTAP with a compression type of `secondary`, switching to the Amazon FSx-managed settings requires first undoing existing compression savings on the volume, then re-enabling compression with the `adaptive` compression type. This operation is resource-intensive. Plan this operation carefully before running it on

production volumes. For more information, see Moving between secondary compression and adaptive compression in the NetApp ONTAP documentation.

Enabling autosizing

Volume autosizing so that the volume will automatically grow to a specified size when it reaches a used space threshold. You can do this for FlexVol volume types (the default volume type for FSx for ONTAP) using the `volume autosize` ONTAP CLI command.

To enable volume autosizing (ONTAP CLI)

1. To access the ONTAP CLI, establish an SSH session on the management port of the Amazon FSx for NetApp ONTAP file system or SVM by running the following command. Replace *`management_endpoint_ip`* with the IP address of the file system's management port.

   ```
   [~]$ ssh fsxadmin@management_endpoint_ip
   ```

   For more information, see Managing file systems with the ONTAP CLI.
2. Use the `volume autosize` command as shown, replacing the following values:

   - Replace *`svm_name`* with the name of the SVM that the volume is created on.
   - Replace *`vol_name`* with name of the volume that you want to resize.
   - Replace *`grow_threshold`* with a used space percentage value (such as `90`) at which the volume will automatically increase in size (up to the *`max_size`* value).
   - Replace *`max_size`* with the maximum size that the volume can grow to. Use the format *`integer`*`[KB|MB|GB|TB|PB]`; for example, `300TB`. The maximum size is 300 TB. The default is 120% of the volume size.
   - Replace *`min_size`* with the minimum size that the volume will shrink to. Use the same format as for *`max_size`*.
   - Replace *`shrink_threshold`* with the used space percentage at which the volume will automatically shrink in size.

   ```
   ::> volume autosize -vserver svm_name -volume vol_name -mode grow_shrink -
   grow-threshold-percent grow_threshold -maximum-size max_size -shrink-threshold-
   percent shrink_threshold -minimum-size min_size
   ```

3. To show the current autosize setting, run the following command. Replace *svm_name* and *vol_name* with your information.

```
::> volume autosize -vserver svm_name -volume vol_name
```

Enabling cloud write mode

Use the `volume modify` ONTAP CLI command to enable or disable cloud write mode for an existing volume. For more information, see `volume modify` in the NetApp ONTAP Documentation Center.

Prerequisites for setting cloud write mode are:

- The volume must be an existing volume. You can only enable the feature on an existing volume.
- The volume must be a read-write (RW) volume.
- The volume must have the **All** tiering policy. For more information about modifying a volume's tiering policy, see Updating a tiering policy.

Cloud write mode is helpful for cases like migrations, for example, where large amounts of data are transferred to a file system using the NFS protocol.

To set a volume's cloud write mode (ONTAP CLI)

1. To access the ONTAP CLI, establish an SSH session on the management port of the Amazon FSx for NetApp ONTAP file system or SVM by running the following command. Replace *management_endpoint_ip* with the IP address of the file system's management port.

```
[~]$ ssh fsxadmin@management_endpoint_ip
```

   For more information, see Managing file systems with the ONTAP CLI.

2. Enter the ONTAP CLI advanced mode using the following command.

```
FSx::> set -privilege advanced
Warning: These advanced commands are potentially dangerous; use them only when
     directed to do so by NetApp personnel.
Do you want to continue? {y|n}: y
```

3. Use the following command to set the volume's cloud write mode, replacing the following values:

   - Replace *svm_name* with the name of the SVM that the volume is created on.
   - Replace *vol_name* with name of the volume for which you are setting cloud write mode.
   - Replace *vol_cw_mode* with either `true` to enable cloud write mode on the volume or `false` to disable it.

   ```
   FSx::> volume modify -vserver svm_name -volume vol_name -is-cloud-write-
   enabled vol_cw_mode
   ```

   The system responds as follows for a successful request.

   ```
   Volume modify successful on volume vol_name of Vserver svm_name.
   ```

Updating storage capacity

You can manage volume storage capacity by manually increasing or decreasing volume size using the AWS Management Console, AWS CLI and API, and the ONTAP CLI. You can also enable volume autosizing so that the volume size automatically grows or shrinks when it reaches certain used storage capacity thresholds. You use the ONTAP CLI to manage volume autosizing.

To change a volume's storage capacity (console)

- You can increase or decrease a volume's storage capacity using the Amazon FSx console, AWS CLI, and API. For more information, see Updating volumes.

You can also use the ONTAP CLI to modify a volume's storage capacity using the `volume modify` command.

To modify a volume's size (ONTAP CLI)

1. To access the ONTAP CLI, establish an SSH session on the management port of the Amazon FSx for NetApp ONTAP file system or SVM by running the following command. Replace *management_endpoint_ip* with the IP address of the file system's management port.

```
[~]$ ssh fsxadmin@management_endpoint_ip
```

For more information, see Managing file systems with the ONTAP CLI.

2. Use the **volume modify** ONTAP CLI command to modify a volume's storage capacity. Run the following command, using your data in place of the following values:

   - Replace *svm_name* with the name of the storage virtual machine (SVM) that the volume is created on.
   - Replace *vol_name* with name of the volume that you want to re-size.
   - Replace *vol_size* with the new size of the volume in the format *integer*[KB|MB|GB|TB|PB]; for example, 100GB to increase the volume size to 100 gigabytes.

```
::> volume modify -vserver svm_name -volume vol_name -size vol_size
```

Updating a tiering policy

You can modify a volume's tiering policy using the AWS Management Console, AWS CLI and API, and the ONTAP CLI.

To modify a volume's data tiering policy (console)

Use the following procedure to modify a volume's data-tiering policy using the AWS Management Console.

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. Choose **Volumes** in the left navigation pane, then choose the ONTAP volume for which you want to modify the data-tiering policy.
3. Choose **Update volume** from the **Actions** drop down menu. The **Update volume** window appears.
4. For **Capacity pool tiering policy**, choose the new policy for the volume. For more information, see Volume tiering policies.
5. Choose **Update** to apply the new policy to the volume.

To set a volume's tiering policy (CLI)

- Modify a volume's tiering policy using the update-volume CLI command (UpdateVolume is the equivalent Amazon FSx API action). The following CLI command example sets a volume's data-tiering policy to SNAPSHOT_ONLY.

```
aws fsx update-volume \
    --volume-id fsxvol-abcde0123456789f
    --ontap-configuration TieringPolicy={Name=SNAPSHOT_ONLY}
```

For a successful request, the system responds with the volume description.

```
{
    "Volume": {
        "CreationTime": "2021-10-05T14:27:44.332000-04:00",
        "FileSystemId": "fs-abcde0123456789f",
        "Lifecycle": "CREATED",
        "Name": "vol1",
        "OntapConfiguration": {
            "FlexCacheEndpointType": "NONE",
            "JunctionPath": "/vol1",
            "SecurityStyle": "UNIX",
            "SizeInMegabytes": 1048576,
            "StorageEfficiencyEnabled": true,
            "StorageVirtualMachineId": "svm-abc0123de456789f",
            "StorageVirtualMachineRoot": false,
            "TieringPolicy": {
                "CoolingPeriod": 2,
                "Name": "SNAPSHOT_ONLY"
            },
            "UUID": "aaaa1111-bb22-cc33-dd44-abcde01234f5",
            "OntapVolumeType": "RW"
        },
        "ResourceARN": "arn:aws:fsx:us-east-2:111122223333:volume/fs-
abcde0123456789f/fsvol-abc012def3456789a",
        "VolumeId": "fsvol-abc012def3456789a",
        "VolumeType": "ONTAP"
    }
}
```

To modify a volume's tiering policy (ONTAP CLI)

You use the `volume modify` ONTAP CLI command to set a volume's tiering policy. For more information, see `volume modify` in the NetApp ONTAP Documentation Center.

1. To access the ONTAP CLI, establish an SSH session on the management port of the Amazon FSx for NetApp ONTAP file system or SVM by running the following command. Replace *`management_endpoint_ip`* with the IP address of the file system's management port.

   ```
   [~]$ ssh fsxadmin@management_endpoint_ip
   ```

   For more information, see Managing file systems with the ONTAP CLI.

2. Enter the ONTAP CLI advanced mode using the following command.

   ```
   FSx::> set adv

   Warning: These advanced commands are potentially dangerous; use them only when
        directed to do so by NetApp personnel.
   Do you want to continue? {y|n}: y
   ```

3. Use the following command to modify the volume data-tiering policy, replacing the following values:

   - Replace *`svm_name`* with the name of the SVM that the volume is created on.
   - Replace *`vol_name`* with name of the volume for which you are setting the data-tiering policy.
   - Replace *`tiering_policy`* with the desired policy. Valid values are `snapshot-only`, `auto`, `all`, or none. For more information, see Volume tiering policies.

   ```
   FSx::> volume modify -vserver svm_name -volume vol_name -tiering-
   policy tiering_policy
   ```

Updating the minimum cooling days

Minimum cooling days for a volume set the threshold that's used to determine which data is warm and which data is cold. You can set a volume's minimum cooling days using AWS CLI and API, and the ONTAP CLI.

To set a volume's minimum cooling days (CLI)

- Modify a volume configuration by using the update-volume CLI command (UpdateVolume is the equivalent Amazon FSx API action). The following CLI command example sets a volume's `CoolingPeriod` to 104 days.

```
aws fsx update-volume \
    --volume-id fsxvol-abcde0123456789f
    --ontap-configuration TieringPolicy={Name=SNAPSHOT_ONLY}
aws fsx update-volume --volume-id fsvol-006530558c14224ac --ontap-configuration
 TieringPolicy={CoolingPeriod=104}
```

The system responds with the volume description for a successful request.

```
{
    "Volume": {
        "CreationTime": "2021-10-05T14:27:44.332000-04:00",
        "FileSystemId": "fs-abcde0123456789f",
        "Lifecycle": "CREATED",
        "Name": "vol1",
        "OntapConfiguration": {
            "FlexCacheEndpointType": "NONE",
            "JunctionPath": "/vol1",
            "SecurityStyle": "UNIX",
            "SizeInMegabytes": 1048576,
            "StorageEfficiencyEnabled": true,
            "StorageVirtualMachineId": "svm-abc0123de456789f",
            "StorageVirtualMachineRoot": false,
            "TieringPolicy": {
                "CoolingPeriod": 104,
                "Name": "SNAPSHOT_ONLY"
            },
            "UUID": "aaaa1111-bb22-cc33-dd44-abcde01234f5",
            "OntapVolumeType": "RW"
        },
        "ResourceARN": "arn:aws:fsx:us-east-2:111122223333:volume/fs-
abcde0123456789f/fsvol-abc012def3456789a",
        "VolumeId": "fsvol-abc012def3456789a",
        "VolumeType": "ONTAP"
    }
}
```

To set a volume's minimum cooling days (ONTAP CLI)

Use the `volume modify` ONTAP CLI command to set the minimum number of cooling days for an existing volume. For more information, see `volume modify` in the NetApp ONTAP Documentation Center.

1. To access the ONTAP CLI, establish an SSH session on the management port of the Amazon FSx for NetApp ONTAP file system or SVM by running the following command. Replace *`management_endpoint_ip`* with the IP address of the file system's management port.

   ```
   [~]$ ssh fsxadmin@management_endpoint_ip
   ```

   For more information, see Managing file systems with the ONTAP CLI.

2. Enter the ONTAP CLI advanced mode using the following command.

   ```
   FSx::> set adv

   Warning: These advanced commands are potentially dangerous; use them only when
        directed to do so by NetApp personnel.
   Do you want to continue? {y|n}: y
   ```

3. Use the following command to change your volume's tiering minimum cooling days, replacing the following values:

   - Replace *`svm_name`* with the name of the SVM that the volume is created on.
   - Replace *`vol_name`* with name of the volume for which you are setting the cooling days.
   - Replace *`cooling_days`* with the desired, an integer between 2-183.

   ```
   FSx::> volume modify -vserver svm_name -volume vol_name -tiering-minimum-cooling-
   days cooling_days
   ```

   The system responds as follows for a successful request.

   ```
   Volume modify successful on volume vol_name of Vserver svm_name.
   ```

Updating a volume's cloud retrieval policy

Use the `volume modify` ONTAP CLI command to set the cloud retrieval policy for an existing volume. For more information, see `volume modify` in the NetApp ONTAP Documentation Center.

To set a volume's cloud retrieval policy (ONTAP CLI)

1. To access the ONTAP CLI, establish an SSH session on the management port of the Amazon FSx for NetApp ONTAP file system or SVM by running the following command. Replace *`management_endpoint_ip`* with the IP address of the file system's management port.

   ```
   [~]$ ssh fsxadmin@management_endpoint_ip
   ```

   For more information, see Managing file systems with the ONTAP CLI.

2. Enter the ONTAP CLI advanced mode using the following command.

   ```
   FSx::> set adv

   Warning: These advanced commands are potentially dangerous; use them only when
        directed to do so by NetApp personnel.
   Do you want to continue? {y|n}: y
   ```

3. Use the following command to set the volume's cloud retrieval policy, replacing the following values:

   - Replace *`svm_name`* with the name of the SVM that the volume is created on.
   - Replace *`vol_name`* with name of the volume for which you are setting the cloud retrieval policy.
   - Replace *`retrieval_policy`* with the desired value, either `default`, `on-read`, `never`, or `promote`.

   ```
   FSx::> volume modify -vserver svm_name -volume vol_name -cloud-retrieval-
   policy retrieval_policy
   ```

   The system responds as follows for a successful request.

   ```
   Volume modify successful on volume vol_name of Vserver svm_name.
   ```

Updating the maximum number of files on a volume

FSx for ONTAP volumes can run out of file capacity when the number of available inodes, or file pointers, is exhausted.

To increase the maximum number of files on a volume (ONTAP CLI)

You use the `volume modify` ONTAP CLI command to increase the maximum number of files on a volume. For more information, see `volume modify` in the NetApp ONTAP Documentation Center.

1. To access the ONTAP CLI, establish an SSH session on the management port of the Amazon FSx for NetApp ONTAP file system or SVM by running the following command. Replace *`management_endpoint_ip`* with the IP address of the file system's management port.

   ```
   [~]$ ssh fsxadmin@management_endpoint_ip
   ```

   For more information, see Managing file systems with the ONTAP CLI.
2. Do one of the following, depending on your use case. Replace *`svm_name`* and *`vol_name`* with your values.

   - To configure a volume to always have the maximum number of files (inodes) available, perform the following:

     1. Enter advanced mode in the ONTAP CLI by using the following command.

        ```
        ::> set adv
        ```

     2. After running this command, you'll see this output. Enter `y` to continue.

        ```
        Warning: These advanced commands are potentially dangerous; use them only
         when
        directed to do so by NetApp personnel.
        Do you want to continue? {y|n}: y
        ```

     3. Enter the following command to always use the maximum number of files on the volume:

        ```
        ::> volume modify -vserver svm_name -volume vol_name -files-set-maximum true
        ```

- To manually specify the total number of files permitted on the volume, with *max_number_files* = (current_size_of_volume) × (1 file ÷ 4 KiB), up to a maximum possible value of 2 billion, use the following command:

```
::> volume modify -vserver svm_name -volume vol_name -files max_number_files
```

Monitoring volume storage capacity

You can view a volume's available storage and it's storage distribution in AWS Management Console, AWS CLI, and the NetApp ONTAP CLI.

To monitor a volume's storage capacity (console)

The **Available storage** graph displays the amount of free storage capacity on a volume over time. The **Storage distribution** graph shows how a volume's storage capacity is currently distributed over 4 categories:

- User data
- Snapshot data
- Available volume capacity
- Other data

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. Choose **Volumes** in the left navigation column, then choose the ONTAP volume that you want to view storage capacity information for. The volume detail page appears.
3. In the second panel, choose the **Monitoring** tab. The **Available storage** and **Storage distribution** graphs display, along with several other graphs.





To monitor a volume's storage capacity (ONTAP CLI)

You can monitor how your volume's storage capacity is being consumed by using the `volume show-space` ONTAP CLI command. For more information, see `volume show-space` in the NetApp ONTAP Documentation Center.

1. To access the ONTAP CLI, establish an SSH session on the management port of the Amazon FSx for NetApp ONTAP file system or SVM by running the following command. Replace *`management_endpoint_ip`* with the IP address of the file system's management port.

   ```
   [~]$ ssh fsxadmin@management_endpoint_ip
   ```

   For more information, see Managing file systems with the ONTAP CLI.

2. View a volume's storage capacity usage by issuing the following command, replacing the following values:

   - Replace *svm_name* with the name of the SVM that the volume is created on.
   - Replace *vol_name* with name of the volume for which you are setting the data-tiering policy.

   ```
   ::> volume show-space -vserver svm_name -volume vol_name
   ```

   If the command is successful, you'll see output similar to the following:

   ```
   Vserver : svm_name
   Volume  : vol_name
   Feature                                     Used      Used%
   --------------------------------     ----------     ------
   User Data                                 140KB         0%
   Filesystem Metadata                     164.4MB         1%
   Inodes                                  10.28MB         0%
   Snapshot Reserve                        563.2MB         5%
   Deduplication                              12KB         0%
   Snapshot Spill                           9.31GB        85%
   Performance Metadata                      668KB         0%

   Total Used                              10.03GB        91%

   Total Physical Used                     10.03GB        91%
   ```

   The output of this command shows the amount of physical space that different types of data occupy on this volume. It also shows the percentage of the total volume's capacity that each type of data consumes. In this example, `Snapshot Spill` and `Snapshot Reserve` consume a combined 90 percent of the volume's capacity.

`Snapshot Reserve` shows the amount of disk space reserved for storing Snapshot copies. If the Snapshot copies storage exceeds the reserve space, it spills into the file system and this amount is shown under `Snapshot Spill`.

To increase the amount of available space, you can either increase the size of the volume, or you can delete snapshots that you are not using, as shown in the following procedures.

For FlexVol volume types (the default volume type for FSx for ONTAP volumes), you can also enable volume autosizing. When you enable autosizing, the volume size automatically increases when it reaches certain thresholds. You can also disable automatic snapshots. Both of these features are explained in the following sections.

Monitoring a volume's file capacity

You can use either of the following methods to view the maximum number of files allowed and the number of files already used on a volume.

- The CloudWatch volume metrics `FilesCapacity` and `FilesUsed`.
- In the Amazon FSx console, navigate to the **Available files (inodes)** chart in your volume's **Monitoring** tab. The following image shows the **Available files (inodes)** on a volume decreasing over time.



Managing FSx for ONTAP file systems

A file system is the primary Amazon FSx resource, analogous to an on-premises ONTAP cluster. You specify the solid state drive (SSD) storage capacity and throughput capacity for your file system,

and choose a virtual private cloud (VPC) in which to create the file system. Each file system has a management endpoint that you can use to manage resources and data with the ONTAP CLI or REST API.

File system resources

An Amazon FSx for NetApp ONTAP file system is composed of the following primary resources:

- The physical hardware of the file system itself, which includes the file servers and storage media.
- One or more highly-available (HA) file server pairs, which host your storage virtual machines (SVMs). First-generation file systems and Multi-AZ second-generation file systems have one HA pair, and second-generation Single-AZ file systems have up to 12 HA pairs. Each HA pair has a storage pool called an aggregate. The collection of aggregates across all HA pairs makes up your SSD storage tier.
- One or more SVMs that host the file system volumes and have their own credentials and access management.
- One or more volumes that virtually organize your data and are mounted by your clients.

The following image illustrates the architecture of a first-generation FSx for ONTAP file system with one HA pair, and the relationship between its primary resources. The FSx for ONTAP file system on the left is the simplest file system, with one SVM and one volume. The file system on the right has multiple SVMs, with some SVMs having multiple volumes. File systems and SVMs each have multiple management endpoints, and SVMs also have data access endpoints.



When creating an FSx for ONTAP file system, you define the following properties:

- **Deployment type** – The deployment type of your file system (Multi-AZ or Single-AZ). Single-AZ file systems replicate your data and offer automatic failover within a single Availability Zone. First-generation Single-AZ file systems support one HA pair. Second-generation Single-AZ file systems support up to 12 HA pairs. Multi-AZ file systems provide added resiliency by also replicating your data and supporting failover across multiple Availability Zones within the same AWS Region. First-generation and second-generation Multi-AZ file systems both support one HA pair.

  > **Note**
  >
  > You can't change your file system's deployment type after creation. If you want to change the deployment type (for example, to move from Single-AZ 1 to Single-AZ 2), you can back up your data and restore it on a new file system. You can also migrate your data with NetApp SnapMirror, with AWS DataSync, or with a third-party data copying tool. For more information, see Migrating to FSx for ONTAP using NetApp SnapMirror and Migrating to FSx for ONTAP using AWS DataSync.

- **Storage capacity** – This is the amount of SSD storage, up to 192 tebibytes (TiB) for first-generation file systems, 512 TiB for second-generation Multi-AZ file systems, and 1 pebibyte (PiB) for second-generation Single-AZ file systems.
- **SSD IOPS** – By default, each gigabyte of SSD storage includes three SSD IOPS (up to the maximum supported by your file system configuration). You can optionally provision additional SSD IOPS as needed.
- **Throughput capacity** – The sustained speed at which the file server can serve data.
- **Networking** – The VPC and subnets for the management and data access endpoints that your file system creates. For a Multi-AZ file system, you also define an IP address range and route tables.
- **Encryption** – The AWS Key Management Service (AWS KMS) key that's used to encrypt the file system data at rest.
- **Administrative access** – You can specify the password for the `fsxadmin` user. You can use this user to administer the file system by using the NetApp ONTAP CLI and REST API.

You can manage FSx for ONTAP file systems by using the NetApp ONTAP CLI or REST API. You can also set up SnapMirror or SnapVault relationships between an Amazon FSx file system and another

ONTAP deployment (including another Amazon FSx file system). Each FSx for ONTAP file system has the following file system endpoints that provide access to NetApp applications:

- **Management** – Use this endpoint to access the NetApp ONTAP CLI over Secure Shell (SSH), or to use the NetApp ONTAP REST API with your file system.
- **Intercluster** – Use this endpoint when setting up replication using NetApp SnapMirror or caching using NetApp FlexCache.

For more information, see Managing FSx for ONTAP resources using NetApp applications and Replicating your data using NetApp SnapMirror.

Creating file systems

This section describes how to create an FSx for ONTAP file system using the Amazon FSx console, AWS CLI, or the Amazon FSx API. You can create a file system in a virtual private cloud (VPC) that you own, or in a VPC that another AWS account has shared with you. There are considerations when creating a Multi-AZ file system in a VPC in which you are a participant. These considerations are explained in this topic.

By default, when you create a new file system from the Amazon FSx console, Amazon FSx automatically creates a file system with a single storage virtual machine (SVM) and one volume, allowing for quick access to data from Linux instances over the Network File System (NFS) protocol. When creating the file system, you can optionally join the SVM to an Active Directory to enable access from Windows and macOS clients over the Server Message Block (SMB) protocol. After your file system is created, you can create additional SVMs and volumes as needed.

To create a file system (console)

This procedure uses the **Standard create** creation option to create an FSx for ONTAP file system with a configuration that you customize for your needs. For information about using the **Quick create** creation option to rapidly create a file system with a default set of configuration parameters, see Create an Amazon FSx for NetApp ONTAP file system.

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. On the dashboard, choose **Create file system**.
3. On the **Select file system type** page, for **File system options**, choose **Amazon FSx for NetApp ONTAP**, and then choose **Next**.

4. In the **Creation method** section, choose **Standard create**.
5. In the **File system details** section, provide the following information:

   - For **File system name - optional**, enter a name for your file system. It's easier to find and manage your file systems when you name them. You can use a maximum of 256 Unicode letters, white space, and numbers, plus these special characters: + - = . _ : /
   - For **Deployment type** choose **Multi-AZ 2**, **Single-AZ 2**, **Multi-AZ 1**, or **Single-AZ 1**.
     - **Multi-AZ** file systems replicate your data and support failover across multiple Availability Zones in the same AWS Region. Multi-AZ 1 is a first-generation FSx for ONTAP file system. Multi-AZ 2 is a second-generation file system. They both support one high-availability (HA) pair.
     - **Single-AZ** file systems replicate your data and offer automatic failover within a single Availability Zone. Single-AZ 1 is a first-generation FSx for ONTAP file system that supports one HA pair. Single-AZ 2 is a second-generation file system that supports up to 12 HA pairs. For more information, see Managing high-availability (HA) pairs.

       For more information about deployment types, see *Availability, durability, and deployment options*.

       > **Note**
       >
       > You can't change your file system's deployment type after creation. If you want to change the deployment type (for example, to move from Single-AZ 1 to Single-AZ 2), you can back up your data and restore it on a new file system. You can also migrate your data with NetApp SnapMirror, with AWS DataSync, or with a third-party data copying tool. For more information, see Migrating to FSx for ONTAP using NetApp SnapMirror and Migrating to FSx for ONTAP using AWS DataSync.

   - For **SSD storage capacity**, enter the storage capacity of your file system, in gibibytes (GiB). Enter any whole number in the range of 1,024–1,048,576 GiB (up to 1 pebibyte [PiB]).

     You can increase the amount of storage capacity as needed at any time after you create the file system. For more information, see Managing storage capacity.
   - For **Provisioned SSD IOPS**, you have two options to provision the number of IOPS for your file system:
     - Choose **Automatic** (the default) if you want Amazon FSx to automatically provision 3 IOPS per GiB of SSD storage.

- Choose **User-provisioned** if you want to specify the number of IOPS. You can provision a maximum of 200,000 SSD IOPS per file system.

> **Note**
>
> You can increase your provisioned SSD IOPS after you create the file system. Keep in mind that the maximum level of SSD IOPS your file system can achieve is also dictated by your file system's throughput capacity even when provisioning additional SSD IOPS. For more information, see Impact of throughput capacity on performance and Managing storage capacity.

- For **Throughput capacity**, you have two options for determining your throughput capacity in megabytes per second (MBps):
  - Choose **Recommended throughput capacity** if you want Amazon FSx to automatically choose the throughput capacity based on the amount of storage capacity that you chose.
  - Choose **Specify throughput capacity** if you want to specify the amount of throughput capacity. If you choose this option, a **Throughput capacity** dropdown appears and is populated based on the deployment type that you chose. You can also choose the number of HA pairs (up to 12). For more information, see Managing high-availability (HA) pairs.

  Throughput capacity is the sustained speed at which the file server that hosts your file system can serve data. For more information, see Amazon FSx for NetApp ONTAP performance.

6. In the **Networking** section, provide the following information:

- For **Virtual Private Cloud (VPC)**, choose the VPC that you want to associate with your file system.
- For **VPC Security Groups**, you can choose a security group to associate with your file system's network interface. If you don't specify one, Amazon FSx will associate the VPC's default security group with your file system.
- (Multi-AZ only) For **Preferred subnet**, choose any value from the list of available subnets. Also choose a **Standby subnet** for the standby file server.
- (Single-AZ only) For **Subnet**, choose any value from the list of available subnets.
- (Multi-AZ only) For **VPC route tables**, specify the VPC route tables to create your file system's endpoints. Select all VPC route tables associated with the subnets in which your

clients are located. By default, Amazon FSx selects your VPC's default route table. For more information, see Accessing data from outside the deployment VPC.

> **Note**
>
> Amazon FSx manages these route tables for Multi-AZ file systems using tag-based authentication. These route tables are tagged with `Key: AmazonFSx; Value: ManagedByAmazonFSx`. When creating FSx for ONTAP Multi-AZ file systems using CloudFormation we recommend that you add the `Key: AmazonFSx; Value: ManagedByAmazonFSx` tag manually.

- For **Network type**, select either **IPv4** (for only IPv4 support) or **Dual-stack** (for both IPv4 and IPv6 support). You can change the network type of an existing file system at any time. For more information, see Changing network type.

  > **Note**
  >
  > If you intend to create an FSx for ONTAP file system that uses dual-stack mode, you must first assign an Amazon-provided IPv6 CIDR block to your VPC and subnets. For more information, see Add IPv6 support for your VPC in the *Amazon Virtual Private Cloud User Guide*.

- (Multi-AZ only) **Endpoint IPv4 address range** specifies the IPv4 address range in which the endpoints to access your file system are created.

  You have three options for the endpoint IPv4 address range:

  - **Unallocated IPv4 address range from your VPC** – Amazon FSx chooses the last 64 IP addresses from the VPC's primary CIDR range to use as the endpoint IPv4 address range for the file system. This range is shared across multiple file systems if you choose this option multiple times.

    > **Note**
    >
    > This option is grayed out if any of the last 64 IP addresses in a VPC's primary CIDR range are in use by a subnet. In this case, you can still choose an in-VPC address range (that is, a range that's not at the end of your primary CIDR range or a range

that's in a secondary CIDR of your VPC) by choosing the **Enter an IP address range** option.

- **Floating IPv4 address range outside your VPC** – Amazon FSx chooses a 198.19.x.0/24 address range that isn't already used by any other file systems with the same VPC and route tables.
- **Enter an IPv4 address range** – You can provide a CIDR range of your own choosing. The IPv4 address range that you choose can either be inside or outside the VPC's IP address range, as long as it doesn't overlap with any subnet.

> **Note**
>
> Do not choose any range that falls within the following CIDR ranges, as they are incompatible with FSx for ONTAP:
>
> - 0.0.0.0/8
> - 127.0.0.0/8
> - 198.19.0.0/20
> - 224.0.0.0/4
> - 240.0.0.0/4
> - 255.255.255.255/32

- (Multi-AZ and dual-stack only) **Endpoint IPv6 address range** specifies the IPv6 address range in which the endpoints to access your file system are created. You have two options for the endpoint IPv6 address range:
  - **Unallocated IPv6 address range from your VPC** – Amazon FSx chooses a block of 1024 available IPv6 addresses from one of the VPC's IPv6 CIDR ranges to use as the endpoint IPv6 address range for the file system.
  - **Enter an IPv6 address range** – You can provide an IPv6 CIDR range of your own choosing. The IPv6 address range that you choose can either be inside or outside the VPC's IPv6 address range, as long as it doesn't overlap with any subnet.

7. In the **Encryption** section, for **Encryption key**, choose the AWS Key Management Service (AWS KMS) encryption key that protects your file system's data at rest.
8. For **File system administrative password**, enter a secure password for the `fsxadmin` user. Confirm the password.

You can use the `fsxadmin` user to administer your file system using the ONTAP CLI and REST API. For more information about the `fsxadmin` user, see Managing file systems with the ONTAP CLI.

9. In the **Default storage virtual machine configuration** section, provide the following information:

   - In the **Storage virtual machine name** field, provide a name for the storage virtual machine. You can use a maximum of 47 alphanumeric characters, plus the underscore (_) special character.
   - For **SVM administrative password**, you can optionally choose **Specify a password** and provide a password for the SVM's `vsadmin` user. You can use the `vsadmin` user to administer the SVM using the ONTAP CLI or REST API. For more information about the `vsadmin` user, see Managing SVMs with the ONTAP CLI.

     If you choose **Don't specify a password** (the default), you can still use the file system's `fsxadmin` user to manage your file system using the ONTAP CLI or REST API, but you can't use your SVM's `vsadmin` user to do the same.
   - For **Volume security style**, choose between **Unix (Linux)** and **NTFS** for the volume. For more information, see Volume security style.
   - In the **Active Directory** section, you can join an Active Directory to the SVM. For more information, see Working with Microsoft Active Directory in FSx for ONTAP.

     If you don't want to join your SVM to an Active Directory, choose **Do not join an Active Directory**.

     If you want to join your SVM to a self-managed Active Directory domain, choose **Join an Active Directory**, and provide the following details for your Active Directory:

     - The NetBIOS name of the Active Directory computer object to create for your SVM. The NetBIOS name cannot exceed 15 characters.
     - The fully qualified domain name of your Active Directory. The domain name cannot exceed 255 characters.
     - **DNS server IP addresses** – The IPv4 or IPv6 addresses of the Domain Name System (DNS) servers for your domain.
     - **Service account credentials** – Choose how to provide your service account credentials:

- **Option 1**: AWS Secrets Manager secret ARN - The secret containing the username and password for a service account on your Active Directory domain. For more information, see Storing Active Directory credentials using AWS Secrets Manager.
- **Option 2**: Plaintext credentials
  - **Service account username** – The user name of the service account in your existing Microsoft Active Directory. Don't include a domain prefix or suffix. For example, for `EXAMPLE\ADMIN`, use only `ADMIN`.
  - **Service account password** – The password for the service account.
  - **Confirm password** – The password for the service account.

- (Optional) **Organizational Unit (OU)** – The distinguished path name of the organizational unit to which you want to join your file system.
- **Delegated file system administrators group** – The name of the group in your Active Directory that can administer your file system.

  If you are using AWS Managed Microsoft AD, you need to specify a group such as AWS Delegated FSx Administrators, AWS Delegated Administrators, or a custom group with delegated permissions to the OU.

  If you are joining to a self-managed AD, use the name of the group in your AD. The default group is `Domain Admins`.

10. In the **Default volume configuration** section, provide the following information for the default volume that is created with your file system:

    - In the **Volume name** field, provide a name for the volume. You can use up to 203 alphanumeric or underscore (_) characters.
    - (File systems with one HA pair only) For **Volume style**, choose either **FlexVol** or **FlexGroup**. FlexVol volumes are general-purpose volumes that can be up to 300 tebibytes (TiB) in size. FlexGroup volumes are intended for high-performance workloads and can be up to 20 PiB in size.
    - For **Volume size**, enter any whole number in the range of 20–314,572,800 mebibytes (MiB) for FlexVol volumes or 800 gibibytes (GiB)–2,400 TiB per HA pair for FlexGroup volumes. For example, a file system with 12 HA pairs would have a minimum volume size of 9,600 GiB and a maximum size of 20,480 TiB.
    - For **Volume type**, choose **Read-Write (RW)** to create a volume that is readable and writable or **Data Protection (DP)** to create a volume that is read-only and can be used as the

destination of a NetApp SnapMirror or SnapVault relationship. For more information, see Volume types.

- For **Junction path**, enter a location within the file system to mount the volume. The name must have a leading forward slash, for example `/vol3`.
- For **Storage efficiency**, choose **Enabled** to enable the ONTAP storage-efficiency features (deduplication, compression, and compaction). For more information, see Storage efficiency.
- For **Snapshot policy**, choose a snapshot policy for the volume. For more information about snapshot policies, see Snapshot policies.

  If you choose **Custom policy**, you must specify the policy's name in the **custom-policy** field. The custom policy must already exist on the SVM or in the file system. You can create a custom snapshot policy with the ONTAP CLI or REST API. For more information, see Create a Snapshot Policy in the NetApp ONTAP Product Documentation.

11. In the **Default volume storage tiering** section, for **Capacity pool tiering policy**, choose the storage pool tiering policy for the volume, which can be **Auto** (the default), **Snapshot Only**, **All**, or **None**. For more information about capacity pool tiering policies, see Volume tiering policies.

    For **Tiering policy cooling period**, if you have set storage tiering to either `Auto` and `Snapshot-only` policies.valid values are 2-183 days. A volume's tiering policy cooling period defines the number of days before data that has not been accessed is marked cold and moved to capacity pool storage.

12. In the **Default Volume SnapLock Configuration** section, for **SnapLock Configuration**, choose between **Enabled** and **Disabled**. For more information about configuring a SnapLock Compliance volume or a SnapLock Enterprise volume, see Understanding SnapLock Compliance and Understanding SnapLock Enterprise. For more information about SnapLock, see Protecting your data with SnapLock.
13. In **Backup and maintenance - *optional***, you can set the following options:

    - For **Daily automatic backup**, choose **Enabled** for automatic daily backups. This option is enabled by default.
    - For **Daily automatic backup window**, set the time of the day in Coordinated Universal Time (UTC) that you want the daily automatic backup window to start. The window is 30 minutes starting from this specified time. This window can't overlap with the weekly maintenance backup window.

- For **Automatic backup retention period**, set a period from 1–90 days that you want to retain automatic backups.
- For **Weekly maintenance window**, you can set the time of the week that you want the maintenance window to start. Day 1 is Monday, 2 is Tuesday, and so on. The window is 30 minutes starting from this specified time. This window can't overlap with the daily automatic backup window.

14. For **Tags - *optional***, you can enter a key and value to add tags to your file system. A tag is a case-sensitive key-value pair that helps you manage, filter, and search for your file system.

    Choose **Next**.

15. Review the file system configuration shown on the **Create file system** page. For your reference, note which file system settings you can modify after the file system is created.
16. Choose **Create file system**.

To create a file system (CLI)

- To create an FSx for ONTAP file system, use the create-file-system CLI command (or the equivalent CreateFileSystem API operation), as shown in the following example.

> **Note**
>
> You can't change your file system's deployment type after creation. If you want to change the deployment type (for example, to move from Single-AZ 1 to Single-AZ 2), you can back up your data and restore it on a new file system. You can also migrate your data with NetApp SnapMirror, with AWS DataSync, or with a third-party data copying tool. For more information, see Migrating to FSx for ONTAP using NetApp SnapMirror and Migrating to FSx for ONTAP using AWS DataSync.

```
aws fsx create-file-system \
    --file-system-type ONTAP \
    --storage-capacity 1024 \
    --storage-type SSD \
    --security-group-ids security-group-id \

    --subnet-ids subnet-abcdef1234567890b subnet-abcdef1234567890c \
    --ontap-configuration DeploymentType=MULTI_AZ_1,
```

```
ThroughputCapacity=512,PreferredSubnetId=subnet-abcdef1234567890b
```

After successfully creating the file system, Amazon FSx returns the file system's description in JSON format as shown in the following example.

```
{
  "FileSystem": {
    "OwnerId": "111122223333",
    "CreationTime": 1625066825.306,
    "FileSystemId": "fs-0123456789abcdef0",
    "FileSystemType": "ONTAP",
    "Lifecycle": "CREATING",
    "StorageCapacity": 1024,
    "StorageType": "SSD",
    "VpcId": "vpc-11223344556677aab",
    "SubnetIds": [
      "subnet-abcdef1234567890b",
      "subnet-abcdef1234567890c"
    ],
    "KmsKeyId": "arn:aws:kms:us-east-1:111122223333:key/wJalrXUtnFEMI/K7MDENG/
bPxRfiCYEXAMPLEKEY",
    "ResourceARN": "arn:aws:fsx:us-east-1:111122223333:file-system/
fs-0123456789abcdef0",
    "Tags": [],
    "OntapConfiguration": {
      "DeploymentType": "MULTI_AZ_HA_1",
      "EndpointIpAddressRange": "198.19.0.0/24",
      "Endpoints": {
        "Management": {
          "DnsName": "management.fs-0123456789abcdef0.fsx.us-east-1.amazonaws.com"
        },
        "Intercluster": {
          "DnsName": "intercluster.fs-0123456789abcdef0.fsx.us-east-1.amazonaws.com"
        }
      },
      "DiskIopsConfiguration": {
                "Mode": "AUTOMATIC",
                "Iops": 3072
      },
      "PreferredSubnetId": "subnet-abcdef1234567890b",
      "RouteTableIds": [
        "rtb-abcdef1234567890e",
```

```
        "rtb-abcd1234ef567890b"
      ],
      "ThroughputCapacity": 512,
      "WeeklyMaintenanceStartTime": "4:10:00"
    }
  }
}
```

> **Note**
>
> Unlike the process of creating a file system in the console, the `create-file-system` CLI command and the `CreateFileSystem` API operation don't create a default SVM or volume. To create an SVM, see Creating storage virtual machines (SVM); to create a volume, see Creating volumes.

Creating FSx for ONTAP file systems in shared subnets

VPC sharing enables multiple AWS accounts to create resources into shared, centrally-managed virtual private clouds (VPCs). In this model, the account that owns the VPC (owner) shares one or more subnets with other accounts (participants) that belong to the same organization from AWS Organizations.

Participant accounts can create FSx for ONTAP Single-AZ and Multi-AZ file systems in a VPC subnet that the owner account has shared with them. For a participant account to create a Multi-AZ file system, the owner account also needs to grant Amazon FSx permission to modify route tables in the shared subnets on behalf of the participant account. For more information, see Managing shared VPC support for Multi-AZ file systems.

> **Note**
>
> It is the participant account's responsibility to coordinate with the VPC owner to prevent the creation of any subsequent VPC subnets that will overlap with the in-VPC CIDR of the participant's file systems. If subnets do overlap, traffic to the file system can get interrupted.

Shared subnet requirements and considerations

When creating FSx for ONTAP file systems into shared subnets, note the following:

- The owner of the VPC subnet must share a subnet with a participant account before that account can create an FSx for ONTAP file system in it.
- You can't launch resources using the default security group for the VPC because it belongs to the owner. Additionally, participant accounts can't launch resources using security groups that are owned by other participants or the owner.
- In a shared subnet, the participant and the owner separately controls the security groups within each respective account. The owner account can see security groups that are created by the participants, but cannot perform any actions on them. If the owner account wants to remove or modify these security groups, the participant that created the security group must take the action.
- Participant accounts can view, create, modify, and delete Single-AZ file systems and their associated resources in subnets that the owner account has shared with them.
- Participant accounts can create, view, modify, and delete Multi-AZ file systems and their associated resources in subnets that the owner account has shared with them. Additionally, the owner account must also grant the Amazon FSx service permissions to modify route tables in the shared subnets on behalf of the participants account. For more information, see Managing shared VPC support for Multi-AZ file systems
- The shared VPC owner cannot view, modify, or delete resources that a participant creates in the shared subnet. This is in addition to the VPC resources that each account has different access to. For more information, see Responsibilities and permissions for owners and participants in the Amazon VPC User Guide.

For more information, see Share your VPC with other accounts in the Amazon VPC User Guide.

When sharing a VPC subnet

When sharing your subnets with participant accounts that will be creating FSx for ONTAP file systems in the shared subnets, you will need to do the following:

- The VPC owner needs to use AWS Resource Access Manager to securely share VPCs and subnets with other AWS accounts. For more information, see Sharing your AWS resources in the AWS Resource Access Manager User Guide.
- The VPC owner needs to share one or more VPCs with a participant account. For more information, see Share your VPC with other accounts in the Amazon Virtual Private Cloud User Guide.

- For participant accounts to create FSx for ONTAP Multi-AZ file systems, the VPC owner must also grant the Amazon FSx service permissions to create and modify route tables in the shared subnets on behalf of the participant accounts. This is because FSx for ONTAP Multi-AZ file systems use floating IP addresses so that connected clients can seamlessly transition between the preferred and standby file servers during a failover event. When a failover event occurs, Amazon FSx updates all routes in all route tables associated with the file system to point to the currently active file server.

Managing shared VPC support for Multi-AZ file systems

Owner accounts can manage whether or not participant accounts can create Multi-AZ FSx for ONTAP file systems in VPC subnets that the owner has shared with participants using the AWS Management Console, AWS CLI, and API, as described in the following sections.

To manage VPC sharing for Multi-AZ file systems (console)

Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.

1. In the navigation pane, choose **Settings**.
2. Locate the **Multi-AZ shared VPC settings** on the **Settings** page.
   - To enable VPC sharing for Multi-AZ file systems in VPC subnets that you share, choose **Enable route table updates from participant accounts**.
   - To disable VPC sharing for Multi-AZ file systems in all VPCs that you own, choose **Disable route table updates from participant accounts**. The confirmation screen is displayed.

   > **Important**
   >
   > We strongly recommend that participant-created Multi-AZ file systems in the shared VPC are deleted before you disable this feature. Once the feature is disabled, these file systems will enter a `MISCONFIGURED` state and will be at risk of becoming unavailable.

3. Enter **`confirm`** and choose **Confirm** to disable the feature.

To manage VPC sharing for Multi-AZ file systems (AWS CLI)

1. To view the current setting for Multi-AZ VPC sharing, use the describe-shared-vpc-configuration CLI command, or the equivalent DescribeSharedVpcConfiguration API command, shown as follows:

```
$ aws fsx describe-shared-vpc-configuration
```

The service responds to a successful request as follows:

```
{
    "EnableFsxRouteTableUpdatesFromParticipantAccounts": "false"
}
```

2. To manage the Multi-AZ shared VPC configuration, use the update-shared-vpc-configuration CLI command, or the equivalent UpdateSharedVpcConfiguration API command. The following example enables VPC sharing for Multi-AZ file systems.

```
$ aws fsx update-shared-vpc-configuration --enable-fsx-route-table-updates-from-participant-accounts true
```

The service responds to a successful request as follows:

```
{
    "EnableFsxRouteTableUpdatesFromParticipantAccounts": "true"
}
```

3. To disable the feature, set `EnableFsxRouteTableUpdatesFromParticipantAccounts` to `false`, as shown in the following example.

```
$ aws fsx update-shared-vpc-configuration --enable-fsx-route-table-updates-from-participant-accounts false
```

The service responds to a successful request as follows:

```
{
    "EnableFsxRouteTableUpdatesFromParticipantAccounts": "false"
}
```

Updating file systems

This topic explains which properties of an existing file system that you can update, and provides procedures to do so using the Amazon FSx console and CLI. You can update the following FSx for ONTAP file system properties using the Amazon FSx console, AWS CLI, and API:

- **Automatic daily backups**. Turns automatic daily backups on or off, modifies the backup window and the backup retention period. For more information, see Automatic daily backups.
- **Weekly maintenance window**. Sets the day of the week and time that Amazon FSx performs file system maintenance and updates. For more information, see Optimizing performance with Amazon FSx maintenance windows.
- **File system administrative password**. Changes the password for the file system's `fsxadmin` user. You can use the `fsxadmin` user to administer your file system using the ONTAP CLI and REST API. For more information about the `fsxadmin` user, see Managing file systems with the ONTAP CLI.
- **Amazon VPC route tables**. With Multi-AZ FSx for ONTAP file systems, the endpoints you use to access data over NFS or SMB and the management endpoints to access the ONTAP CLI, API, and NetApp Console use floating IP addresses in the Amazon VPC route tables that you associate with your file system. You can associate new route tables that you create with your existing Multi-AZ file systems—allowing you to configure which clients can access your data even as your network evolves. You can also disassociate (remove) existing route tables from your file system.

> **Note**
>
> Amazon FSx manages VPC route tables for Multi-AZ file systems using tag-based authentication. These route tables are tagged with `Key: AmazonFSx; Value: ManagedByAmazonFSx`. When creating or updating FSx for ONTAP Multi-AZ file systems using CloudFormation we recommend that you add the `Key: AmazonFSx; Value: ManagedByAmazonFSx` tag manually.

To update a file system (console)

The following procedures provide you with instructions on how to make updates to an existing FSx for ONTAP file system using the AWS Management Console.

To update automatic daily backups

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. To display the file system details page, in the left navigation pane, choose **File systems**, and then choose the FSx for ONTAP file system that you want to update.
3. Choose the **Backups** tab in the second panel on the page.
4. Choose **Update**.
5. Modify the automatic daily backup settings for this file system.
6. Choose **Save** to save your changes.

To update the weekly maintenance window

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. To display the file system details page, in the left navigation pane, choose **File systems**, and then choose the FSx for ONTAP file system that you want to update.
3. Choose the **Administration** tab in the second panel on the page.
4. In the **Maintenance** pane, choose **Update**.
5. Modify when the weekly maintenance window occurs for this file system.
6. Choose **Save** to save your changes.

To change the file system administrative password

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. To display the file system details page, in the left navigation pane, choose **File systems**, and then choose the FSx for ONTAP file system that you want to update.
3. Choose the **Administration** tab.
4. In the **ONTAP administration** panel, choose **Update** under **ONTAP administrator password**.
5. In the **Update ONTAP administrator credentials** dialog box, enter a new password in the **ONTAP administrative password** field.
6. Use the **Confirm password** field to confirm the password.
7. Choose **Update credentials** to save your change.

> **Note**
>
> If you receive an error stating that the new password does not meet the password requirements, you can use the `security login role config show` ONTAP CLI command to view the password requirement settings on the file system. For more information, including instructions on how to change password setting, see Updating the `fsxadmin` account password fails.

To update VPC route tables on Multi-AZ file systems

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. To display the file system details page, in the left navigation pane, choose **File systems**, and then choose the FSx for ONTAP file system that you want to update.
3. For **Actions**, choose **Update file system > Update route tables**. Or, in the **Network & security** panel, choose **Manage** next to the file system's **Route tables**.
4. In the **Manage route tables** dialog box. do one of the following:
   - To associate a new VPC route table, select a route table from the **Associate new route tables** dropdown list, and then choose **Associate**.
   - To disassociate an existing VPC route table, select a route table from the **Current route tables** pane, and then choose **Disassociate**.
5. Choose **Close**.

To update a file system (CLI)

The following procedure illustrates how to make updates to an existing FSx for ONTAP file system using the AWS CLI.

1. To update the configuration of an FSx for ONTAP file system, use the update-file-system CLI command (or the equivalent UpdateFileSystem API operation), as shown in the following example.

```
aws fsx update-file-system \
    --file-system-id fs-0123456789abcdef0 \
    --ontap-configuration
 AutomaticBackupRetentionDays=30,DailyAutomaticBackupStartTime=01:00, \
```

```
    WeeklyMaintenanceStartTime=1:01:30,AddRouteTableIds=rtb-0123abcd, \
    FsxAdminPassword=new-fsx-admin-password
```

2. To disable automatic daily backups, set the `AutomaticBackupRetentionDays` property to 0. Setting it to 0 disables automatic backups and deletes all existing automatic backups for the file system's volumes.

```
aws fsx update-file-system \
    --file-system-id fs-0123456789abcdef0 \
    --ontap-configuration AutomaticBackupRetentionDays=0
```

Managing high-availability (HA) pairs

Each FSx for ONTAP file system is powered by one or more high-availability (HA) pairs of file servers in an active-standby configuration. In this configuration, there is a preferred file server that actively serves traffic and a secondary file server that takes over if the active server is unavailable. FSx for ONTAP first-generation file systems are powered by one HA pair, which delivers up to 4 GBps of throughput capacity and 160,000 SSD IOPs. FSx for ONTAP second-generation Multi-AZ file systems are powered by one HA pair as well, and they deliver up to 6 GBps of throughput capacity and 200,000 SSD IOPS. FSx for ONTAP second-generation Single-AZ file systems are powered by up to 12 HA pairs, which can deliver up to 72 GBps of throughput capacity and 2,400,000 SSD IOPS (6 GBps of throughput capacity and 200,000 SSD IOPS per HA pair).

When you create your file system from the Amazon FSx console, Amazon FSx recommends the number of HA pairs that you should use based on your desired SSD storage. You can also manually choose the number of HA pairs based on your workload and performance requirements. We recommend that you use a single HA pair if your file system requirements are satisfied by up to 6 GBps of throughput capacity and 200,000 SSD IOPs, and multiple HA pairs if your workloads need higher levels of performance scalability.

Each HA pair has one aggregate, which is a logical set of physical disks.

> **Note**
>
> You can add HA pairs to second-generation Single-AZ file systems. For more information, see Adding high-availability (HA) pairs. Otherwise, you can migrate data between file systems (with different HA pairs) using SnapMirror, AWS DataSync, or by restoring your data from a backup to a new file system.

Adding high-availability (HA) pairs

FSx for ONTAP file systems are composed of one or more HA pairs of file servers. First-generation file systems and second-generation Multi-AZ file systems support one HA pair whereas second-generation Single-AZ file systems support up to 12 HA pairs. You can also add more HA pairs after creating a second-generation Single-AZ file system (up to the maximum of 12). Adding HA pairs isn't disruptive and typically takes only a few minutes to complete.

Consider the following points when adding HA pairs to your file system:

- Adding HA pairs to your file system introduces new file servers with their own storage (or aggregate). The new HA pairs have the same throughput capacity and storage capacity as your file system's existing HA pairs. For example, assume that your file system has two HA pairs with a total of 12 GBps of throughput capacity and 2 tebibytes (TiB) of SSD storage. If you add one new HA pair, then your file system will have 18 GBps of throughput capacity and 3 TiB of SSD storage.
- To benefit from the additional performance of the new HA pairs, you need to move some of your existing volumes to the new HA pairs and remount clients to connect to them. For more information, see Balancing workloads across HA pairs.
- You can't modify your file system's throughput capacity, SSD storage capacity, or provisioned SSD IOPS when adding HA pairs or while an update to add HA pairs is in progress.
- You can't remove HA pairs after you add them. We recommend scaling the throughput capacity of your file system if you need more performance temporarily (assuming that your file system isn't at the highest throughput capacity). This increases the throughput capacity of your file system's existing HA pairs.
- The iSCSI protocol is available on file systems that have six or fewer high-availability pairs (HA pairs). The NVMe/TCP protocol is available on second-generation file systems that have six or fewer HA pairs. For more information, see Accessing your FSx for ONTAP data.
- When you add new HA pairs to your file system, the NVMe cache is enabled by default for the new file system nodes. We recommend disabling it for throughput-heavy workloads. For more information, see Managing the NVMe cache.

To add HA pairs

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.

2. To display the file system details page, in the left navigation pane, choose **File systems**, and then choose the FSx for ONTAP file system that you want to update.
3. On the **Summary** panel, for **Number of HA pairs**, choose **Update**.
4. From the **HA Pairs** dropdown, select the number of HA pairs that you want to add to your file system.
5. Choose the **Update** button.

After you add HA pairs, it's important to rebalance your existing data to ensure that your I/O remains evenly distributed across your file system's HA pairs. For more information, see Balancing workloads across HA pairs.

Balancing workloads across HA pairs

If you have a file system with multiple high-availability (HA) pairs, then its throughput and storage are spread across each of your HA pairs. FSx for ONTAP automatically balances your files as they are written to your file system, but your workload data and I/O are no longer balanced once you add HA pairs. Additionally, in rare cases, your workload data or I/O could become unbalanced across your file system's existing HA pairs, which can impact your workload's overall performance. If your workload is ever imbalanced, you can rebalance it across each of your file system's HA pairs (and their commensurate file servers and *aggregates*—the storage pools which make up your primary storage tier).

Topics

- Primary storage utilization balance
- File server and disk performance utilization imbalance
- Mapping CloudWatch dimensions to ONTAP CLI and REST API resources
- Rebalancing clients
- Rebalancing volumes

Primary storage utilization balance

Your file system's primary storage capacity is divided evenly among each of your HA pairs in storage pools called aggregates. Each HA pair has one aggregate. We recommend that you maintain an average utilization no higher than 80% for your primary storage tier on an ongoing basis. For file systems with multiple HA pairs, we recommend that you maintain an average utilization of up to 80% for every aggregate.

Maintaining 80% utilization ensures there is free space for new incoming data, and maintains a healthy overhead for maintenance operations which can temporarily claim free space on your aggregates.

If you notice that your aggregates are imbalanced, you can either increase your file system's primary storage capacity (commensurately increasing the storage capacity of each aggregate), or you can move your volumes between aggregates. For more information, see Moving volumes between aggregates.

File server and disk performance utilization imbalance

Your file system's total performance capabilities (such as the network throughput, file server to disk throughput and IOPS, and disk IOPS) is divided evenly among your file system's HA pairs. We recommend that you maintain an average utilization below 50% (and a maximum peak utilization below 80%) for all performance limits on an ongoing basis—this goes for both the overall utilization of your file system's file server resources across all HA pairs, as well as on a per-file server basis.

If you notice that your file server performance utilization is imbalanced—and the file servers on which your workload is imbalanced have an ongoing utilization of over 80%—you can use the ONTAP CLI and REST API to further diagnose the cause of performance imbalance and remediate it. Following is a table of possible imbalance indicators and next steps for further diagnosis.

If your file system's...	Then...
File server disk throughput or file server disk IOPS are imbalanced	You may be experiencing I/O hotspotting on a subset of HA pairs (a subset of your volumes containing an outsized amount of data being accessed) which can limit your workload's overall performance because it's bottlenecked against a subset of HA pairs. For each highly-utilized file server, check the most-utilized volumes to see which volumes have the most activity within an aggregate. For more information on this procedure, see Rebalancing volumes.
Network throughput is imbalanced, but your file server disk throughput, file server disk IOPS, or	Your data is evenly-distributed across HA pairs, but your clients are not. For the file servers which have more network throughput utilization than others, check the top clients for each file server, then rebalance those clients by unmounting any volumes from those clients and remounting them using a different endpoint on a different HA pair. For more information on this procedure, see Rebalancing clients.

If your file system's...	Then...
disk IOPS are not imbalanced	

Mapping CloudWatch dimensions to ONTAP CLI and REST API resources

Your second-generation file system has Amazon CloudWatch metrics with the `FileServer` or `Aggregate` dimension. In order to further diagnose cases of imbalance, you need to map these dimension values to specific file servers (or *nodes*) and aggregates in the ONTAP CLI or REST API.

- For file servers, each file server name maps to a file server (or node) name in ONTAP (for example, `FsxId01234567890abcdef-01`). Odd-numbered file servers are preferred file servers (that is, they service traffic unless the file system has failed over to the secondary file server), while even-numbered file servers are secondary file servers (that is, they serve traffic only when their partner is unavailable). Because of this, secondary file servers will typically show less utilization than preferred file servers.
- For aggregates, each aggregate name maps to an aggregate in ONTAP (for example, `aggr1`). There is one aggregate for every HA pair, meaning aggregate `aggr1` is shared by file servers `FsxId01234567890abcdef-01` (the active file server) and `FsxId01234567890abcdef-02` (the secondary file server) in an HA pair, aggregate `aggr2` is shared by file servers `FsxId01234567890abcdef-03` and `FsxId01234567890abcdef-04`, and so on.

You can view the mappings between all aggregates and file servers using the ONTAP CLI.

1. To SSH into the NetApp ONTAP CLI of your file system, follow the steps documented in the Using the NetApp ONTAP CLI section of the *Amazon FSx for NetApp ONTAP User Guide*.

   ```
   ssh fsxadmin@file-system-management-endpoint-ip-address
   ```

2. Use the storage aggregate show command, specifying the `-fields node` parameter.

   ```
   ::> storage aggregate show -fields node
   aggregate                     node
   ----------------------------- -------------------------
   aggr1                         FsxId01234567890abcdef-01
   aggr2                         FsxId01234567890abcdef-03
   aggr3                         FsxId01234567890abcdef-05
   ```

```
aggr4                          FsxId01234567890abcdef-07
aggr5                          FsxId01234567890abcdef-09
aggr6                          FsxId01234567890abcdef-11
6 entries were displayed.
```

Rebalancing clients

After adding HA pairs or if you're experiencing I/O imbalance across file servers (specifically with network throughput utilization), you can rebalance your clients. If you're rebalancing clients after adding HA pairs, you can skip to Remounting clients. Otherwise, you should first identify high-traffic clients you want to move to rebalance your workload I/O.

If you're experiencing I/O imbalance across file servers (specifically with Network throughput utilization), high I/O clients may be the cause. To identify high-traffic clients, use the ONTAP CLI.

Identify high-traffic clients

1. To SSH into the NetApp ONTAP CLI of your file system, follow the steps documented in the Using the NetApp ONTAP CLI section of the *Amazon FSx for NetApp ONTAP User Guide*.

   ```
   ssh fsxadmin@file-system-management-endpoint-ip-address
   ```

2. To view the highest-traffic clients, use the statistics top client show ONTAP CLI command. You can optionally specify the `-node` parameter to only view the top clients for a specific file server. If you are diagnosing imbalance for a specific file server, use the `-node` parameter, replacing `node_name` with the name of the file server (for example, `FsxId01234567890abcdef-01`).

   You can optionally add the `-interval` parameter, providing the interval over which to measure (in seconds) before each report is output. Increasing the interval (for example, to the maximum 300 seconds) provides a longer-term sample for the amount of traffic driven to each volume. The default is 5 (seconds).

   ```
   ::> statistics top client show -node FsxId01234567890abcdef-01 [-interval [5,300]]
   ```

   In the output, the top clients are shown by their IP address and port.

   ```
                                                    *Total     Total
              Client    Vserver          Node           Ops     (Bps)
   ```

```
------------------ --------- ------------------------ ------ ---------
 172.17.236.53:938 svm01     FsxId01234567890abcdef-01   2143 140443648
172.17.236.160:898 svm02     FsxId01234567890abcdef-01    812  53215232
```

Remounting clients

- You can rebalance clients to other HA pairs. To do so, unmount the volume from the client and remount it using the DNS name for the SVM's NFS/SMB endpoint—this returns a random endpoint corresponding to a random HA pair.

  We recommend you re-use the DNS name, but you have the option to explicitly choose which HA pair a given client mounts. To guarantee that you are mounting a client to a different endpoint, you can instead specify a different endpoint IP address than the one that corresponds to the file server that is experiencing high traffic. You can do so by running the following command:

  ```
  ::> network interface show -vserver svm_name -lif nfs_smb_management* -fields
   address,curr-node
  vserver   lif                  address      curr-node
  --------- -------------------- ------------ ------------------------
  svm01 nfs_smb_management_1 172.31.15.89 FsxId01234567890abcdef-01
  svm01 nfs_smb_management_3 172.31.8.112 FsxId01234567890abcdef-03
  2 entries were displayed.
  ```

  According to the example output for the `statistics top client show` command, client `172.17.236.53` is driving high traffic to `FsxId01234567890abcdef-01`. The output of the `network interface show` command indicates this is the address `172.31.15.89`. To mount to a different endpoint, select any other address (in this example, the only other address is `172.31.8.112`, corresponding to `FsxId01234567890abcdef-03`).

Rebalancing volumes

If you're experiencing I/O imbalance across your volumes or aggregates, you can rebalance volumes in order to redistribute your I/O traffic across your volumes.

> **Note**
>
> If you're experiencing storage utilization imbalance across your aggregates, there is generally not any performance impact unless the high utilization is coupled with I/O imbalance. While you can move volumes between aggregates to balance storage utilization, we recommend only moving volumes if you are seeing a performance impact, as moving volumes can have adverse impact on performance if you don't also consider the I/O driven to each volume you're considering moving.

1. To SSH into the NetApp ONTAP CLI of your file system, follow the steps documented in the Using the NetApp ONTAP CLI section of the *Amazon FSx for NetApp ONTAP User Guide*.

   ```
   ssh fsxadmin@file-system-management-endpoint-ip-address
   ```

2. Use the statistics volume show ONTAP CLI command to view the highest-traffic volumes for a given aggregate, with the following changes:

   - Replace `aggregate_name` with the aggregate's name (for example, `aggr1`).
   - You can optionally add the `-interval` parameter, providing the interval over which to measure (in seconds) before each report is output. Increasing the interval (for example, to the maximum 300 seconds) provides a longer-term sample for the amount of traffic driven to each volume. The default is 5 (seconds).

   ```
   ::> statistics volume show -aggregate aggregate_name -sort-key total_ops [-interval
    [5,300]]
   ```

   Depending on the interval you chose, it can take up to 5 minutes to show data. The command shows all volumes in the aggregate, along with the amount of traffic being driven to each aggregate.

   ```
                              *Total Read Write Other      Read Write Latency
       Volume Vserver Aggregate    Ops  Ops   Ops   Ops     (Bps) (Bps)    (us)
   ---------- ------- --------- ------ ---- ----- ----- --------- ----- -------
   vol1__0007    svm1     aggr1   4078 4078     0     0 267255808     0    1092
   vol1__0005    svm1     aggr1   4078 4078     0     0 267255808     0    1086
   vol1__0003    svm1     aggr1   4077 4077     0     0 267223040     0    1086
   vol1__0001    svm1     aggr1   4077 4077     0     0 267239424     0    1087
   ```

```
vol1__0008    svm1    aggr2   2314 2314     0     0 151650304     0    1112
vol1__0006    svm1    aggr2   2144 2144     0     0 140509184     0    1104
vol1__0002    svm1    aggr2   2183 2183     0     0 143065088     0    1106
vol1__0004    svm1    aggr2   2183 2183     0     0 143065088     0    1103
```

The volume statistics are shown on a per-constituent basis (for example, `vol1__0015` is the 15th constituent for FlexGroup `vol1`). You can see from the example output, the constituents for `aggr1` are more highly-utilized than the constituents for `aggr2`. To balance traffic between aggregates, you can move the constituent volumes between aggregates so that traffic is more evenly distributed.

3. If you have added new HA pairs, then you should move existing volumes to new aggregates. For more information, see Moving volumes between aggregates.

Managing the NVMe cache

The NVMe cache is enabled by default on your second-generation file system. If your second-generation file system has a throughput-heavy workload, you can disable the NVMe cache to improve performance. The following procedure explains how to enable, disable, and validate your file system's NVMe cache.

To manage the NVMe cache

1. SSH into your ONTAP file system. For more information, see the section called “Using the NetApp ONTAP CLI”.

```
ssh fsxadmin@file-system-management-endpoint-ip-address
```

2. Use the **system node external-cache modify** ONTAP CLI commnd. Choose **`true`** to enable the NVMe cache or **`false`** to disable it.

```
::> system node external-cache modify -node * -is-enabled [true|false]
```

3. Use the **system node external-cache show** ONTAP CLI command to check if the NVMe cache is enabled or disabled.

```
::> system node external-cache show -node * -fields is-enabled
```

The NVMe cache is enabled or disabled on a per-node basis. When you add new high-availability (HA) pairs to your file system, each new node has the same default behavior of a new file system's nodes. Therefore, the NVMe cache would be enabled for any new nodes on a file system even if the existing nodes have it disabled. For more information, see Adding high-availability (HA) pairs.

Managing network type

When you create an FSx for ONTAP file system, you must specify a network type, which must be one of the following options:

- `IPv4` allows your file system to communicate using only Internet Protocol version 4 (IPv4).
- `Dual-stack` allows your file system to communicate using both Internet Protocol version 6 (IPv6) and IPv4.

You can change the network type of an existing FSx for ONTAP file system at any time using the Amazon FSx Management Console, AWS CLI, AWS API, or one of the AWS SDKs. For example, if your subnets support both IPv4 and IPv6 addressing, you can update your existing file system from IPv4-only to dual-stack mode, You can also update your dual-stack file system to IPv4-only.

Using dual-stack mode

You should use dual-stack mode if you need to access and manage your Amazon FSx file systems natively from IPv6 clients. By configuring your Amazon FSx file system to use dual-stack addressing, you can access your file data from IPv6 clients, as well as IPv4 clients, in the same Amazon VPC, in another AWS account's VPC, or in your on-premises network. For example, with an Amazon FSx file system configured to use dual-stack, you can have existing IPv4 clients and new IPv6 clients accessing your file data stored on your file system.

By default, Amazon FSx and Amazon VPC use the IPv4 addressing protocol. So as a prerequisite to using IPv6, you must first assign an Amazon-provided IPv6 Classless Inter-Domain Range (CIDR) block to your VPC and subnets before you can use IPv6 with your Amazon FSx file systems. For information on enabling IPv6 for your VPC, see Add IPv6 support for your VPC in the *Amazon Virtual Private Cloud User Guide*.

When creating FSx for ONTAP file systems set to dual-stack mode, you can specify the IPv6 address range, in addition to the existing IPv4 address range, in which the endpoints to access your file system will be created. By default, Amazon FSx chooses a block of 1024 IP addresses from one of the VPC's IPv6 CIDR ranges to use as the endpoint IPv6 address range for the file system.

Changing network type

You can modify a file system's network type using the Amazon FSx console, the AWS Command Line Interface (AWS CLI), or the Amazon FSx API.

To change a file system's network type (console)

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. Navigate to **File systems**, and choose the FSx for ONTAP file system that you want to change the network type for.
3. For **Actions**, choose **Update network type**. Or, in the **Network & security** panel, choose **Manage** next to the file system's **Network type**.

   The **Update network type** window appears.
4. For **Desired network type**, choose either **IPv4** or **Dual-stack**.
   - If you choose `IPv4`, no further configuration is required.
   - If you choose `Dual-stack`, specify the IPv6 address range that your file system endpoints will use:
     - **Unallocated IPv6 address range from your VPC** – Amazon FSx chooses an available /118 IP address range from one of the VPC's IPv6 CIDR ranges to use as the endpoint IPv6 address range for the file system.
     - **Enter an IPv6 address range** – You can provide an IPv6 CIDR range of your own choosing. The IP address range that you choose can either be inside or outside the VPC's IP address range, as long as it doesn't overlap with any subnet.
5. Choose **Update**.

To modify a file system's network type (CLI)

- To modify a file system's network type, use the update-file-system CLI command (or the equivalent UpdateFileSystem API operation), as shown in the following example.

```
aws fsx update-file-system \
    --file-system-id fs-0123456789abcdef0 \
    --network-type DUAL
```

Monitoring file system details

You can view detailed configuration information for your FSx for ONTAP file system using the Amazon FSx console, the AWS CLI, and the API and supported AWS SDKs.

To view detailed file system information:

- **Using the console** – Choose a file system to view the **File systems** detail page. The **Summary** panel shows the file system's ID, life cycle status, deployment type, SSD storage capacity, throughput capacity, provisioned IOPS, Availability Zones, and creation time.

  The following tabs provide detailed configuration information and editing for properties that can be modified:

  - Network & security – Displays the following file system administration information:
    - Default Amazon VPC
    - Amazon VPC route tables associated with a Multi-AZ file system
    - File system's network type (IPv4-only or dual-stack)
    - Endpoint IPv4 or IPv6 address range
    - The AWS Key Management Service (AWS KMS) key ID
  - Monitoring & performance – Displays CloudWatch alarms you've created, and metrics and warnings for the following categories:
    - Summary – high level summary of file system activity metrics
    - File system storage capacity
    - File server and disk performance

    For more information, see Monitoring with Amazon CloudWatch.
  - Administration – Displays the following file system administration information:
    - The DNS names and IP addresses of the file system's management and inter-cluster endpoints.
    - The ONTAP administrator username.
    - The option to update the ONTAP administrator password.
  - List of the file system's SVMs
  - List of the file system's volumes
  - Backup settings – change the file system's automatic daily backup setting.

- Updates – shows the status of user initiated updates made to the file system's configuration.
- Tags – view, edit, add, remove tag Key:Value pairs.

- **Using the CLI or API** – Use the describe-file-systems CLI command or the DescribeFileSystems API operation.

FSx for ONTAP file system status

You can view the status of an Amazon FSx file system by using the Amazon FSx console, the AWS CLI command describe-file-systems, or the API operation DescribeFileSystems.

File system status	Description
AVAILABLE	The file system has been successfully created and is available for use.
CREATING	Amazon FSx is creating a new file system.
DELETING	Amazon FSx is deleting an existing file system.
MISCONFIGURED	The file system is in a misconfigured but recoverable state.
FAILED	1. The file system has failed and Amazon FSx can't recover it. 2. When creating new file system, Amazon FSx was unable to create a new file system.

Deleting file systems

You can delete an FSx for ONTAP file system using the Amazon FSx console, the AWS CLI, and the Amazon FSx API and SDKs.

To delete a file system:

- **Using the console** – Follow the procedure described in Cleaning up resources.
- **Using the CLI or API** – First delete all the volumes and SVMs on your file system. Then use the delete-file-system CLI command or the DeleteFileSystem API operation.

Managing FSx for ONTAP storage virtual machines

In FSx for ONTAP, volumes are hosted on virtual file servers called storage virtual machines (SVMs). An SVM is an isolated file server with its own administrative credentials and endpoints for administering and accessing data. When you access data in FSx for ONTAP, your clients and workstations mount a volume, SMB share, or iSCSI LUN hosted by an SVM using the SVM's endpoint (IP address).

Amazon FSx automatically creates a default SVM on your file system when you create a file system using the AWS Management Console. You can create additional SVMs on your file system at any time using the console, AWS CLI, or Amazon FSx API and SDKs. You cannot create SVMs using the ONTAP CLI or REST API.

You can join your SVMs to a Microsoft Active Directory for file access authentication and authorization. For more information, see Working with Microsoft Active Directory in FSx for ONTAP.

Maximum number of SVMs per file system

The following table lists the maximum number of SVMs that you can create for a file system. The maximum number of SVMs depends on the amount of throughput capacity provisioned in megabytes per second (MBps), and also on the file system's network type.

High-availability (HA) pairs	Amount of throughput capacity (MBps)	Maximum number of SVMs per file system (IPv4-only mode)	Maximum number of SVMs per file system (dual-stack mode)
1 HA pair	128	6	6
	256	6	6
	384	6	6
	512	14	11
	768	6	6
	1,024	14	11
	1,536	14	11

High-availability (HA) pairs	Amount of throughput capacity (MBps)	Maximum number of SVMs per file system (IPv4-only mode)	Maximum number of SVMs per file system (dual-stack mode)
	2,048	24	11
	3,072	14	11
	4,096	24	11
	6,144	24	11
2–12 HA pairs	Any	11	11

Topics

- Creating storage virtual machines (SVM)
- Updating storage virtual machines (SVM)
- Managing SVM Microsoft Active Directory configurations
- Auditing file access
- Setting up an SMB server in a workgroup
- Monitoring storage virtual machine (SVM) configuration details
- Deleting storage virtual machines (SVM)

Creating storage virtual machines (SVM)

You can create an FSx for ONTAP SVM using the AWS Management Console, AWS CLI, and API.

The maximum number of SVMs you can create for a file system depends on your file system's deployment type, network type, and the amount of throughput capacity provisioned. For more information, see Maximum number of SVMs per file system.

SVM properties

When creating an SVM, you define the following properties:

- The FSx for ONTAP file system to which it belongs.

- The Microsoft Active Directory (AD) configuration – You can optionally join your SVM to a self-managed AD for authentication and access control of Windows and macOS clients. For more information, see Working with Microsoft Active Directory in FSx for ONTAP.
- The root volume security style – Set the root volume security style (Unix or NTFS) to align with the type of clients that you're using to access your data within the SVM. For more information, see Volume security style.
- The SVM administrative password – you can optionally set the password for the SVM's `vsadmin` user. For more information, see Managing SVMs with the ONTAP CLI.

To create a storage virtual machine (console)

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. In the left navigation pane, choose **Storage virtual machines**.
3. Choose **Create new storage virtual machine**.
4. For **File system**, choose the file system to create the storage virtual machine on.
5. In the **Storage virtual machine name** field, provide a name for the storage virtual machine. You can use a maximum of 47 alphanumeric characters, plus the underscore (_) special character.
6. For **SVM administrative password**, you can optionally choose **Specify a password** and provide a password for this SVM's `vsadmin` user. You can use the `vsadmin` user to administer the SVM using the ONTAP CLI or REST API. For more information about the `vsadmin` user, see Managing SVMs with the ONTAP CLI.

   If you choose **Don't specify a password** (the default), you can still use the file system's `fsxadmin` user to manage your file system using the ONTAP CLI or REST API, but you can't use your SVM's `vsadmin` user to do the same.
7. For **Active Directory**, you have the following options:

   - If you are not joining your file system to an Active Directory (AD), choose **Do not join an Active Directory**.
   - If you are joining your SVM to a self-managed AD domain, choose **Join an Active Directory**, and provide the following details for your AD. For more information, see Prerequisites for joining an SVM to a self-managed Microsoft AD.

- The NetBIOS name of the Active Directory computer object to create for your SVM. The NetBIOS name cannot exceed 15 characters. This is the name of this SVM in Active Directory.
- The fully qualified domain name (FQDN) of your Active Directory. The FQDN cannot exceed 255 characters.
- **DNS server IP addresses** – The IPv4 or IPv6 addresses of the DNS servers for your domain.
- **Service account credentials** – Choose how to provide your service account credentials:
  - **Option 1**: AWS Secrets Manager secret ARN - The secret containing the username and password for a service account on your Active Directory domain. For more information, see Storing Active Directory credentials using AWS Secrets Manager.
  - **Option 2**: Plaintext credentials
    - **Service account username** – The user name of the service account in your existing Microsoft Active Directory. Don't include a domain prefix or suffix. For example, for `EXAMPLE\ADMIN`, use only `ADMIN`.
    - **Service account password** – The password for the service account.
    - **Confirm password** – The password for the service account.
- (Optional) **Organizational Unit (OU)** – The distinguished path name of the organizational unit to which you want to join your file system.
- **Delegated file system administrators group** – The name of the group in your AD that can administer your file system.

  If you are using AWS Managed Microsoft AD, you must specify a group such as AWS Delegated FSx Administrators, AWS Delegated Administrators, or a custom group with delegated permissions to the OU.

  If you are joining to a self-managed AD, use the name of the group in your AD. The default group is `Domain Admins`.

8. For **SVM root volume security style**, choose the security style for the SVM depending on the type of clients that access your data. Choose **Unix (Linux)** if you primarily access your data using Linux clients; choose **NTFS** if you primarily access your data using Windows clients. For more information, see Volume security style.
9. Choose **Confirm** to create the storage virtual machine.

You can monitor the update progress on the **File systems** detail page, in the **Status** column of the **Storage virtual machines** pane. The storage virtual machine is ready for use when its status is **Created**.

To create a storage virtual machine (CLI)

- To create an FSx for ONTAP storage virtual machine (SVM), use the create-storage-virtual-machine CLI command (or the equivalent CreateStorageVirtualMachine API operation), as shown in the following example.

```
aws fsx create-storage-virtual-machine \
    --file-system-id fs-0123456789abcdef0 \
    --name svm1 \
    --svm-admin-password password \
    --active-directory-configuration
 SelfManagedActiveDirectoryConfiguration='{DomainName="corp.example.com", \
OrganizationalUnitDistinguishedName="OU=FileSystems,DC=corp,DC=example,DC=com",FileSystemAd
 \
UserName="FSxService",Password="password", \
   DnsIps=["10.0.1.18"]}',NetBiosName=amznfsx12345
```

After successfully creating the storage virtual machine, Amazon FSx returns its description in JSON format, as shown in the following example.

```
{
  "StorageVirtualMachine": {
    "CreationTime": 1625066825.306,
    "Endpoints": {
      "Management": {
        "DnsName": "svm-abcdef0123456789a.fs-0123456789abcdef0.fsx.us-
east-1.amazonaws.com",
        "IpAddressses": ["198.19.0.4"]
      },
      "Nfs": {
        "DnsName": "svm-abcdef0123456789a.fs-0123456789abcdef0.fsx.us-
east-1.amazonaws.com",
        "IpAddressses": ["198.19.0.4"]
      },
      "Smb": {
        "DnsName": "amznfsx12345",
        "IpAddressses": ["198.19.0.4"]
```

```
      },
      "SmbWindowsInterVpc": {
        "IpAddressses": ["198.19.0.5", "198.19.0.6"]
      },
      "Iscsi": {
        "DnsName": "iscsi.svm-abcdef0123456789a.fs-0123456789abcdef0.fsx.us-
east-1.amazonaws.com",
        "IpAddressses": ["198.19.0.7", "198.19.0.8"]
      }
    },
    "FileSystemId": "fs-0123456789abcdef0",
    "Lifecycle": "CREATING",
    "Name": "vol1",
    "ResourceARN": "arn:aws:fsx:us-east-1:123456789012:storage-virtual-machine/
fs-0123456789abcdef0/svm-abcdef0123456789a",
    "StorageVirtualMachineId": "svm-abcdef0123456789a",
    "Subtype": "default",
    "Tags": [],
    "ActiveDirectoryConfiguration": {
      "NetBiosName": "amznfsx12345",
      "SelfManagedActiveDirectoryConfiguration": {
        "UserName": "Admin",
        "DnsIps": [
          "10.0.1.3",
          "10.0.91.97"
        ],
        "OrganizationalUnitDistinguishedName": "OU=Computers,OU=customer-
ad,DC=customer-ad,DC=example,DC=com",
        "DomainName": "customer-ad.example.com"
      }
    }
  }
}
```

Updating storage virtual machines (SVM)

You can update the following storage virtual machine (SVM) configuration properties using the Amazon FSx console, AWS CLI, and Amazon FSx API:

- SVM administrative account password.

- SVM Active Directory (AD) configuration – You can join an SVM to an AD, or modify the AD configuration of an SVM already joined to an AD. For more information, see Managing SVM Microsoft Active Directory configurations.

To update the SVM administrator account credentials (console)

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. Choose the SVM to update as follows:
   - In the left navigation pane, choose **File systems**, and then choose the ONTAP file system for which you want to update an SVM.
   - Choose the **Storage virtual machines** tab.

     –Or–
   - To display a list of all the SVMs available in your AWS account in the current AWS Region, expand **ONTAP** and choose **Storage virtual machines**.
3. Choose the storage virtual machine that you want to update.
4. Choose **Actions > Update administrator password**. The **Update SVM administrative credentials** window appears.
5. Enter the new password for the `vsadmin` user, and confirm it.
6. Choose **Update credentials** to save the new password.

To update the SVM administrator account credentials (CLI)

- To update the configuration of an FSx for ONTAP SVM, use the update-storage-virtual-machine CLI command (or the equivalent UpdateStorageVirtualMachine API operation), as shown in the following example.

```
aws fsx update-storage-virtual-machine \
--storage-virtual-machine-id svm-abcdef01234567890 \
--svm-admin-password new-svm-password \
```

After successfully creating the storage virtual machine, Amazon FSx returns its description in JSON format, as shown in the following example.

```
{
```

```
  "StorageVirtualMachine": {
    "CreationTime": 1625066825.306,
    "Endpoints": {
      "Management": {
        "DnsName": "svm-abcdef01234567890.fs-0123456789abcdef0.fsx.us-
east-1.amazonaws.com",
        "IpAddressses": ["198.19.0.4"]
      },
      "Nfs": {
        "DnsName": "svm-abcdef01234567890.fs-0123456789abcdef0.fsx.us-
east-1.amazonaws.com",
        "IpAddressses": ["198.19.0.4"]
      },
      "Smb": {
        "DnsName": "amznfsx12345",
        "IpAddressses": ["198.19.0.4"]
      },
      "SmbWindowsInterVpc": {
        "IpAddressses": ["198.19.0.5", "198.19.0.6"]
      },
      "Iscsi": {
        "DnsName": "iscsi.svm-abcdef01234567890.fs-0123456789abcdef0.fsx.us-
east-1.amazonaws.com",
        "IpAddressses": ["198.19.0.7", "198.19.0.8"]
      }
    },
    "FileSystemId": "fs-0123456789abcdef0",
    "Lifecycle": "CREATING",
    "Name": "vol1",
    "ResourceARN": "arn:aws:fsx:us-east-1:123456789012:storage-virtual-machine/
fs-0123456789abcdef0/svm-abcdef01234567890",
    "StorageVirtualMachineId": "svm-abcdef01234567890",
    "Subtype": "default",
    "Tags": [],
    "ActiveDirectoryConfiguration": {
      "NetBiosName": "amznfsx12345",
      "SelfManagedActiveDirectoryConfiguration": {
        "UserName": "Admin",
        "DnsIps": [
          "10.0.1.3",
          "10.0.91.97"
        ],
        "OrganizationalUnitDistinguishedName": "OU=Computers,OU=customer-
ad,DC=customer-ad,DC=example,DC=com",
```

```
        "DomainName": "customer-ad.example.com"
      }
    }
  }
}
```

Managing SVM Microsoft Active Directory configurations

You can join an SVM to Microsoft Active Directory or modify the Microsoft Active Directory configuration of an SVM that's already joined to Microsoft Active Directory. FSx for ONTAP integrates with AWS Secrets Manager to securely manage your domain join service account credentials.

To update SVM Microsoft Active Directory configuration (console)

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. Choose the SVM to update as follows:
   - In the left navigation pane, choose **File systems**, and then choose the ONTAP file system for which you want to update an SVM.
   - Choose the **Storage virtual machines** tab.

     –Or–
   - To display a list of all the SVMs available in your AWS account in the current AWS Region, expand **ONTAP** and choose **Storage virtual machines**.
3. Choose the storage virtual machine that you want to update.
4. Choose **Actions > Update Microsoft Active Directory configuration**. The **Update Microsoft Active Directory configuration** window appears.
5. For **Domain join service account credentials**, choose **Managed in Secrets Manager** (recommended) to use Secrets Manager for secure credential management.

> **Note**
>
> Using Secrets Manager eliminates the need to store plaintext credentials and provides centralized credential management. For more information, see Storing Active Directory credentials using AWS Secrets Manager.

6. For **Secret**, choose an existing secret from Secrets Manager that contains your updated domain join service account credentials, or choose **Create new secret** to create one.
7. Update other Microsoft Active Directory configuration fields as needed for your environment.
8. Choose **Update configuration** to save the changes.

To update SVM Microsoft Active Directory configuration (CLI)

- To update the Microsoft Active Directory configuration of an FSx for ONTAP SVM, use the update-storage-virtual-machine CLI command with the `--active-directory-configuration` parameter, as shown in the following example.

```
aws fsx update-storage-virtual-machine \
--storage-virtual-machine-id svm-abcdef01234567890 \
--active-directory-configuration DomainJoinServiceAccountSecret=secret-arn
```

Auditing file access

Amazon FSx for NetApp ONTAP supports auditing of end-user accesses to files and directories in a storage virtual machine (SVM).

Topics

- File access auditing overview
- Overview of tasks for setting up file access auditing

File access auditing overview

File access auditing enables you to record end-user accesses of individual files and directories based on audit policies you define. File access auditing can help you improve your system's security and reduce the risk of unauthorized access to your system data. File access auditing helps your organizations remain compliant with data protection requirements, identify potential threats early, and reduce the risk of a data breach.

Across file and directory accesses, Amazon FSx supports logging of successful attempts (such as a user with sufficient permissions successfully accessing a file), failed attempts, or both. You can also turn off file access auditing at any time.

By default, audit event logs are stored in the EVTX file format, which allows you to view them using Microsoft Event Viewer.

SMB access events that can be audited

The following table lists the SMB file and folder access events can be audited.

Event ID (EVT/EVTX)	Event	Description	Category
560/4656	Open Object/Create Object	OBJECT ACCESS: Object (file or directory) open	File Access
563/4659	Open Object with the Intent to Delete	OBJECT ACCESS: A handle to an object (file or directory) was requested with the Intent to Delete	File Access
564/4660	Delete Object	OBJECT ACCESS: Delete Object (file or directory). ONTAP generates this event when a Windows client attempts to delete the object (file or directory)	File Access
567/4663	Read Object/Write Object/Get Object Attributes/Set Object Attributes	OBJECT ACCESS: Object access attempt (read, write, get attribute, set attribute). **Note** For this event, ONTAP audits only the first	File Access

Event ID (EVT/EVTX)	Event	Description	Category
		SMB read and first SMB write operation (success or failure) on an object. This prevents ONTAP from creating excessive log entries when a single client opens an object and performs many successive read or write operations to the same object.	
N/A/4664	Hard link	OBJECT ACCESS: An attempt was made to create a hard link	File Access
N/A/N/A ONTAP Event ID 9999	Rename Object	OBJECT ACCESS: Object renamed. This is an ONTAP event. It is not currently supported by Windows as a single event.	File Access

Event ID (EVT/EVTX)	Event	Description	Category
N/A/N/A ONTAP Event ID 9998	Unlink Object	OBJECT ACCESS: Object unlinked. This is an ONTAP event. It is not currently supported by Windows as a single event.	File Access

NFS access events that can be audited

The following NFS file and folder access events can be audited.

- READ
- OPEN
- CLOSE
- READDIR
- WRITE
- SETATTR
- CREATE
- LINK
- OPENATTR
- REMOVE
- GETATTR
- VERIFY
- NVERIFY
- RENAME

Overview of tasks for setting up file access auditing

Setting up FSx for ONTAP for file access auditing involves the following high-level tasks:

1. Familiarize yourself with the file access auditing requirements and considerations.

2. Create an auditing configuration on a specific SVM.
3. Enable auditing on that SVM.
4. Configure audit policies on your files and directories.
5. View the audit event logs after FSx for ONTAP emits them.

Task details are provided in the following procedures.

Repeat the tasks for any other SVM on your file system that you want to enable file access auditing for.

Auditing requirements

Before you configure and enable auditing on an SVM, you should be aware of the following requirements and considerations.

- NFS auditing supports audit Access Control Entries (ACEs) designated as type u, which generate an audit log entry when access is attempted on the object. For NFS auditing, there is no mapping between mode bits and audit ACEs. When converting ACLs to mode bits, audit ACEs are skipped. When converting mode bits to ACLs, audit ACEs are not generated.
- Auditing is dependent on having available space in the staging volumes. (A staging volume is dedicated volume created by ONTAP to store staging files, which are intermediate binary files on individual nodes where audit records are stored prior to conversion to an EVTX or XML file format.) You must ensure that there is sufficient space for the staging volumes in aggregates that contain audited volumes.
- Auditing is dependent on having available space in the volume containing the directory where converted audit event logs are stored. You must ensure that there is sufficient space in the volumes used to store event logs. You can specify the number of audit logs to retain in the auditing directory by using the `-rotate-limit` parameter when creating an auditing configuration, which can help to ensure that there is enough available space for the audit logs in the volume.

Creating auditing configurations on SVMs

Before you can begin auditing file and directory events, you must create an auditing configuration on the Storage Virtual Machine (SVM). After you create the auditing configuration, you must enable it on the SVM.

Before you use the `vserver audit create` command to create the auditing configuration, make sure you've created a directory to be used as the destination for logs, and that the directory doesn't have symlinks. You specify the destination directory with the `-destination` parameter.

You can create an auditing configuration that rotates audit logs based on log size or a schedule, as follows:

- To rotate audit logs based on log size, use this command:

```
vserver audit create -vserver svm_name -destination path [-format {xml|evtx}] [-
rotate-limit integer] [-rotate-size {integer[KB|MB|GB|TB|PB]}]
```

  The following example creates an auditing configuration for the SVM named `svm1` that audits file operations and CIFS (SMB) logon and logoff events (the default) using size-based rotation. The log format is EVTX (the default), logs are stored in the `/audit_log` directory, and you'll have a single log file at a time (up to 200MB in size).

```
vserver audit create -vserver svm1 -destination /audit_log -rotate-size 200MB
```

- To rotate audit logs based on a schedule, use this command:

```
vserver audit create -vserver svm_name -destination path [-format {xml|evtx}]
        [-rotate-limit integer] [-rotate-schedule-month chron_month]
        [-rotate-schedule-dayofweek chron_dayofweek] [-rotate-schedule-
day chron_dayofmonth]
        [-rotate-schedule-hour chron_hour] [-rotate-schedule-minute chron_minute]
```

  The `-rotate-schedule-minute` parameter is required if you are configuring time-based audit log rotation.

  The following example creates an auditing configuration for the SVM named `svm2` using time-based rotation. The log format is EVTX (the default) and the audit logs are rotated monthly, at 12:30 PM on all days of the week.

```
vserver audit create -vserver svm2 -destination /audit_log -rotate-size 200MB  -
rotate-schedule-month all -rotate-schedule-dayofweek all -rotate-schedule-hour 12 -
rotate-schedule-minute 30
```

You can use the `-format` parameter to specify whether the audit logs are created in the converted EVTX format (the default) or in the XML file format. The EVTX format allows you to view the log files with Microsoft Event Viewer.

By default, the categories of events to be audited are file access events (both SMB and NFS), CIFS (SMB) logon and logoff events, and authorization policy change events. You can have greater control over which events to log by the `-events` parameter, which has the following format:

```
-events {file-ops|cifs-logon-logoff|cap-staging|file-share|audit-policy-change|user-
account|authorization-policy-change|security-group}
```

For example, using `-events file-share` enables auditing of file share events.

For more information on the `vserver audit create` command, see Create an audit configuration.

Enabling auditing on an SVM

After you finish setting up the auditing configuration, you must enable auditing on the SVM. To do so, use the following command:

```
vserver audit enable -vserver svm_name
```

For example, use the following command to enable auditing on the SVM named `svm1`.

```
vserver audit enable -vserver svm1
```

You can disable access auditing at any time. For example, use the following command to turn off auditing on the SVM named `svm4`.

```
vserver audit disable -vserver svm4
```

When you disable auditing, the audit configuration isn't deleted on the SVM, which means that you can re-enable auditing on that SVM at any time.

Configuring file and folder audit policies

You need to configure audit policies on the files and folders that you want audited for user access attempts. You can configure audit policies to monitor both successful and failed access attempts.

You can configure both SMB and NFS audit policies. SMB and NFS audit policies have different configuration requirements and audit capabilities based on the security style of the volume.

Audit policies on NTFS security-style files and directories

You can configure NTFS audit policies by using the Windows Security tab or the ONTAP CLI.

To configure NTFS audit policies (Windows Security tab)

You configure NTFS audit policies by adding entries to NTFS SACLs that are associated with an NTFS security descriptor. The security descriptor is then applied to NTFS files and directories. These tasks are automatically handled by the Windows GUI. The security descriptor can contain discretionary access control lists (DACLs) for applying file and folder access permissions, SACLs for file and folder auditing, or both SACLs and DACLs.

1. From the **Tools** menu in Windows Explorer, select **Map network drive**.
2. Complete the **Map Network Drive** box:

   a. Choose a **Drive** letter.
   b. In the **Folder** box, type the SMB (CIFS) server name that contains the share, holding the data you want to audit and the name of the share.
   c. Choose **Finish**.

   The drive you selected is mounted and ready with the Windows Explorer window displaying files and folders contained within the share.
3. Select the file or directory for which you want to enable auditing access.
4. Right-click the file or directory, and then choose **Properties**.
5. Choose the **Security** tab.
6. Click **Advanced**.
7. Choose the **Auditing** tab.
8. Perform the desired actions:

If you want to...	Do the following
Set up auditing for a new user or group	1. Choose **Add**. 2. In the **Enter the object name to select** box, type the name of the user or group that you want to add.

If you want to...	Do the following
	3. Choose **OK**.
Remove auditing from a user or group	1. In the **Enter the object name to select** box, select the user or group that you want to remove. 2. Choose **Remove**. 3. Choose **OK**. 4. Skip the rest of this procedure.
Change auditing for a user or group	1. In the **Enter the object name to select** box, choose the user or group that you want to change. 2. Choose **Edit**. 3. Choose **OK**.

If you are setting up auditing on a user or group or changing auditing on an existing user or group, the **Auditing Entry for *object*** box opens.

9. In the **Apply to** box, select how you want to apply this auditing entry.

   If you are setting up auditing on a single file, the **Apply to** box is not active, as it defaults to This object only.

10. In the **Access** box, select what you want audited and whether you want to audit successful events, failure events, or both.

    - To audit successful events, choose the **Success** box.
    - To audit failure events, choose the **Failure** box.

    Choose the actions that you need to monitor to meet your security requirements. For more information about these auditable events, see your Windows documentation. You can audit the following events:

    - Full control
    - Traverse folder / execute file
    - List folder / read data
    - Read attributes

- Read extended attributes
- Create files / write data
- Create folders / append data
- Write attributes
- Write extended attributes
- Delete subfolders and files
- Delete
- Read permissions
- Change permissions
- Take ownership

11. If you do not want the auditing setting to propagate to subsequent files and folders of the original container, choose the **Apply these auditing entries to objects and/or containers within this container only** box.
12. Choose **Apply**.
13. After you finish adding, removing, or editing auditing entries, choose **OK**.

    The **Auditing Entry for *object*** box closes.
14. In the **Auditing** box, choose the inheritance settings for this folder. Choose only the minimal level that provides the auditing events that meet your security requirements.

    You can choose one of the following:

    - Choose the **Include inheritable auditing entries from this object's parent** box.
    - Choose the **Replace all existing inheritable auditing entries on all descendants with inheritable auditing entries from this object** box.
    - Choose both boxes.
    - Choose neither box.

    If you are setting SACLs on a single file, the **Replace all existing inheritable auditing entries on all descendants with inheritable auditing entries from this object** box is not present in the **Auditing** box.
15. Choose **OK**.

To configure NTFS audit policies (ONTAP CLI)

By using the ONTAP CLI, you can configure NTFS audit policies without needing to connect to the data using an SMB share on a Windows client.

- You can configure NTFS audit policies by using the vserver security file-directory ntfs sacl add command family.

For example, the following command creates a security policy named p1 for the SVM named vs0.

```
vserver security file-directory policy create -policy-name p1 -vserver vs0
```

Then, the following command applies the p1 security policy to the vs0 SVM.

```
vserver security file-directory apply -vserver vs0 -policy-name p1
```

Audit policies on UNIX security-style files and directories

You configure auditing for UNIX security-style files and directories by adding audit ACEs (access control expressions) to NFS v4.x ACLs (access control lists). This allows you to monitor certain NFS file and directory access events for security purposes.

> **Note**
>
> For NFS v4.x, both discretionary and system ACEs are stored in the same ACL. Therefore, you must be careful when adding audit ACEs to an existing ACL to avoid overwriting and losing an existing ACL. The order in which you add the audit ACEs to an existing ACL does not matter.

To configure UNIX audit policies

1. Retrieve the existing ACL for the file or directory by using the nfs4_getfacl or equivalent command.
2. Append the desired audit ACEs.
3. Apply the updated ACL to the file or directory by using the nfs4_setfacl or equivalent command.

This example uses the `-a` option to give a user (named `testuser`) read permissions to the file named `file1`.

```
nfs4_setfacl -a "A::testuser@example.com:R" file1
```

Viewing audit event logs

You can view audit event logs saved in the EVTX or XML file formats.

- EVTX file format – You can open the converted EVTX audit event logs as saved files using Microsoft Event Viewer.

  There are two options that you can use when viewing event logs using Event Viewer:

  - **General view**: Information that is common to all events is displayed for the event record. The event-specific data for the event record is not displayed. You can use the detailed view to display event-specific data.
  - **Detailed view**: A friendly view and a XML view are available. The friendly view and the XML view display both the information that is common to all events and the event-specific data for the event record.
- XML file format – You can view and process XML audit event logs on third-party applications that support the XML file format. XML viewing tools can be used to view the audit logs provided you have the XML schema and information about definitions for the XML fields.

Setting up an SMB server in a workgroup

You can configure a Server Message Block (SMB) server in a workgroup as an alternative to joining an SVM to a Microsoft Active Directory when the Microsoft Active Directory domain infrastructure is not available. A workgroup is a peer-to-peer network that uses the SMB protocol, and has only local accounts and groups.

The process of setting up an SMB server as a member in a workgroup consists of the following:

- Creating the SMB server on a storage virtual machine (SVM).
- Creating local users and groups.
- Adding local users or groups as members of the workgroup.

Keep in mind that SMB servers in workgroup mode do not support the following SMB features:

- SMB3 Witness protocol
- SMB3 CA shares
- SQL over SMB
- Folder Redirection
- Roaming Profiles
- Group Policy Object (GPO)
- Volume Snapshot Service (VSS)

Also, an SMB server in workgroup mode supports only NTLM authentication and does not support Kerberos authentication.

The following procedures take you through the process of setting up an SMB server on an SVM in a workgroup, create local accounts, and adding these accounts to the workgroup membership. You will use the NetApp ONTAP CLI from either the file system or SVM management interface to implement these procedures. For more information, see Using the NetApp ONTAP CLI.

Topics

- Creating an SMB server in a workgroup
- Creating a local user account on the SMB server
- Creating local groups on the SMB server
- Adding local users to the local group

Creating an SMB server in a workgroup

You can use the **vserver cifs create** ONTAP CLI command to create an SMB server on the SVM and specify the workgroup to which it belongs.

Before you begin

The SVM and volumes (and interfaces) that you are using to serve data must have been configured to allow the SMB protocol.

The LIFs must be able to connect to the DNS servers that are configured on the SVM. A CIFS license may be required on the file system, however a CIFS license is not required if the SMB server will be used for authentication only.

To create an SMB server in a workgroup

1. To access the ONTAP CLI, establish an SSH session on the management port of the Amazon FSx for NetApp ONTAP file system or SVM by running the following command. Replace *management_endpoint_ip* with the IP address of the file system's management port.

   ```
   [~]$ ssh fsxadmin@management_endpoint_ip
   ```

   For more information, see Managing file systems with the ONTAP CLI.

2. Create the SMB server in a workgroup:

   ```
   FSxIdabcde123456::> vserver cifs create -vserver vserver_name -cifs-
   server cifs_server_name -workgroup workgroup_name [-comment workgroup_description]
   ```

   The following command creates the SMB server `smb_server01` in the workgroup `workgroup01`:

   ```
   FSxIdabcde123456::> vserver cifs create -vserver svm1 -cifs-server SMB_SERVER01 -
   workgroup workgroup01
   ```

   If you are connected to management port of the SVM, you do not need to specify a `-vserver`.

3. Verify the SMB server configuration by using the `vserver cifs show` command.

   In the following example, the command output shows that a SMB server named `smb_server01` was created on SVM `svm1` in the workgroup `workgroup01`:

   ```
   FSxIdabcde123456::> vserver cifs show -vserver svm1

                                             Vserver: svm1
                           CIFS Server NetBIOS Name: SMB_SERVER01
                       NetBIOS Domain/Workgroup Name: workgroup01
                        Fully Qualified Domain Name: -
                                Organizational Unit: -
       Default Site Used by LIFs Without Site Membership: -
                                      Workgroup Name: workgroup01
                                 Authentication Style: workgroup
                    CIFS Server Administrative Status: up
                              CIFS Server Description:
                              List of NetBIOS Aliases: -
   ```

Creating a local user account on the SMB server

You can create a local user account that can be used to authorize access to data contained in the SVM over an SMB connection. You can also use local user accounts for authentication when creating an SMB session. Local user functionality is enabled by default when the SVM is created. When you create a local user account, you must specify a user name and you must specify the SVM with which to associate the account.

To create local user accounts on the SMB server

1. Create the local user using the **vserver cifs users-and-groups local-user create** ONTAP CLI command:

   ```
   vserver cifs users-and-groups local-user create -vserver svm_name -user-
   name user_name optional_parameters
   ```

   The following optional parameters might be useful:

   - `-full-name` – The user's full name.
   - `-description` – A description for the local user.
   - `-is-account-disabled {true|false}` – Specifies whether the user account is enabled or disabled. If this parameter is not specified, the default is to enable the user account.

   The command prompts for the local user's password.
2. Enter a password for the local user, and then confirm the password.
3. Verify that the user was successfully created:

   ```
   vserver cifs users-and-groups local-user show -vserver svm_name
   ```

The following example creates a local user `SMB_SERVER01\sue`, with a full name `Sue Chang`, associated with SVM `svm1`:

```
FSxIdabcde123456::> vserver cifs users-and-groups local-user create -vserver svm1
 -user-name SMB_SERVER01\sue -full-name "Sue Chang"

Enter the password:
Confirm the password:
```

```
FSxIdabcde123456::> vserver cifs users-and-groups local-user show
Vserver  User Name                  Full Name  Description
-------- -------------------------- ---------- -------------
svm1     SMB_SERVER01\Administrator            Built-in administrator account
svm1     SMB_SERVER01\sue           Sue Chang
```

Creating local groups on the SMB server

You can create local groups that can be used for authorizing access to data associated with the SVM over an SMB connection. You can also assign privileges that define what user rights or capabilities a member of the group has.

Local group functionality is enabled by default when the SVM is created. When you create a local group, you must specify a name for the group and you must specify the SVM with which to associate the group. You can specify a group name with or without the local domain name, and you can optionally specify a description for the local group. You cannot add a local group to another local group.

To create a local group on the SMB server

1. create the local group using the **vserver cifs users-and-groups local-group create** ONTAP CLI command.

   ```
   vserver cifs users-and-groups local-group create -vserver svm_name -group-
   name group_name [-description local_group_description
   ```

   Including a description for the local group is useful.
2. Verify that the group was successfully created:

   ```
   vserver cifs users-and-groups local-group show -vserver svm_name
   ```

The following example creates a local group `SMB_SERVER01\engineering` associated with SVM `svm1`:

```
FSxIdabcde123456::> vserver cifs users-and-groups local-group create -vserver svm1 -
group-name SMB_SERVER01\engineering
```

```
FSxIdabcde123456::> vserver cifs users-and-groups local-group show -vserver svm1
```

```
Vserver          Group Name                    Description
---------------- ----------------------------- ----------------------------
svm1             BUILTIN\Administrators        Built-in Administrators group
svm1             BUILTIN\Backup Operators      Backup Operators group
svm1             BUILTIN\Guests                Built-in Guests group
svm1             BUILTIN\Power Users           Restricted administrative privileges
svm1             BUILTIN\Users                 All users
svm1             SMB_SERVER01\engineering
```

Adding local users to the local group

You can manage local group membership by adding and removing local or domain users, or adding and removing domain groups. This is useful if you want to control access to data based on access controls placed on the group, or if you want users to have privileges associated with that group. If you no longer want a local user, domain user, or domain group to have access rights or privileges based on membership in a group, you can remove the member from the group.

When adding members to a local group, keep the following in mind:

- You cannot add users to the special *Everyone* group.
- You cannot add a local group to another local group.
- To add a domain user or group to a local group, ONTAP must be able to resolve the name to a SID.

When removing members from a local group, keep the following in mind:

- You cannot remove members from the special *Everyone* group.
- To remove a member from a local group, ONTAP must be able to resolve their name to a SID.

You need to have the `fsxadmin` role to run the commands used in this procedure. For more information, see ONTAP roles and users.

To manage the local group membership

- Add a member to or remove a member from a group using the **vserver cifs users-and-groups local-group add-members** and vserver cifs users-and-groups local-group remove-members ONTAP CLI commands.

- To add members to a workgroup:

  ```
  vserver cifs users-and-groups local-group add-members -vserver svm_name -group-
  name group_name -member-names name[,...]
  ```

  You can specify a comma-delimited list of local users, domain users, or domain groups to add to the specified local group.

- To view members of a workgroup:

  ```
  vserver cifs users-and-groups local-group show-members -vserver svm_name -group-
  name group_name
  ```

- To remove members from a workgroup:

  ```
  vserver cifs users-and-groups local-group remove-members -vserver svm_name -
  group-name group_name -member-names name[,...]
  ```

  You can specify a comma-delimited list of local users, domain users, or domain groups to remove from the specified local group.

The following example adds a local user SMB_SERVER01\sue to the local group SMB_SERVER01\engineering on SVM svm1:

```
FSxIdabcde123456::> vserver cifs users-and-groups local-group add-members -vserver svm1
 -group-name SMB_SERVER01\engineering -member-names SMB_SERVER01\sue
```

The following example removes the local user SMB_SERVER01\sue and SMB_SERVER01\james from the local group SMB_SERVER01\engineering on SVM svm1:

```
FSxIdabcde123456::> vserver cifs users-and-groups local-group remove-
members -vserver svm1 -group-name SMB_SERVER01\engineering -member-names
 SMB_SERVER01\sue,SMB_SERVER01\james
```

The following example lists the members of the local group SMB_SERVER01\engineering:

```
FsxIdabcdef01234::> vserver cifs users-and-groups local-group show-members -
vserver svm_name -group-name group_name
```

```
          Vserver: svm1
      Domain Name: SMB_SERVER01
       Group Name: SMB_SERVER01\engineering
      Member Name: SMB_SERVER01\anita
                   SMB_SERVER01\james
                   SMB_SERVER01\liang
```

Monitoring storage virtual machine (SVM) configuration details

You can see the FSx for ONTAP storage virtual machines that are currently on your file system using the Amazon FSx console, the AWS CLI, and the Amazon FSx API.

To view a storage virtual machine on your file system:

- **Using the console** – Choose a file system to view its **File systems** detail page. To list all the storage virtual machines on the file system, choose the **Storage virtual machines** tab, and then choose the storage virtual machine that you want to view.
- **Using the CLI or API** – Use the describe-storage-virtual-machines CLI command or the DescribeStorageVirtualMachines API operation.

  The system response is a list of full descriptions of all the SVMs in your account in that AWS Region.

Deleting storage virtual machines (SVM)

You can only delete an FSx for ONTAP SVM by using the Amazon FSx console, the AWS CLI, and API. Before you can delete an SVM, you must delete all non-root volumes attached to the SVM first.

> **Important**
>
> You cannot delete an SVM by using the NetApp ONTAP CLI or API.

> **Note**
>
> Before you delete a storage virtual machine, make sure that no applications are accessing the data in the SVM, and that you have deleted all non-root volumes attached to the SVM.

To delete a storage virtual machine (console)

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. Choose the SVM that you want to delete as follows:

   - In the left navigation pane, choose **File systems**, and then choose the ONTAP file system for which you want to delete an SVM.
   - Choose the **Storage virtual machines** tab.

     –Or–

   - To display a list of all the SVMs available, expand **ONTAP** and choose **Storage virtual machines**.

   Select the SVM that you want to delete from the list.
3. In the **Volumes** tab, view the list of volumes attached to the SVM. If there are any non-root volumes attached to the SVM, you must delete them before you can delete the SVM. See Deleting volumes for more information.
4. Choose **Delete storage virtual machine** from the **Actions** menu.
5. In the delete confirmation dialog box, choose **Delete storage virtual machine**.

To delete a storage virtual machine (CLI)

- To delete an FSx for ONTAP storage virtual machine, use the delete-storage-virtual-machine CLI command (or the equivalent DeleteStorageVirtualMachine API operation), as shown in the following example.

```
aws fsx delete-storage-virtual-machine --storage-virtual-machine-id svm-
abcdef0123456789d
```

Managing FSx for ONTAP volumes

Each storage virtual machine (SVM) on an FSx for ONTAP file system can have one or more *volumes*. A volume is an isolated data container for files, directories, or iSCSI logical units of storage (LUNs). Volumes are *thin provisioned*, meaning that they consume storage capacity only for the data stored in them.

You can access a volume from Linux, Windows, or macOS clients over the Network File System (NFS) protocol, the Server Message Block (SMB) protocol, or over the Internet Small Computer Systems Interface (iSCSI) protocol by creating an iSCSI LUN (shared block storage). FSx for ONTAP also supports multi-protocol access (concurrent NFS and SMB access) to the same volume.

You can create volumes by using the AWS Management Console, AWS CLI, the Amazon FSx API, or NetApp Console. You can also use your file system's or SVM's administrative endpoint to create, update, and delete volumes by using the NetApp ONTAP CLI or REST API.

Note

You can create 500 volumes per HA pair, up to 1,000 volumes across all HA pairs. FlexGroup constituent volumes count toward this limit. By default, there are eight constituent volumes per aggregate, per FlexGroup.

When you create a volume, you define the following properties:

- Volume style – The volume style can be either FlexVol or FlexGroup.
- Volume name – The name of the volume.
- Volume type – The volume type can be either Read-Write (RW) or Data protection (DP). DP volumes are read-only and used as the destination in a NetApp SnapMirror or SnapVault relationship.
- Volume size – This is the maximum amount of data that the volume can store, regardless of the storage tier.
- Junction path – This is the location in the SVM's namespace where the volume gets mounted.
- Storage efficiency – Storage efficiency features, including data compaction, compression, and deduplication provide typical storage savings of 65% for general-purpose file sharing workloads.
- Volume security style (Unix or NTFS) – Determines what type of permissions are used for data access on the volume when authorizing users.
- Data tiering – The tiering policy defines which data is stored in the cost-effective capacity pool tier.
- Tiering policy cooling period – Defines when data is marked cold and moved to capacity pool storage.

- Snapshot policy – Snapshot policies define how the system creates snapshots for a volume. You can choose from three predefined policies or use a custom policy. that you have created using the ONTAP CLI or REST API.
- Copy tags to backups – Amazon FSx will automatically copy any tags from your volumes to backups using this option. You can set this option using the AWS CLI or Amazon FSx API.

Topics

- Volume styles
- Volume types
- Volume security style
- Creating volumes
- Updating volumes
- Moving volumes between aggregates
- Monitoring volumes
- Deleting volumes

Volume styles

FSx for ONTAP offers two styles of volumes that you can use for different purposes. You can create either FlexVol or FlexGroup volumes using the Amazon FSx console, the AWS CLI, and the Amazon FSx API.

- FlexVol volumes offer the simplest experience for file systems with one high-availability (HA) pair, so they are the default volume style for first-generation file systems and second-generation file systems with one HA pair. The minimum size of a FlexVol volume is 20 mebibytes (MiB), and the maximum size is 314,572,800 MiB.
- FlexGroup volumes are comprised of multiple constituent FlexVol volumes, which allows them to deliver higher performance and storage scalability than FlexVol volumes for file systems with multiple HA pairs. FlexGroup volumes are the default volume style for second-generation file systems with more than one HA pair. The minimum size of a FlexGroup volume is 100 gibibytes (GiB) per constituent, and the maximum size is 20 pebibytes (PiB).

You can convert a volume with the FlexVol style to the FlexGroup style with the ONTAP CLI, which creates a FlexGroup with a single constituent. However, we recommend that you use AWS DataSync

to move data between a FlexVol volume and a new FlexGroup volume to ensure that the data is evenly distributed across the FlexGroup's constituents. For more information, see FlexGroup constituents.

> **Note**
>
> If you want to use the ONTAP CLI to convert a FlexVol volume to a FlexGroup volume, make sure that you delete any backups of the FlexVol volume before converting it. ONTAP doesn't automatically rebalance data as part of the conversion, so the data might be imbalanced across the FlexGroup constituents.

FlexGroup constituents

A FlexGroup volume is made up of constituents, which are FlexVol volumes. By default, FSx for ONTAP assigns eight constituents to a FlexGroup volume per HA pair.

When you create your FlexGroup volume, the size of it is divided evenly among its constituents. For example, if you create an 800 gigabyte (GB) FlexGroup volume with eight constituents, each constituent is 100 GB in size. A FlexGroup volume can be between 100 GB and 20 PiB in size, but the total size depends on the size of the constituents. Each constituent has a minimum size of 100 GB and a maximum size of 300 TiB. For example, a FlexGroup volume with eight constituents has a minimum size of 800 GB and a maximum size of 20 PiB.

ONTAP distributes data at the file-level across the constituents. You can store up to two billion files in each constituent on your FlexGroup volume.

When you update the size of your FlexGroup volume, the new size is evenly distributed among its existing constituents.

You can also add more constituents to your FlexGroup volume using the ONTAP CLI or REST API. However, we recommend that you only do so if you need additional storage capacity and all of your constituents are already at their maximum size (300 TiB per constituent). Adding constituents can lead to an imbalance of data and I/O across the constituents. Until the constituents are balanced, it's possible that the write throughput might be 5–10% lower than a balanced FlexGroup volume. When new data is written to the FlexGroup volume, ONTAP prioritizes distributing it among the new constituents until the constituents are balanced. If you do add new constituents, we recommend choosing an even number and not exceeding eight per aggregate.

> **Note**
>
> If you add new constituents, your existing snapshots become partial snapshots; therefore, they can't be used to fully restore your FlexGroup volume to a prior state. The previous snapshots can't offer a complete point-in-time image of your FlexGroup volume because the new constituents didn't exist yet. However, the partial snapshots can be used to restore individual files and directories, to create a new volume, or to replicate with SnapMirror.

Volume types

FSx for ONTAP offers two types of volumes that you can create using the Amazon FSx console, the AWS CLI, and the Amazon FSx API.

- Read-write (RW) volumes are used in most cases. As their name indicates, they are read-writable.
- Data protection (DP) volumes are read-only volumes that you use as the destination of a NetApp SnapMirror or SnapVault relationship. You should use DP volumes when you want to migrate or protect a single volume's data.

FlexVol and FlexGroup volumes can be either RW or DP.

> **Note**
>
> You can't update a volume's type after the volume is created.

Volume security style

When creating an FSx for ONTAP volume, you can choose from two security styles: Unix and NTFS. Each security style has a different effect on how permissions are handled for data. You must understand the different effects to ensure that you select the appropriate security style for your purposes.

It is important to understand that security styles do not determine what client types can or cannot access data. Security styles only determine the type of permissions FSx for ONTAP uses to control data access and what client type can modify these permissions.

The two factors that you use to determine the security style for a volume are the type of administrators that manage the file system and the type of users or services that access the data on the volume.

When creating a volume in the Amazon FSx console, CLI, and API, the security style is automatically set to the root volume's security style. You can modify a volume's security style using the AWS CLI or API. You can modify this setting after the volume is created. See Updating volumes for more information.

When you configure the security style on a volume, consider the needs of your environment to ensure that you select the best security style in order to avoid issues with managing permissions. Keep in mind that security style doesn't determine which client types can access data. Security style determines the permissions that are used to allow data access and the client types that can modify those permissions. Following are considerations that can help you decide which security style to choose for a volume:

- **Unix (Linux)** – Choose this security style if the file system is managed by a Unix administrator, the majority of users are NFS clients, and an application accessing the data uses a Unix user as the service account. Only Linux clients can modify permissions with the Unix security style, and the type of permissions used on files and directories are mode-bits or NFS v4.x ACLs.
- **NTFS** – Choose this security style if the file system is managed by a Windows administrator, the majority of users are SMB clients, and an application accessing the data uses a Windows user as the service account. If any Windows access is required to a volume, we recommend that you use the NTFS security style. Only Windows clients can modify permissions with NTFS security style, and the types of permissions used on file and directories is NTFS ACLs.

Creating volumes

You can create an FSx for ONTAP FlexVol or FlexGroup volume using the Amazon FSx console, the AWS CLI, and the Amazon FSx API, in addition to the NetApp ONTAP command line interface (CLI) and REST API.

To create a FlexVol volume (console)

> **Note**
>
> The volume's security style is automatically set to the root volume's security style.

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. In the left navigation pane, choose **Volumes**.
3. Choose **Create volume**.
4. For **File system type**, choose **Amazon FSx for NetApp ONTAP**.
5. In the **File system details** section, provide the following information:
   - For **File system**, choose the file system to create the volume on.
   - For **Storage virtual machine**, choose the storage virtual machine (SVM) to create the volume on.
6. In the **Volume style** section, choose **FlexVol**.
7. In the **Volume details** section, provide the following information:
   - In the **Volume name** field, provide a name for the volume. You can use up to 203 alphanumeric or underscore (_) characters.
   - For **Volume size**, enter any whole number in the range of 20–314572800 to specify the size in mebibytes (MiB).
   - For **Volume type**, choose **Read-Write (RW)** to create a volume that is readable and writable or **Data Protection (DP)** to create a volume that is read-only and can be used as the destination of a NetApp SnapMirror or SnapVault relationship. For more information, see Volume types.
   - For **Junction path**, enter a location within the file system to mount the volume. The name must have a leading forward slash, for example `/vol3`.
   - For **Storage efficiency**, choose **Enabled** to enable the ONTAP storage-efficiency features (deduplication, compression, and compaction) on this volume. For more information, see Storage efficiency.
   - For **Volume security style**, choose between **Unix (Linux)** and **NTFS** for the volume. For more information, see Volume security style.
   - For **Snapshot policy**, choose a snapshot policy for the volume. For more information about snapshot policies, see Snapshot policies.

     If you choose **Custom policy**, you must specify the policy's name in the **custom-policy** field. The custom policy must already exist on the SVM or in the file system. You can create a custom snapshot policy with the ONTAP CLI or REST API. For more information, see Create a Snapshot Policy in the NetApp ONTAP Product Documentation.
8. In the **Storage tiering** section, provide the following information:

- For **Capacity pool tiering policy**, choose the storage pool tiering policy for the volume, which can be **Auto** (the default), **Snapshot Only**, **All**, or **None**. For more information, see Volume tiering policies.
- If you choose either **Auto** or **Snapshot Only**, you can set the **Tiering policy cooling period** to define the number of days before data that has not been accessed is marked cold and moved to capacity pool storage. You can provide a value between 2 and 183 days. The default setting is 31 days.

9. In the **Advanced** section, for **SnapLock Configuration**, choose between **Enabled** and **Disabled**. For more information about configuring a SnapLock Compliance volume or a SnapLock Enterprise volume, see Understanding SnapLock Compliance and Understanding SnapLock Enterprise. For more information about SnapLock, see Protecting your data with SnapLock.
10. Choose **Confirm** to create the volume.

You can monitor the update progress on the **File systems** detail page, in the **Status** column of the **Volumes** pane. The volume is ready for use when its status is **Created**.

To create a FlexGroup volume (console)

> **Note**
>
> You can only create FlexGroup volumes for file systems with multiple HA pairs using the Amazon FSx console. To create FlexVol volumes for file systems with multiple HA pairs, use the AWS CLI, Amazon FSx API, or NetApp management tools.

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. In the left navigation pane, choose **Volumes**.
3. Choose **Create volume**.
4. For **File system type**, choose **Amazon FSx for NetApp ONTAP**.
5. In the **File system details** section, provide the following information:
   - For **File system**, choose the file system to create the volume on.
   - For **Storage virtual machine**, choose the storage virtual machine (SVM) to create the volume on.
6. In the **Volume style** section, choose **FlexGroup**.

7. In the **Volume details** section, provide the following information:

   - In the **Volume name** field, provide a name for the volume. You can use up to 203 alphanumeric or underscore (_) characters.
   - For **Volume size**, enter any whole number in the range of 800 gibibytes (GiB)–2,400 tebibytes (TiB) per HA pair. For example, a file system with 12 high-availability (HA) pairs would have a minimum volume size of 9,600 GiB and a maximum size of 20,480 TiB.
   - For **Volume type**, choose **Read-Write (RW)** to create a volume that is readable and writable or **Data Protection (DP)** to create a volume that is read-only and can be used as the destination of a NetApp SnapMirror or SnapVault relationship. For more information, see Volume types.
   - For **Junction path**, enter a location within the file system to mount the volume. The name must have a leading forward slash, for example `/vol3`.
   - For **Storage efficiency**, choose **Enabled** to enable the ONTAP storage-efficiency features (deduplication, compression, and compaction). For more information, see Storage efficiency.
   - For **Volume security style**, choose between **Unix (Linux)** and **NTFS** for the volume. For more information, see Volume security style.

     > **Note**
     >
     > The volume's security style is automatically set to the root volume's security style.

   - For **Snapshot policy**, choose a snapshot policy for the volume. For more information about snapshot policies, see Snapshot policies.

     If you choose **Custom policy**, you must specify the policy's name in the **custom-policy** field. The custom policy must already exist on the SVM or in the file system. You can create a custom snapshot policy with the ONTAP CLI or REST API. For more information, see Create a Snapshot Policy in the NetApp ONTAP Product Documentation.

8. In the **Storage tiering** section, provide the following information:

   - For **Capacity pool tiering policy**, choose the storage pool tiering policy for the volume, which can be **Auto** (the default), **Snapshot Only**, **All**, or **None**. For more information, see Volume tiering policies.
   - If you choose either **Auto** or **Snapshot Only**, you can set the **Tiering policy cooling period** to define the number of days before data that has not been accessed is marked cold and

moved to capacity pool storage. You can provide a value between 2–183 days. The default setting is 31 days.

9. In the **Advanced** section, for **SnapLock Configuration**, choose between **Enabled** and **Disabled**. For more information about configuring a SnapLock Compliance volume or a SnapLock Enterprise volume, see Understanding SnapLock Compliance and Understanding SnapLock Enterprise. For more information about SnapLock, see Protecting your data with SnapLock.
10. Choose **Confirm** to create the volume.

You can monitor the update progress on the **File systems** detail page, in the **Status** column of the **Volumes** pane. The volume is ready for use when its status is **Created**.

To create a volume (CLI)

- To create an FSx for ONTAP volume, use the create-volume CLI command (or the equivalent CreateVolume API operation), as shown in the following example.

```
aws fsx create-volume \
    --volume-type ONTAP \
    --name vol1 \
    --ontap-configuration CopyTagsToBackups=true,JunctionPath=/
vol1,SecurityStyle=NTFS, \
          SizeInMegabytes=1024,SnapshotPolicy=default, \
          StorageVirtualMachineId=svm-abcdef0123456789a,OntapVolumeType=RW, \
          StorageEfficiencyEnabled=true
```

After successfully creating the volume, Amazon FSx returns its description in JSON format, as shown in the following example.

```
{
    "Volume": {
        "CreationTime": "2022-08-12T13:03:37.625000-04:00",
        "FileSystemId": "fs-abcdef0123456789c",
        "Lifecycle": "CREATING",
        "Name": "vol1",
        "OntapConfiguration": {
            "CopyTagsToBackups": true,
            "FlexCacheEndpointType": "NONE",
            "JunctionPath": "/vol1",
            "SecurityStyle": "NTFS",
```

```
            "SizeInMegabytes": 1024,
            "SnapshotPolicy": "default",
            "StorageEfficiencyEnabled": true,
            "StorageVirtualMachineId": "svm-abcdef0123456789a",
            "StorageVirtualMachineRoot": false,
            "TieringPolicy": {
                "Name": "NONE"
            },
            "OntapVolumeType": "RW"
        },
        "ResourceARN": "arn:aws:fsx:us-east-2:111122223333:volume/fs-abcdef0123456789c/
fsvol-abcdef0123456789b",
        "VolumeId": "fsvol-abcdef0123456789b",
        "VolumeType": "ONTAP"


    }
}
```

You can also create a new volume by restoring a backup of a volume to a new volume. For more information, see Restoring backups to a new volume.

Updating volumes

You can update the configuration of an FSx for ONTAP volume using the Amazon FSx console, the AWS CLI, and the Amazon FSx API, in addition to the NetApp ONTAP command line interface (CLI) and REST API. You can modify the following properties of an existing FSx for ONTAP volume:

- Volume name
- Junction path
- Volume size
- Storage efficiency
- Capacity pool tiering policy
- Volume security style
- Snapshot policy
- Tiering policy cooling period
- Copy tags to backups (using the AWS CLI and Amazon FSx API)

For more information, see Managing FSx for ONTAP volumes.

To update a volume configuration (console)

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. Navigate to **File systems** and choose the ONTAP file system that you want to update a volume for.
3. Choose the **Volumes** tab.
4. Choose the volume that you want to update.
5. For **Actions**, choose **Update volume**.

   The **Update volume** dialog box displays with the volume's current settings.
6. For **Junction path**, enter an existing location within the file system to mount the volume. The name must have a leading forward slash, such as `/vol15`.
7. For **Volume size**, you can increase or decrease the size of the volume within the range specified in the Amazon FSx console. For FlexVol volumes, the maximum size is 300 TiB. For FlexGroup volumes, the maximum size is 300 TiB multiplied by the total number of constituent volumes that your FlexGroup has, up to a maximum of 20 PiB.
8. For **Storage efficiency**, choose **Enabled** to enable the ONTAP storage efficiency features (deduplication, compression, and compaction) on the volume, or choose **Disabled** to disable them.
9. For **Capacity pool tiering policy**, choose a new storage pool tiering policy for the volume, which can be **Auto** (the default), **Snapshot-only**, **All**, or **None**. For more information about capacity pool tiering policies, see Volume tiering policies.
10. For **Volume security style**, choose either **Unix (Linux)**, **NTFS**, or **Mixed**. A volume's security style determines whether preference is given to NTFS or UNIX ACLs for multi-protocol access. The MIXED mode is not required for multi-protocol access and is only recommended for advanced users.
11. For **Snapshot policy**, choose a snapshot policy for the volume. For more information about snapshot policies, see Snapshot policies.

    If you choose **Custom policy**, you must specify the policy's name in the **custom-policy** field. The custom policy must already exist on the SVM or in the file system. You can create a custom snapshot policy with the ONTAP CLI or REST API. For more information, see Create a Snapshot Policy in the NetApp ONTAP Product Documentation.

12. For **Tiering policy cooling period**, valid values are 2-183 days. A volume's tiering policy cooling period defines the number of days before data that has not been accessed is marked cold and moved to capacity pool storage. This setting only affects the `Auto` and `Snapshot-only` policies.
13. Choose **Update** to update the volume.

To update a volume's configuration (CLI)

- To update the configuration of an FSx for ONTAP volume, use the update-volume CLI command (or the equivalent UpdateVolume API operation), as shown in the following example.

```
aws fsx update-volume \
    --volume-id fsvol-1234567890abcdefa \
    --name new_vol \
    --ontap-configuration CopyTagsToBackups=true,JunctionPath=/new_vol, \
           SizeInMegabytes=2048,SnapshotPolicy=default-1weekly, \
           StorageEfficiencyEnabled=true, \
           TieringPolicy=all
```

Expanding FlexGroup volumes

You can add additional constituent volumes to your FlexGroup volume with the `volume expand` command in the ONTAP CLI. This is a best practice after adding high-availability (HA) pairs to your file system because it ensures that your FlexGroup volume stays balanced.

Before expanding your FlexGroup volume, consider the following points:

- All of a FlexGroup's constituent volumes have the same storage capacity. When you expand your FlexGroup volume with additional constituents, each constituent is the same size as the existing constituents. Therefore, ensure that each aggregate has sufficient space available before adding constituents.
- AWS recommends maintaining eight constituent volumes per aggregate for each FlexGroup volume. Eight constituent volumes per aggregate maximizes the parallelism of FlexGroup volumes and offers the most optimal performance for your workload. Generally, we only recommend expanding your FlexGroup volume with additional constituents if you add HA

pairs. This is the only scenario in which you would need to add constituents to maintain eight constituents per aggregate.

- If your FlexGroup volume is in a SnapMirror relationship, then both the source and destination FlexGroup volumes need to have the same number of constituents. Otherwise, SnapMirror transfers will fail. SnapMirror operates at the constituent level and transfers data between each individual constituent. Therefore, if you expand a FlexGroup volume with additional constituent volumes, you must also manually expand any volume that is in a SnapMirror relationship with it.
- When you expand a FlexGroup volume with additional constituents, all of its existing snapshot copies become "partial" copies. Partial copies can't be restored, but they can be browsed and the individual files can be restored. Additionally, this results in the loss of any incrementality for Amazon FSx backups, AWS backups, or SnapMirror relationships.
- You can't remove constituent volumes once you add them.

Adding FlexGroup volume constituents

You can use the ONTAP CLI to add constituent volumes to your FlexGroup volume.

To add FlexGroup volume constituents

1. To access the NetApp ONTAP CLI, establish an SSH session on the management port of the Amazon FSx for NetApp ONTAP file system by running the following command. Replace *`management_endpoint_ip`* with the IP address of the file system's management port.

   ```
   [~]$ ssh fsxadmin@management_endpoint_ip
   ```

   For more information, see Managing file systems with the ONTAP CLI.
2. Use the volume expand ONTAP CLI command to expand your FlexGroup volume with additional constituents. Replace the following values:

   - `svm_name` with the name of the storage virtual machine (SVM) that hosts your FlexGroup volume (for example, `svm1`).
   - `vol_name` with the name of the FlexGroup volume that you want to expand (for example, `vol1`).
   - `aggregates` with a comma-separated list of aggregates that you want to add FlexGroup constituent volumes into. For example, `aggr1` for a single aggregate or `aggr1,aggr2` for multiple aggregates.

- `constituent_per_aggregate` with the number of additional constituents that you want to add to each of the specified `aggregates`. You should only add enough constituents to ensure that your FlexGroup volume has a balanced number of constituents across the aggregates it resides on.

```
::> volume expand -vserver svm_name -volume vol_name -aggr-list aggregates -aggr-
list-multiplier constituents_per_aggregate
```

Important

You can't remove FlexGroup constituents after you add them, so check your inputs before running the previous command.

Moving volumes between aggregates

When you add high-availability (HA) pairs to your file system, you need to rebalance the existing data by moving volumes to the new aggregates. To move a volume between aggregates, you can use the `volume move` command in the ONTAP CLI.

Before using the `volume move` command, consider the following points:

- Using the `volume move` command can impact performance because it consumes network and disk resources on your file system. Therefore, we recommend moving volumes between aggregates during periods of low activity. Alternatively, you can reduce the network throughput utilization and disk throughput utilization on your file system to no more than 50% while moving volumes.
- To reduce the performance impact on your file system, we recommend moving a single volume between two HA pairs and aggregates at a time. For example, if your file system has four HA pairs, we recommend moving two volumes at a time (assuming the volume moves are not from or toward the same HA pairs). ONTAP supports moving up to eight volumes on each HA pair at a time, but more simultaneous volume moves will reduce the performance of both client I/O and any in-progress volume moves.
- Any data stored on the SSD tier on the impacted volume is physically moved to a different set of disks on a different file server. This operation occurs in the background and takes time. The rate of time that the transfer takes depends on your file system's throughput capacity and the

amount of activity on your file system. However, the volume move can be throttled. For more information, see Throttling volume moves.

- Data stored in capacity pool is not physically moved because the HA pairs share the same capacity pool storage. Instead, ONTAP moves metadata that fully describes each block in capacity pool (a logical move). Keep in mind that file metadata is always stored on the SSD tier. For more information, see Volume data tiering.

Phases of moving a volume

There are two phases in a volume move operation: the replication phase and the cutover phase. During the replication phase, existing data is replicated to the volume's new aggregate. During the cutover phase, ONTAP attempts a final rapid transfer to the volume's new aggregate. This includes transferring any data that has been written during the transfer phase and redirecting new traffic to the volume's new aggregate. By default, the cutover window is 30 seconds and halts all I/O to your volume. If ONTAP can't perform all of these steps during the cutover window, it will fail. By default, ONTAP will try to cut over three times consecutively. If all three consecutive attempts fail, then ONTAP will retry once an hour until it succeeds. You can reduce the load on your file system to ensure that the cutover phase is successful by reducing or pausing I/O traffic to the volume before the cutover phase begins.

Starting volume moves

To start a volume move

1. To access the NetApp ONTAP CLI, establish an SSH session on the management port of the Amazon FSx for NetApp ONTAP file system by running the following command. Replace *management_endpoint_ip* with the IP address of the file system's management port.

   ```
   [~]$ ssh fsxadmin@management_endpoint_ip
   ```

   For more information, see Managing file systems with the ONTAP CLI.

2. Run the volume move start ONTAP CLI command. Replace the following values:

   - `vserver_name` with the name of the SVM hosting the volume that you're moving.
   - `volume_name` with the name of the volume's constituent (for example, `vol1__0001`).
   - `aggregate_name` with the name of the destination aggregate for the volume.

- `-enforce-network-throttling` to throttle the volume move's total throughput. This is optional.

```
::> volume move start -vserver svm_name -volume volume_name --destination-
aggregate aggregate_name -foreground false
[Job 1] Job is queued: Move "vol1__0001" in Vserver "svm01" to aggregate "aggr1".
 Use the "volume move show -vserver svm01 -volume vol1__0001" command to view the
 status of this operation.
```

Important

Moving volumes consumes network and disk resources for the source and destination file servers. Therefore, your workload's performance can be impacted by any volume moves that are in progress. Additionally, your I/O traffic to the volume will be temporarily paused during the cutover phase of the volume move.

Monitoring volume moves

To monitor a volume move

- To check the status of the volume move operation, use the `volume move show` ONTAP CLI command.

```
::> volume move show -vserver svm_name -volume volume_name

Vserver Name: svm01
Volume Name: vol1__0001
Actual Completion Time: -
Bytes Remaining: 1.00TB
Specified Action For Cutover: retry_on_failure
Specified Cutover Time Window: 30
Destination Aggregate: aggr2
Destination Node: FsxId01234567890abcdef-03
Detailed Status: Transferring data: 12.23GB sent.
Percentage Complete: 1%
Move Phase: replicating
Prior Issues Encountered: -
Estimated Remaining Duration: 00:40:25
```

```
Replication Throughput: 434.3MB/s
Duration of Move: 00:00:27
Source Aggregate: aggr1
Source Node: FsxId01234567890abcdef-01
Move State: healthy
```

The command output shows the estimated time to complete the move. When it's finished, the `Move phase` will show the `completed` status.

Maintaining balanced FlexGroup volumes

In order for your workload to perform optimally, your FlexGroup volumes should span all aggregates and have an even number of constituent volumes per aggregate. We recommend having eight constituents per aggregate. Consider the following scenarios when rebalancing FlexGroup volumes:

- **Moving FlexGroup constituents among existing aggregates:** If you move a FlexGroup's constituent volume to another aggregate of an otherwise balanced FlexGroup, you should then move another constituent that's less utilized to the original aggregate. This ensures that your FlexGroup has an even number of constituents per aggregate.

  Moving FlexGroup constituents into new aggregates after adding HA pairs: If you move a FlexGroup's constituent volumes to new aggregates after adding HA pairs, then you should expand the FlexGroup with additional constituents on the aggregates that lost constituents. This ensures that your FlexGroup has an even number of constituents per aggregate. For more information, see the section called “Expanding FlexGroup volumes”.

Throttling volume moves

If you want to limit the bandwidth of a volume move on your file system, you can add the `-enforce-network-throttling` option at the beginning of the operation.

> **Note**
>
> Using this option affects incoming SnapMirror replication data transfers for the file system. Keep track of how you configure your file system's replication options because you can't view them after setting them.

To throttle a volume move

1. The throttle uses the global replication throttle. To set the global replication throttle, use the following command in the ONTAP CLI.

```
::> options -option-name replication.throttle.enable on
```

2. Specify the maximum total bandwidth that can be used by replication, replacing the following option:

   - `kbs_throttle` with the maximum desired throughput to use for any replication (including SnapMirror and volume moves), in Kilobytes per second.

```
::> options -option-name replication.throttle.incoming.max_kbs kbs_throttle
::> options -option-name replication.throttle.outgoing.max_kbs kbs_throttle
```

Monitoring volumes

You can see the volumes that are currently on your file system using the Amazon FSx console, the AWS CLI, and the Amazon FSx API and SDKs.

To monitor the volumes on your file system:

- **Using the console** – Choose a file system to view the **File systems** detail page. Choose the **Volumes** tab to list all the volumes on the file system, and then choose the volume you want to view.
- **Using the CLI or API** – Use the describe-volumes CLI command or the DescribeVolumes API operation.

```
$ aws fsx describe-volumes
{
    "Volumes": [
        {
            "CreationTime": "2024-03-04T20:17:44+00:00",
            "FileSystemId": "fs-abcdef0123a0bb087",
            "Lifecycle": "CREATED",
            "Name": "SVM8_ext_root",
            "OntapConfiguration": {
                "FlexCacheEndpointType": "NONE",
```

```
                "JunctionPath": "/",
                "SecurityStyle": "NTFS",
                "SizeInMegabytes": 1024,
                "StorageEfficiencyEnabled": false,
                "StorageVirtualMachineId": "svm-01234567890abcdef",
                "StorageVirtualMachineRoot": true,
                "TieringPolicy": {
                    "Name": "NONE"
                },
                "UUID": "42ce3de0-da64-11ee-a22d-7f7cdfb8d381",
                "OntapVolumeType": "RW",
                "SnapshotPolicy": "default",
                "CopyTagsToBackups": false,
                "VolumeStyle": "FLEXVOL",
                "AggregateConfiguration": {
                    "Aggregates": [
                        "aggr1"
                    ]
                },
                "SizeInBytes": 1073741824
            },
            "ResourceARN": "arn:aws:fsx:us-east-2:111122223333:volume/fs-
abcdef0123a0bb087/fsvol-abcdef0123456789a",
            "VolumeId": "fsvol-abcdef0123456789a",
            "VolumeType": "ONTAP"
        }
    ]
}
```

Viewing offline volumes

You can't create or delete volume backups when the source volume is offline. You can use the `volume show` ONTAP CLI command to determine a volume's current status.

```
volume show -vserver svm-name
```

For information about accessing the ONTAP CLI on your file system, see Using the NetApp ONTAP CLI.

```
FsxIdabc12345::> volume show -vserver vs1
Vserver   Volume       Aggregate    State      Type       Size  Available Used%
```

```
--------- ------------ ------------ ---------- ---- ---------- ---------- -----
vs1       vol1         aggr1        online     RW          2GB      1.9GB    5%
vs1       vol1_dr      aggr0_dp     online     DP        200GB    160.0GB   20%
vs1       vol2         aggr0        online     RW        150GB    110.3GB   26%
vs1       vol2_dr      aggr0_dp     online     DP        150GB    110.3GB   26%
vs1       vol3         aggr1        online     RW        150GB    120.0GB   20%
vs1       vol3_dr      aggr1_dp     online     DP        150GB    120.0GB   20%
vs1       vol4         aggr1        online     RW        200GB    159.8GB   20%
7 entries were displayed.
```

To bring an offline volume back online, use the `volume online` ONTAP CLI command, as shown in the following example. If only one SVM (Vserver) exists, you do not need to specify the `-vserver` parameter.

```
FsxID-abcdef123456::> volume online -volume volume_name -vserver svm_name

Volume 'vs1:vol1' is now online.
```

Deleting volumes

You can delete an FSx for ONTAP volume using the Amazon FSx console, the AWS CLI, and the Amazon FSx API, in addition to the NetApp ONTAP command line interface (CLI) and REST API.

Before you delete a volume, make sure that no applications are accessing the data in the volume that you want to delete.

> **Important**
>
> You can only delete volumes using the Amazon FSx console, API, or CLI if the volume has Amazon FSx backups enabled.

Taking a final volume backup

When you delete a volume using the Amazon FSx console, you have the option to take a final backup of the volume. As a best practice, we recommend that you choose to take a final backup. If you find you don't need it after a certain period of time, you can delete this and other manually created volume backups. When you delete a volume by using the `delete-volume` CLI command, Amazon FSx takes a final backup by default.

For more information about volume backups, see Protecting your data with volume backups.

To delete a volume (console)

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. In the left navigation pane, choose **File systems**, and then choose the ONTAP file system that you want to delete a volume from.
3. Choose the **Volumes** tab.
4. Choose the volume that you want to delete.
5. For **Actions**, choose **Delete volume**.
6. (SnapLock Enterprise volumes only) For **Bypass SnapLock Enterprise Retention**, choose **Yes**.
7. In the confirmation dialog box, for **Create final backup**, you have two options:
   - Choose **Yes** to take a final backup of the volume. The name of the final backup is displayed.
   - Choose **No** if you don't want a final backup of the volume. You are asked to acknowledge that once the volume is deleted, automatic backups are no longer available.
8. Confirm the volume deletion by entering **delete** in the **Confirm delete** field.
9. Choose **Delete volume(s)**.

To delete a volume (CLI)

- To delete an FSx for ONTAP volume, use the delete-volume CLI command (or the equivalent DeleteVolume API operation), as shown in the following example.

```
aws fsx delete-volume --volume-id fsvol-1234567890abcde
```

Deleting SnapLock volumes

This section explains how to delete a SnapLock volume.

You can delete a SnapLock Compliance volume if the retention periods of all the write once, read many (WORM) files on it are expired.

> **Note**
>
> When you close an AWS account that contains SnapLock Enterprise or Compliance volumes, AWS and FSx for ONTAP suspend your account for 90 days leaving your data intact. If you don't reopen your account during those 90 days, AWS deletes your data including data in SnapLock volumes regardless of your retention settings.

You can delete a SnapLock Enterprise volume at any time if you have the required permissions. To delete a SnapLock Enterprise volume using the ONTAP CLI, you must have the `fsxadmin` role. For more information, see File system administrator roles and users.

To delete a SnapLock Enterprise volume that contains WORM data with an active retention policy using the Amazon FSx console, CLI, or Amazon FSx API, you must have the `fsx:BypassSnapLockEnterpriseRetention` IAM permission.

> **Warning**
>
> The minimum retention period for a SnapLock audit log volume is six months. Until this retention period expires you can't delete the SnapLock audit log volume, the storage virtual machine (SVM), or the file system that's associated with the SVM—even if the volume was created in SnapLock Enterprise mode. For more information, see SnapLock audit log volumes.

Creating an iSCSI LUN

This process describes how to create an iSCSI LUN on an Amazon FSx for NetApp ONTAP file system using the NetApp ONTAP CLI **lun create** command. For more information, see **lun create** in the NetApp ONTAP Documentation Center.

> **Note**
>
> The iSCSI protocol isn't supported for file systems with more than six HA pairs.

This process assumes you already have a volume created on your file system. For more information, see Creating volumes.

1. To access the ONTAP CLI, establish an SSH session on the management port of the Amazon FSx for NetApp ONTAP file system or SVM by running the following command. Replace *management_endpoint_ip* with the IP address of the file system's management port.

   ```
   [~]$ ssh fsxadmin@management_endpoint_ip
   ```

   For more information, see Managing file systems with the ONTAP CLI.

2. Create a LUN using the **lun create** NetApp CLI command, replacing the following values:

   - ***svm_name*** - The name of the storage virtual machine (SVM) providing the iSCSI target. The host uses this value to reach the LUN.
   - ***vol_name*** - The name of the volume hosting the LUN.
   - ***lun_name*** - The name you want to assign to the LUN.
   - ***size*** - The size, in bytes, of the LUN. The maximum size LUN you can create is 128 TB.

     > **Note**
     >
     > We recommend that you use a volume at least 5% larger than your LUN size. This margin leaves space for volume snapshots.

   - ***ostype*** - The operating system of the host, either `windows_2008` or `linux`. Use `windows_2008` for all versions of Windows; this ensures the LUN has proper block offset for the operating system and optimizes performance.

   > **Note**
   >
   > We recommend enabling space allocation on your LUN. With space allocation enabled, ONTAP can inform your host when the LUN is out of capacity and can reclaim space as you delete data from the LUN.

   For more information, see `lun create` in the NetApp ONTAP CLI documentation.

   ```
   > lun create -vserver svm_name -path /vol/vol_name/lun_name -size size -
   ostype ostype -space-allocation enabled
   ```

```
Created a LUN of size 10g (10737418240)
```

3. Confirm the LUN is created, online, and mapped.

```
> lun show
```

The system responds with the following output:

```
Vserver   Path                            State   Mapped   Type         Size
--------- ------------------------------- ------- -------- ------------ --------
svm_name
          /vol/vol_name/lun_name          online  unmapped windows_2008 10GB
```

Next steps

Now that you have created an iSCSI LUN, the next step in the process of using an iSCSI LUN as block storage is to map the LUN to an `igroup`. For more information, see Provisioning iSCSI for Linux or Provisioning iSCSI for Windows.

Optimizing performance with Amazon FSx maintenance windows

As a fully-managed service, FSx for ONTAP regularly performs maintenance on and updates to your file system. This maintenance has no impact for most workloads. For workloads that are performance-sensitive, on rare occasions you may notice a brief (<60 seconds) impact on performance when maintenance is occurring; Amazon FSx enables you to use the maintenance window to control when any such potential maintenance activity occurs.

Patching occurs infrequently, typically once every several weeks. When patching occurs, each of your file system's file servers is patched one at a time, and each file server typically takes up to an hour to be patched. Before any file server is patched within an HA pair, your file system automatically fails over to the file servers' HA partner, which may result in a brief (less than 60 seconds) I/O pause for any I/O directed toward that HA pair. Your file system will then fail back, which may result in another brief (less than 60 seconds) I/O pause. You choose the maintenance window start time during file system creation. If you don't choose a window, one is automatically assigned.

> **Important**
>
> To ensure that your file system can be patched successfully, FSx for ONTAP will bring online any offline volumes for the duration of the patching process. Any volumes that Amazon FSx brings back online will not be accessible to clients.

FSx for ONTAP allows you to adjust your maintenance window as needed to accommodate your workload and operational requirements. You can move your maintenance window as frequently as required, provided that a maintenance window occurs at least once every 14 days. If a patch is released and a maintenance window does not occur within 14 days, FSx for ONTAP will proceed with maintenance on the file system to ensure its security and reliability.

> **Note**
>
> To ensure data integrity during maintenance activity, FSx for ONTAP closes all opportunistic locks and completes any pending write operations to the underlying storage volumes that are hosting your file system before maintenance begins.

You can use the Amazon FSx Management Console, AWS CLI, AWS API, or one of the AWS SDKs to change the maintenance window for your file systems.

To change the weekly maintenance window (console)

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. Choose **File systems** in the left hand navigation column.
3. Choose the file system that you want to change the weekly maintenance window for. The **Summary** file system details page appears.
4. Choose **Administration** to display the file system administration **Settings** panel.
5. Choose **Update** to display the **Change maintenance window** window.
6. Enter the new day and time that you want the weekly maintenance window to start.
7. Choose **Save** to save your changes. The new maintenance start time is displayed in the file system administration **Settings** panel.

To change the weekly maintenance window using the update-file-system CLI command, see To update a file system (CLI).

Managing throughput capacity

FSx for ONTAP configures throughput capacity when you create the file system. You can modify your file system's throughput capacity at any time. Keep in mind that your file system requires a specific configuration to achieve the maximum amount of throughput capacity. For example, to provision 4 GBps of throughput capacity for a first-generation file system, your file system requires a configuration with a minimum of 5,120 GiB of SSD storage capacity and 160,000 SSD IOPS. For more information, see Impact of throughput capacity on performance.

Throughput capacity is one factor that determines the speed at which the file server that's hosting the file system can serve the file data. Higher levels of throughput capacity come with higher levels of network, disk read I/O operations per second (IOPS), and data caching capacity on the file server. For more information, see *Performance*.

When you modify your file system's throughput capacity, Amazon FSx switches out the file server that's powering your file system. Both Single-AZ and Multi-AZ file systems experience an automatic failover and failback during this process, which typically takes a few minutes to complete. The failover and failback processes are transparent to NFS (Network File Sharing), SMB (Server Message Block), and iSCSI (Internet Small Computer Systems Interface) clients, allowing your workloads to continue running without interruption or manual intervention. You are billed for the new amount of throughput capacity once it's available to your file system.

Note

To ensure data integrity during maintenance activity, FSx for ONTAP closes all opportunistic locks and completes any pending write operations to the underlying storage volumes that are hosting your file system before maintenance begins. During a scheduled file system maintenance window, system modifications (such as modifications to your throughput capacity) may be delayed. System maintenance can cause these changes to queue up until they are processed. For more information, see the section called “Updating maintenance windows”.

Topics

- When to modify throughput capacity

- How concurrent requests are handled
- Updating throughput capacity
- Monitoring throughput capacity changes

When to modify throughput capacity

Amazon FSx integrates with Amazon CloudWatch, which helps you to monitor your file system's ongoing throughput usage levels. The throughput and IOPS performance that you can drive through your file system depends on your specific workload's characteristics, in addition to your file system's throughput capacity. As a rule, you should provision enough throughput capacity to support your workload's read throughput plus twice your workload's write throughput. You can use CloudWatch metrics to determine which of these dimensions to change to improve performance. For more information, see the section called "Monitoring in the Amazon FSx console".

How concurrent requests are handled

For first-generation file systems, you can request a throughput capacity update just before an SSD storage capacity and provisioned IOPS update workflow begins or while it is in progress. The sequence of how Amazon FSx handles the two requests is as follows:

- If you submit an SSD/IOPS update and throughput capacity update at the same time, both requests are accepted. The SSD/IOPS update is prioritized before the throughput capacity update.
- If you submit a throughput capacity update while an SSD/IOPS update is in progress, the throughput capacity update request is accepted and queued to occur after the SSD/IOPS update. The throughput capacity update starts after SSD/IOPS is updated (new values are available) and during the optimization step. This typically takes less than 10 minutes.
- If you submit a SSD/IOPS update while a throughput capacity update is in progress, the SSD/IOPS storage update request is accepted and queued to start after the throughput capacity update has completed (new throughput capacity is available). This typically takes 20 minutes.

Consider the following points when requesting a throughput capacity update for second-generation file systems:

- You must wait a minimum of six hours between updating the throughput capacity for second-generation file systems.

- The throughput capacity cooldown period is shared with SSD/IOPS scaling.
- Throughput capacity scaling and SSD/IOPS scaling can't be done simulatenously or queued while either is in progress.
- You can't add high-availability (HA) pairs in conjunction with or while throughput capacity scaling or SSD/IOPS scaling are in progress. However, adding HA pairs doesn't share a cooldown with SSD/IOPS scaling and throughput capacity scaling. For more information, see Adding high-availability (HA) pairs.

For more information on SSD storage and provisioned IOPS updates, see Managing storage capacity.

Updating throughput capacity

You can modify a file system's throughput capacity using the Amazon FSx console, the AWS Command Line Interface (AWS CLI), or the Amazon FSx API.

> **Note**
>
> You must wait a minimum of six hours between updating the throughput capacity for second-generation file systems.

To modify a file system's throughput capacity (console)

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. Navigate to **File systems**, and choose the ONTAP file system that you want to increase the throughput capacity for.
3. For **Actions**, choose **Update throughput capacity**. Or, in the **Summary** panel, choose **Update** next to the file system's **Throughput capacity**.
4. Choose the new value for **Throughput capacity** from the list.
5. Choose **Update** to initiate the throughput capacity update.
6. You can monitor the update progress on the **File systems** detail page, on the **Updates** tab.

   You can monitor the progress of the update by using the Amazon FSx console, the AWS CLI, and the API. For more information, see Monitoring throughput capacity changes.

To modify a file system's throughput capacity (CLI)

To modify a file system's throughput capacity, use the AWS CLI command update-file-system. Set the following parameters:

- `--file-system-id` to the ID of the file system that you are updating.
- `ThroughputCapacity` to the desired value to update the file system to.

You can monitor the progress of the update by using the Amazon FSx console, the AWS CLI, and the API. For more information, see Monitoring throughput capacity changes.

Monitoring throughput capacity changes

You can monitor the progress of a throughput capacity modification using the Amazon FSx console, the API, and the AWS CLI.

Monitoring throughput capacity changes in the console

On the **Updates** tab in the **File system details** window, you can view the 10 most recent update actions for each update action type.

For throughput capacity update actions, you can view the following information.

Update type

Supported types are **Throughput capacity**, **Storage capacity**, and **Storage optimization**.

Target value

The desired value to change the file system's throughput capacity to.

Status

The current status of the update. For throughput capacity updates, the possible values are as follows:

- **Pending** – Amazon FSx has received the update request, but has not started processing it.
- **In progress** – Amazon FSx is processing the update request.
- **Completed** – The throughput capacity update completed successfully.
- **Failed** – The throughput capacity update failed. Choose the question mark (**?**) to see details on why the throughput update failed.

Request time

The time when Amazon FSx received the update request.

Monitoring changes with the AWS CLI and API

You can view and monitor file system throughput capacity modification requests using the describe-file-systems CLI command and the DescribeFileSystems API action. The `AdministrativeActions` array lists the 10 most recent update actions for each administrative action type. When you modify a file system's throughput capacity, a `FILE_SYSTEM_UPDATE` administrative action is generated.

The following example shows the response excerpt of a `describe-file-systems` CLI command. The file system has a throughput capacity of 128 MBps, and a target throughput capacity of 256 MBps.

```
.
.
.
    "ThroughputCapacity": 128,
"AdministrativeActions": [
    {
        "AdministrativeActionType": "FILE_SYSTEM_UPDATE",
        "RequestTime": 1581694764.757,
        "Status": "PENDING",
        "TargetFileSystemValues": {
          "OntapConfiguration": {
            "ThroughputCapacity": 256
          }
        }
    }
]
```

When Amazon FSx processes the action successfully, the status changes to `COMPLETED`. The new throughput capacity is then available to the file system, and shows in the `ThroughputCapacity` property. This is shown in the following response excerpt of a **describe-file-systems** CLI command.

```
.
.
.
```

```
    "ThroughputCapacity": 256,
"AdministrativeActions": [
    {
        "AdministrativeActionType": "FILE_SYSTEM_UPDATE",
        "RequestTime": 1581694764.757,
        "Status": "COMPLETED",
        "TargetFileSystemValues": {
          "OntapConfiguration": {
            "ThroughputCapacity": 256
          }
        }
    }
]
```

If the throughput capacity modification fails, the status changes to `FAILED`, and the `FailureDetails` property provides information about the failure.

Managing SMB shares

To manage SMB file shares on your Amazon FSx file system, you can use the Microsoft Windows Shared Folders GUI. The Shared Folders GUI provides a central location for managing all shared folders in your storage virtual machine (SVM). The following procedures detail how to create, update, and remove your file shares.

> **Note**
>
> You can also manage SMB file shares by using the NetApp System Manager. For more information, see Using NetApp System Manager with NetApp Console.

To connect shared folders to your Amazon FSx file system

1. Launch your Amazon EC2 instance and connect it to the Microsoft Active Directory that your Amazon FSx file system is joined to. To do this, choose one of the following procedures from the *AWS Directory Service Administration Guide*:

   - Seamlessly join a Windows EC2 instance
   - Manually join a Windows instance

2. Connect to your instance as a user that is a member of the file system administrators group. For more information, see Connecting to Your Windows Instance in the *Amazon EC2 User Guide*.
3. Open the **Start** menu and run **fsmgmt.msc** using **Run As Administrator**. Doing this opens the Shared Folders GUI tool.
4. For **Action**, choose **Connect to another computer**.
5. For **Another computer**, enter the DNS name for your storage virtual machine (SVM), for example **`netbios_name.corp.example.com`**.

   To find your SVM's DNS name on the Amazon FSx console, choose **Storage virtual machines**, choose your SVM, and then scroll down to **Endpoints** until you find **SMB DNS name**. You can also get the DNS name in the response of the DescribeStorageVirtualMachines API operation.
6. Choose **OK**. An entry for your Amazon FSx file system then appears in the list for the Shared Folders tool.

Now that Shared Folders is connected to your Amazon FSx file system, you can manage the Windows file shares on the file system with the following actions:

> **Note**
>
> We recommend that you locate your SMB shares on a volume other than your root volume.

- **Create a new file share** – In the Shared Folders tool, choose **Shares** in the left pane to see the active shares for your Amazon FSx file system. Volumes are shown mounted on the path chosen during volume creation. Choose **New Share** and complete the Create a Shared Folder wizard.

  You have to create the local folder prior to creating the new file share. You can do so as follows:

  - Using the Shared Folders tool: choose **Browse** when specifying a local folder path, choose **Make new folder** to create the local folder.
  - Using command line:

    ```
    New-Item -Type Directory -Path \\netbios_name.corp.example.com\C
    $volume_path\MyNewFolder
    ```

- **Modify a file share** – In the Shared Folders tool, open the context (right-click) menu for the file share that you want to modify in the right pane, and choose **Properties**. Modify the properties and choose **OK**.
- **Remove a file share** – In the Shared Folders tool, open the context (right-click) menu for the file share that you want to remove in the right pane, and then choose **Stop Sharing**.

> **Note**
>
> Removing file shares from the GUI is possible only if you connected to **fsmgmt.msc** using the DNS name of the Amazon FSx file system. If you connected using the IP address or DNS alias name of the file system, the **Stop Sharing** option won't work and the file share isn't removed.

Managing FSx for ONTAP resources using NetApp applications

In addition to the AWS Management Console, AWS CLI, and AWS API and SDKs, you can also use these NetApp management tools and applications to manage your FSx for ONTAP resources:

Topics

- Signing up for a NetApp account
- Using NetApp Console
- Using the NetApp ONTAP CLI
- Using the ONTAP REST API

> **Important**
>
> Amazon FSx periodically syncs with ONTAP to ensure consistency. If you create or modify volumes using NetApp applications, it may take up to several minutes for these changes to be reflected in the AWS Management Console, AWS CLI, API and SDKs.

Signing up for a NetApp account

In order to download some NetApp software, such as NetApp Console, SnapCenter, and the ONTAP Antivirus connector, you need to have a NetApp account. To sign up for a NetApp account, perform the following steps:

1. Go to the NetApp User Registration page and register for a new NetApp user account.
2. Complete the form(s) with your information. Be sure to select the **NetApp Customer/End User** access level. In the **SERIAL NUMBER** field, copy and paste the File System ID for your FSx for ONTAP file system. See the following example:



What to expect after you register

Customers with existing NetApp products will have their NSS account leveled-up to **Customer Level** access within one business day. Customers new to NetApp will be onboarded using standard business practices, in addition to having their NSS account leveled-up to Customer Level access. Providing the File System ID helps expedite this process. You can check the status of your NSS account by logging into mysupport.netapp.com and navigating to the **Welcome** page. The access level of your account should be **Customer Access**.

Using NetApp Console

NetApp Console (formerly NetApp BlueXP) is a unified control plane that simplifies management experiences for storage and data services across on-premises and cloud environments. NetApp Console provides a centralized user interface to manage, monitor, and automate ONTAP deployments in AWS and on premises. For more information, see the NetApp Console documentation and the Amazon FSx for NetApp ONTAP management documentation.

> **Note**
>
> NetApp Console isn't supported for second-generation file systems with more than one high-availability (HA) pair.

Using NetApp System Manager with NetApp Console

You can manage your Amazon FSx for NetApp ONTAP file systems using System Manager directly from NetApp Console. NetApp Console lets you use the same System Manager interface that you're accustomed to using, so you can manage your hybrid multi-cloud infrastructure from a single control plane. You also have access to NetApp Console's other functionality. For more information, see the Integrate ONTAP System Manager with NetApp Console topic in the NetApp ONTAP documentation.

> **Note**
>
> NetApp System Manager isn't supported for second-generation file systems with more than one HA pair.

Using the NetApp ONTAP CLI

You can manage your Amazon FSx for NetApp ONTAP resources using the NetApp ONTAP CLI. You can manage resources at the file system (analogous to NetApp ONTAP cluster) level, and at the SVM level.

Managing file systems with the ONTAP CLI

You can run ONTAP CLI commands on your FSx for ONTAP file system, similar to running them on a NetApp ONTAP cluster. You access the ONTAP CLI on your file system by establishing a secure shell

(SSH) connection to the file system's management endpoint, and logging in with the `fsxadmin` username and password. You have the option to set the `fsxadmin` password when you create a file system using the custom create flow or using the AWS CLI. If you created the file system using the Quick create option, the `fsxadmin` password was not set, so you'll need to set one in order to log in to the ONTAP CLI. For more information about setting the file system's `fsxadmin`, password, see Updating file systems. You can find the **DNS name** and **IP address** of your file system's management endpoint in the Amazon FSx console, in the **Administration** tab of the FSx for ONTAP file system details page.

To connect to the file system's management endpoint with SSH, first log in to an EC2 instance in the same VPC as the FSx for ONTAP file system. Once you're logged into the EC2 instance, use the `fsxadmin` user and password to SSH into the file system's management endpoint IP address or DNS name, as in the following examples.

```
ssh fsxadmin@file-system-management-endpoint-ip-address
```

The SSH command with sample values:

```
ec2user $ ssh fsxadmin@198.51.100.0
```

The SSH command using the management endpoint DNS name:

```
ec2user $ ssh fsxadmin@file-system-management-endpoint-dns-name
```

The SSH command using a sample DNS name:

```
ec2user $ ssh fsxadmin@management.fs-0abcdef123456789.fsx.us-east-2.aws.com
  Password: fsxadmin_password

This is your first recorded login.
FsxId0abcdef123456789::>
```

Scope of ONTAP CLI commands available to `fsxadmin`

The `fsxadmin`'s administrative view is at the file system level, which includes all SVMs and volumes in the file system. The `fsxadmin` role performs the role of the ONTAP cluster administrator. Because Amazon FSx for NetApp ONTAP file systems are fully managed, the `fsxadmin` role can run a subset of the available ONTAP CLI commands.

To see a list of the commands that `fsxadmin` can run, use the following [security login role show](#) ONTAP CLI command:

```
FsxId0abc123def456::> security login role show -role fsxadmin -access !none
           Role          Command/                                    Access
Vserver    Name          Directory                             Query Level
---------- ------------- --------- ----------------------------------- --------
FsxId0abcdef123456789
           fsxadmin      application                                   all
                         cluster application-record                    all
                         cluster date show                             readonly
                         cluster ha modify                             readonly
                         cluster ha show                               readonly
                         cluster identity modify                       readonly
                         cluster identity show                         readonly
                         cluster log-forwarding           -port !55555 all
                         cluster modify                                readonly
                         cluster peer                                  all
                         cluster show                                  readonly
                         cluster statistics show                       readonly
                         cluster time-service ntp server create        readonly
                         cluster time-service ntp server delete        readonly
                         cluster time-service ntp server modify        readonly
                         cluster time-service ntp server show          readonly
                         debug network tcpdump       -ipspace !Cluster all
                         debug san lun                                 all
                         df         -vserver !FsxId* -vserver !Cluster readonly
                         echo                                          all
                         event catalog show                            readonly
                         event config                                  all
.
.
.
378 entries were displayed.
```

Managing SVMs with the ONTAP CLI

You can access the ONTAP CLI on your SVM by establishing a secure shell (SSH) connection to the SVM's management endpoint using the `vsadmin` user name and password. You can find the SVM's management endpoint **DNS name** and **IP address** in the Amazon FSx console, in the **Endpoints** panel of the **Storage virtual machines** details page, shown in the following graphic.



To connect to the SVM's management endpoint with SSH, you can use the `vsadmin` username and password. If you did not set a password for the `vsadmin` user when the SVM was created, you can set the `vsadmin` password at anytime. For more information, see Updating storage virtual machines (SVM). You can SSH into the SVM from a client that is in the same VPC as the file system, using the management endpoint IP address or DNS name.

```
ssh vsadmin@svm-management-endpoint-ip-address
```

The command with sample values:

```
ssh vsadmin@198.51.100.10
```

The SSH command using the management endpoint DNS name:

```
ssh vsadmin@svm-management-endpoint-dns-name
```

The SSH command using a sample DNS name:

```
ssh vsadmin@management.svm-abcdef01234567892fs-0abcdef123456789.fsx.us-east-2.aws.com
```

```
Password: vsadmin-password

This is your first recorded login.
FsxId0abcdef123456789::>
```

Amazon FSx for NetApp ONTAP supports the NetApp ONTAP CLI commands.

For a complete reference of NetApp ONTAP CLI commands, see the ONTAP Commands: Manual Page Reference.

Using the ONTAP REST API

When accessing your FSx for ONTAP file system using the ONTAP REST API using the `fsxadmin` credentials, do one of the following:

- Disable TLS validation.

  Or

- Trust the AWS certificate authorities (CAs) – The certificate bundle for the CAs in each region can be found at the follow URLs:
  - https://fsx-aws-certificates.s3.amazonaws.com/bundle-*aws-region*.pem for Public AWS Regions
  - https://fsx-aws-us-gov-certificates.s3.us-gov-west-1.amazonaws.com/bundle-*aws-region*.pem for AWSGovCloud Regions
  - https://fsx-aws-cn-certificates.s3.cn-north-1.amazonaws.com.cn/bundle-*aws-region*.pem for AWS China Regions

For a complete reference of NetApp ONTAP REST API commands, see the NetApp ONTAP REST API Online Reference.

Tagging Amazon FSx resources

To help you manage your file systems and other Amazon FSx resources, you can assign your own metadata to each resource in the form of *tags*. With tags, you can categorize your AWS resources in different ways, for example, by purpose, owner, or environment. This categorization is useful when you have many resources of the same type—you can quickly identify a specific resource based on the tags that you've assigned to it. This topic describes tags and shows you how to create them.

Topics

- Tag basics
- Tagging your resources
- Copying tags to backups

- Tag restrictions
- Permissions and tagging

Tag basics

A *tag* is a label that you assign to an AWS resource. Each tag consists of two parts that you define:

- A *tag key* (for example, `CostCenter`, `Environment`, or `Project`). Tag keys are case sensitive.
- A *tag value* (for example, `111122223333` or `Production`). Like tag keys, tag values are case sensitive. Tag values are optional.

You can use tags to categorize your AWS resources in different ways, such as, by purpose, owner, or environment. For example, you could define a set of tags for your account's Amazon FSx file systems that helps you track each instance's owner and stack level.

We recommend that you devise a set of tag keys that meets your needs for each resource type. Using a consistent set of tag keys makes it easier for you to manage your resources. You can search and filter the resources based on the tags that you add. For more information about how to implement an effective resource tagging strategy, see Tagging AWS resources in the *AWS General Reference*.

Some tagging behaviors to keep in mind:

- Tags don't have any semantic meaning to Amazon FSx and are interpreted strictly as a string of characters.
- Tags are not automatically assigned to your resources.
- You can edit tag keys and values, and you can remove tags from a resource at any time.
- You can set the value of a tag to an empty string, but you can't set the value of a tag to `null`.
- If you add a tag that has the same key as an existing tag on that resource, the new value overwrites the old value.
- If you delete a resource, any tags for the resource are also deleted.
- If you're using the Amazon FSx API, the AWS Command Line Interface (AWS CLI), or an AWS SDK, you can do the following:

- You can use the `TagResource` API action to apply tags to existing resources.
- For some resource-creating actions, you can specify tags for a resource when the resource is created. By tagging resources at the time of creation, you can eliminate the need to run custom tagging scripts after resource creation.

  If tags cannot be applied during resource creation, Amazon FSx rolls back the resource creation process. This behavior helps ensure that resources are either created with tags or not created at all, and that no resources are left untagged at any time.

  > **Note**
  >
  > Certain AWS Identity and Access Management (IAM) permissions are required for users to tag resources on creation. For more information, see Grant permission to tag resources during creation.

Tagging your resources

You can tag Amazon FSx resources that exist in your account. If you're using the Amazon FSx console, you can apply tags to resources by using the **Tags** tab on the relevant resource screen. When you create resources, you can apply the **Name** key with a value, and you can apply tags of your choice when creating a new file system. However, even though the console organizes resources according to the **Name** key, this key doesn't have any semantic meaning to the Amazon FSx service.

To implement granular control over the users and groups that can tag resources on creation, you can apply tag-based resource-level permissions in your IAM policies to the Amazon FSx API actions that support tagging on creation. By using such permissions in your policies, you get the following benefits:

- Your resources are properly secured from creation.
- Because tags are applied immediately to your resources, any tag-based resource-level permissions controlling the use of resources are immediately effective.
- Your resources can be tracked and reported on more accurately.
- You can enforce the use of tagging on new resources, and control which tag keys and values are set on your resources.

To control which tag keys and values are set on your existing resources, you can apply resource-level permissions to the `TagResource` and `UntagResource` Amazon FSx API actions in your IAM policies.

For more information about the permissions required to tag Amazon FSx resources at creation, see Grant permission to tag resources during creation.

For more information about using tags to restrict access to Amazon FSx resources in IAM policies, see Using tags to control access to your Amazon FSx resources.

For information about tagging your resources for billing, see Using cost allocation tags in the *AWS Billing User Guide*.

Copying tags to backups

When you create or update a volume in the Amazon FSx API or AWS CLI, you can enable `CopyTagsToBackups` to automatically copy any tags from your volumes to backups.

> **Note**
>
> If you specify tags while creating a user-initiated backup (including the name tag when you create a backup using the Amazon FSx console), tags are *not* copied from the volume even if you've enabled `CopyTagsToBackups`.

For more information about backups, see Protecting your data with volume backups. For more information about enabling `CopyTagsToBackups`, see To create a volume (CLI) and To update a volume's configuration (CLI) in the *Amazon FSx for NetApp ONTAP User Guide* or CreateVolume and UpdateVolume in the *Amazon FSx for NetApp ONTAP API Reference*.

Tag restrictions

The following basic restrictions apply to tags:

- The maximum number of tags per resource is 50.
- The maximum key length is 128 Unicode characters in UTF-8.
- The maximum value length is 256 Unicode characters in UTF-8.
- The allowed characters are letters, numbers, and spaces representable in UTF-8, and the following characters: `+ - =` (hyphen) `. _` (underscore) `: / @`.

- For each resource, each tag key must be unique, and each tag key can have only one value.
- Tag keys and values are case sensitive.
- The `aws:` prefix is reserved for AWS use. If a tag has a tag key with this prefix, you can't edit or delete the tag's key or value. Tags with the `aws:` prefix do not count against your tags per resource limit.

You can't delete a resource based solely on its tags; you must specify the resource identifier. For example, to delete a file system that you tagged with a tag key called `DeleteMe`, you must use the `DeleteFileSystem` action with the file system resource identifier, such as `fs-1234567890abcdef0`.

When you tag public or shared resources, the tags that you assign are available only to your AWS account; no other AWS account has access to those tags. For tag-based access control to shared resources, each AWS account must assign its own set of tags to control access to the resource.

Permissions and tagging

For more information about the permissions required to tag Amazon FSx resources at creation, see Grant permission to tag resources during creation.

For more information about using tags to restrict access to Amazon FSx resources in IAM policies, see Using tags to control access to your Amazon FSx resources.

Protecting your data

Beyond automatically replicating your file system's data to ensure high durability, with Amazon FSx you also have the following options that you can use to further protect your data:

- Native Amazon FSx volume backups that support your backup retention and compliance needs within Amazon FSx.
- Using AWS Backup to implement a centrally managed, automated backup and retention strategy across multiple AWS services.
- Snapshots that enable your users to easily undo unwanted file changes, by restoring files to previous versions.
- Use SnapLock to create write once, read many (WORM) storage volumes to prevent file modification or deletion once committed, for a specified retention period.
- FlexCache volumes offer storage efficient, cost effective, high-performance data replication for read-heavy workloads with data that remains largely unchanged.
- Use SnapMirror to create scheduled, automatic file system replication to a second file system for data protection and disaster recovery.

Topics

- Protecting your data with volume backups
- Protecting your data with snapshots
- Protecting your data with Autonomous Ransomware Protection
- Protecting your data with SnapLock
- Replicating your data with FlexCache
- Replicating your data using NetApp SnapMirror

Protecting your data with volume backups

With FSx for ONTAP, you can protect your data by taking automatic daily backups and user-initiated backups of the volumes on your file system. Creating regular backups for your volumes is a best practice that helps support your data retention and compliance needs. You can restore volume backups to any existing FSx for ONTAP file system you have access to that is in the same

AWS Region where the backup is stored. Working with Amazon FSx backups makes it is easy to create, view, restore, and delete backups of your volumes.

Amazon FSx supports backing up ONTAP volumes with an `OntapVolumeType` of read-write (RW).

> **Note**
>
> Amazon FSx doesn't support backing up data protection (DP) volumes, load sharing mirror (LSM) volumes, or destination volumes for FlexCache and SnapMirror.

Topics

- How backups work
- Storage requirements
- Automatic daily backups
- User-initiated backups
- Copying tags to backups
- Using AWS Backup with Amazon FSx
- Copying backups
- Restoring backups to a new volume
- Backup and restore performance
- Backing up SnapLock volumes
- Creating user-initiated backups
- Copying backups within the same AWS account
- Restoring a backup to a new volume
- Restoring a subset of data
- Monitoring progress when restoring a backup
- Deleting backups

How backups work

All Amazon FSx backups (automatic daily backups and user-initiated backups) are incremental, which means that they only store changes in the data since the previous backup was completed. This minimizes both the time required to create a backup and the amount of storage used by

each backup. Incremental backups optimize storage costs by not storing duplicate data. FSx for ONTAP backups are per volume, with each backup containing only the data of one specific volume. Amazon FSx backups are stored redundantly across multiple Availability Zones to achieve high durability.

Amazon FSx backups use snapshots – point-in-time, read-only images of your volumes – to maintain incrementality between backups. Each time a backup is taken, Amazon FSx first takes a snapshot of your volume. The backup snapshot is stored in your volume, and consumes storage space on the volume. Amazon FSx then compares this snapshot to the previous backup snapshot (if one exists) and copies only the changed data into your backup.

If no prior backup snapshot exists, then the entire contents of the most recent backup snapshot is copied into your backup. After the latest backup snapshot is successfully taken, Amazon FSx deletes the previous backup snapshot. The snapshot used for the latest backup remains in your volume until the next backup is taken, when the process repeats. To optimize backup storage costs, ONTAP preserves a volume's storage efficiency savings in its backups.

When you delete a backup, only the data unique to that backup is deleted. Each Amazon FSx backup contains all of the information that is needed to create a new volume from the backup, effectively restoring a point-in-time snapshot of the volume.

There are limits to the number of backups that you can store per AWS account and per volume. For more information, see Quotas that you can increase and Resource quotas for each file system.

> **Note**
>
> If you use NDMP for backups, ONTAP does not allow maintenance activities such as patch operations to proceed while an NDMP transfer is in progress. To avoid delaying patches, Amazon FSx will abort any active NDMP transfer sessions when a patch operation is applied during your file system's maintenance window. Once patching is complete, you will need to manually restart your NDMP transfer sessions from the client side, as Amazon FSx cannot automatically resume them. To avoid backup interruptions, we recommend using Amazon FSx backups or AWS Backup, which support concurrent backup and patch operations.

Storage requirements

Your volume and your file system must each have enough available SSD storage capacity to store a backup snapshot. When taking a backup snapshot, the additional storage capacity consumed by

the snapshot cannot cause the volume to exceed 98% SSD storage utilization. If this happens, the backup will fail. You can increase a volume's or file system's SSD storage at anytime to ensure that your backups won't be interrupted.

Automatic daily backups

When you create a file system, automatic daily backups are enabled by default for your file system's volumes. You can enable or disable automatic daily backups for existing file systems at any time. Automatic daily backups for all volumes occur during the file system's daily backup window, which is automatically set when you create a file system. You can modify the daily backup window at any time. For optimal backup performance, we recommend that you choose a daily backup window that is outside of the normal operating hours when clients and applications are accessing the data on your volumes. We also recommend choosing a backup window that does not overlap with your file system's maintenance window. If the windows overlap, maintenance activities take precedence and automated backups occur after maintenance is complete. Backups that are already in progress will continue during maintenance, however, new backup creation may not occur until maintenance is complete. If maintenance runs for the full duration of the window, automated backups may not occur during that window.

Using the console, you can set the retention period for automatic daily backups to a value from 1 to 90 days when creating a file system or at any time. The default automatic daily backup retention period is 30 days. Amazon FSx deletes an automatic daily backup once its retention period expires. Using the AWS CLI and API, you can set the retention period to a value from 0 to 90 days; setting it to 0 disables automatic backups and deletes all existing automatic backups for the file system's volumes.

Automatic daily backups, the daily backup window, and the backup retention period are file system settings, and apply to all volumes on your file system. You can use the Amazon FSx console, the AWS CLI, or API to change these settings. For more information, see Updating file systems.

You can't create a volume backup (automatic daily backups or user-initiated backups) if the volume is offline. For more information, see Viewing offline volumes.

> **Note**
>
> Automatic daily backups have a maximum retention period of 90 days, but user-initiated backups that you create, which include backups created using AWS Backup, are retained forever unless you or AWS Backup deletes them.

You can manually delete an automatic daily backup using the Amazon FSx console, CLI, and API. When you delete a volume, you also delete the automatic daily backups for that volume. Amazon FSx provides the option to create a final backup of a volume before you delete it. The final backup is kept forever, unless you delete it.

User-initiated backups

With Amazon FSx, you can manually take backups of your file system's volumes at any time using the AWS Management Console, AWS CLI, and API. Your user-initiated backups are incremental relative to other backups that may have been created for a volume and are retained forever, unless you delete them. User-initiated backups are retained even after you delete the volume or the file system the backups were created on. You can delete user-initiated backups only by using the Amazon FSx console, API, or CLI. They are never automatically deleted by Amazon FSx.

For instructions on how to create a user-initiated backup, see Creating user-initiated backups.

Copying tags to backups

When you create or update a volume using the CLI or API, you can enable `CopyTagsToBackups` to automatically copy any tags on your volume to its backups. However, if you add any tags while creating a user-initiated backup, including naming a backup when you use the console, Amazon FSx does *not* copy tags from the volume, even if `CopyTagsToBackups` is enabled.

Using AWS Backup with Amazon FSx

AWS Backup is a simple and cost-effective way to protect your data by backing up your Amazon FSx for NetApp ONTAP volumes. AWS Backup is a unified backup service designed to simplify the creation, restoration, and deletion of backups, while providing improved reporting and auditing. Using AWS Backup makes it easier to develop a centralized backup strategy for legal, regulatory, and professional compliance. It also makes protecting your AWS storage volumes, databases, and file systems simpler by providing a central place where you can do the following:

- Configure and audit the AWS resources that you want to back up.
- Automate backup scheduling.
- Set retention policies.
- Monitor all recent backup, copy, and restore activity.

AWS Backup uses the built-in backup functionality of Amazon FSx. Backups created using the AWS Backup console have the same level of file system consistency and performance, are incremental relative to any other Amazon FSx user-initiated backups taken of your volume, and offer the same restore options as backups taken using the Amazon FSx console. Using AWS Backup to manage these backups provides additional functionality, including the ability to create scheduled backups as frequently as every hour. You can add an additional layer of defense to protect backups from inadvertent or malicious deletions by storing them in a backup vault.

Backups created by AWS Backup are considered user-initiated backups, and they count toward the user-initiated backup quota for Amazon FSx. For more information, see Quotas that you can increase. You can view and restore backups created by AWS Backup using the Amazon FSx console, CLI, and API. However, you can't delete backups created by AWS Backup in the Amazon FSx console, CLI, or API. For more information, see Getting started with AWS Backup in the AWS Backup Developer Guide.

AWS Backup can't back up volumes that are offline.

You can use tags to select which of your FSx for ONTAP resources are protected in a backup plan. These tags must be applied at the volume level rather than the file system level as a whole. For more information, see Assigning resources to a backup plan in the AWS Backup Developer Guide.

Copying backups

With Amazon FSx, you can manually copy volume backups to another AWS Region (cross-Region copies) or within the same AWS Region (in-Region copies). Both copy types operate within the same AWS account. You can make cross-Region copies only within the same AWS partition. You can create user-initiated backup copies using the Amazon FSx console, AWS CLI, or API. When you create a user-initiated backup copy, it has the type `USER_INITIATED`.

You can also use AWS Backup to copy backups across AWS Regions and across AWS accounts. With AWS Backup, a fully managed backup management service, you can manage policy-based backup plans from a central interface. With its cross-account management, you can use backup policies to apply backup plans across the accounts within your organization.

Cross-Region backup copies

Cross-Region backup copies are particularly valuable for cross-Region disaster recovery. You take backups and copy them to another AWS Region. Then, if a disaster affects the primary AWS Region, you can restore from backup and quickly recover availability in the other Region. You can also use backup copies to clone a volume's data to another AWS Region or within the same AWS Region.

You make backup copies within the same AWS account (cross-Region or in-Region) by using the Amazon FSx console, AWS CLI, or Amazon FSx API. You can also use AWS Backup to perform backup copies, either on-demand or policy-based.

Cross-account backup copies

Use cross-account backup copies to meet regulatory compliance requirements and copy backups to an isolated account. They also provide an additional layer of data protection. This helps prevent accidental or malicious deletion of backups, loss of credentials, or compromise of AWS KMS keys. Cross-account backups support two patterns. With *fan-in*, you copy backups from multiple primary accounts to one isolated account. With *fan-out*, you copy backups from one primary account to multiple isolated accounts.

You can make cross-account backup copies by using AWS Backup with AWS Organizations support. Account boundaries for cross-account copies are defined by AWS Organizations policies. For more information about using AWS Backup to make cross-account backup copies, see Creating backup copies across AWS accounts in the *AWS Backup Developer Guide*.

Backup copy limitations

The following are some limitations when you copy backups:

- Cross-Region backup copies are supported only between any two commercial AWS Regions, between the China (Beijing) and China (Ningxia) Regions, and between the AWS GovCloud (US-East) and AWS GovCloud (US-West) Regions, but not across those sets of Regions.
- You can make in-Region backup copies within any AWS Region.
- The source backup must have a status of `AVAILABLE` before you can copy it.
- You cannot delete a source backup if it is being copied. There might be a short delay between when the destination backup becomes available and when you are allowed to delete the source backup. You should keep this delay in mind if you retry deleting a source backup.
- You can have up to five backup copy requests in progress for a single volume to a single destination AWS Region and AWS KMS key.
- You can have up to 1,000 backup copy requests in progress per account. If you exceed this limit, Amazon FSx rejects the request; retry the copy after one or more of your in-progress copies complete.
- Amazon FSx doesn't support copying backups of FlexGroup volumes.
- Cross-account backup copies aren't supported in the China (Beijing) or China (Ningxia) Regions.

Permissions for cross-Region backup copies

You use an IAM policy statement to grant permissions to perform a backup copy operation. To request a cross-Region backup copy, the requester must communicate with the source AWS Region. The requester (IAM role or IAM user) must have access to the source backup and the source AWS Region.

You use the policy to grant permissions to the `CopyBackup` action for the backup copy operation. You specify the action in the policy's `Action` field, and you specify the resource value in the policy's `Resource` field, as in the following example.

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Effect": "Allow",
            "Action": "fsx:CopyBackup",
            "Resource": "arn:aws:fsx:*:111122223333:backup/*"
        }
    ]
}
```

For more information about IAM policies, see Policies and permissions in IAM in the *IAM User Guide*.

Full and incremental copies

When you copy a backup to a different AWS Region from the source backup, the first copy is always a full backup copy. This is the case even if you use the same AWS KMS key to encrypt both the source and destination copies of the backup. After the first copy, all subsequent backup copies to the same destination Region within the same AWS account are incremental. This applies as long as you haven't deleted all previously-copied backups in that Region and have been using the same AWS KMS key. If both conditions aren't met, the copy operation results in a full (not incremental) backup copy.

To learn how to copy backups of your volumes, see Copying backups within the same AWS account.

Restoring backups to a new volume

You can restore a volume backup to a new volume on a file system that is in the same AWS Region that the backup is stored in. To restore a backup to a file system that is located in a different

AWS Region than the backup, you can copy that backup to that file system's AWS Region and then restore that backup copy. For more information, see Copying backups within the same AWS account.

When restoring a backup on FSx for ONTAP second-generation file systems, clients can mount and read data from a volume while it is being restored. Clients can mount the volume you are restoring and read the file data once Amazon FSx has loaded all the metadata onto the new volume and the volume reports a lifecycle status of CREATED. You can find a volume's lifecycle state on the **Volumes detail** page in the Amazon FSx console and in the response of the describe-volumes CLI command.

When reading data from a volume while it is being restored from a backup, if the data has not been downloaded onto the volume yet, you will incur read latencies of up to tens of milliseconds for the first access. These reads are cached in the SSD tier, and you can expect sub-millisecond read latencies for subsequent reads.

The amount of time it takes for Amazon FSx to make a volume available for read-only access is proportional to the amount of file metadata stored in the backup. File metadata typically consumes 1-7% of the overall backup data depending on the average file size in your data set (small file data sets consume more metadata than large file data sets).

When you restore a FlexGroup volume backup to a file system that has a different number of high-availability (HA) pairs than the original file system, Amazon FSx adds additional constituent volumes to ensure that the constituents are evenly distributed.

> **Note**
>
> Amazon FSx does not support read access to data while a volume is being restored from a backup for either SnapLock volumes or for any volumes on first-generation file systems. When restoring these backups, the volume becomes available to mount and access data after the restore process is completed, and all metadata and data are loaded onto the new volume.

When restoring a backup, all data is initially written to the SSD storage tier. While the restore is in progress, data is tiered to the capacity pool storage in accordance with the tiering policy of volume being restored. Since data is first written to the SSD tier, Amazon FSx will pause the restoration process if the file system runs out of SSD storage space. The restore automatically resumes as soon

as sufficient SSD space becomes available to continue the process. If the restored volume's tiering policy is `All`, a periodic background process tiers the data to the capacity pool. If the restored volume's tiering policy is `Snapshot Only` or `Auto`, data is tiered to the capacity pool if the SSD utilization for the file system is greater than 50%, and the cooling rate is determined by the tiering policy's cooling period.

If your workload requires consistent sub-millisecond read latencies when restoring a backup to a new volume on second-generation file systems, we recommend that you set the volume's tiering policy to `None` when initiating the restore, and then wait until all data has been fully downloaded onto the volume before you access it. All data will be loaded into SSD storage before you attempt to access it, providing you with consistent low-latency access to your data.

For step-by-step instructions on how to restore a backup to a new volume, see Restoring a backup to a new volume.

On second-generation file systems you can also restore just a subset of data from a backup without having to wait for the entire restore operation to complete. Restoring just a subset of a backup's data enables you to resume operations faster in the event of accidental deletion, modification, or corruption of data. For more information, see Restoring a subset of data.

You can monitor the progress when restoring a backup on a second-generation file system in the AWS Management Console, AWS CLI, and API. For more information, see Monitoring progress when restoring a backup.

Note

- You can't create a volume snapshot or perform snapshot-based operations such as cloning, SnapMirror replication, and creating backups of a volume while it is being restored from a backup.
- A restored volume always has the same volume style as the original volume. You can't change the volume style when restoring.

Backup and restore performance

A variety of factors can influence the performance of backup and restore operations. Backup and restore operations are background processes, which means they have a lower priority relative to client IO operations. Client IO operations include NFS, CIFS, and iSCSI data and metadata reads and

writes. All background processes utilize only the unused portion of your file system's throughput capacity, and can take from a few minutes to a few hours to complete depending on the size of your backup and the amount of unused throughput capacity on your file system.

Other factors that affect backup and restore performance include the storage tier in which your data is stored and the dataset profile. We recommend that you create the first backups of your volumes when most of the data is on SSD storage. Datasets containing mostly small files will typically have lower performance as compared to similarly sized datasets that contain mostly large files. This is because processing large numbers of small files consumes more CPU cycles and network overhead than processing fewer large files.

Generally, you can expect the following backup rates when backing up data stored in the SSD storage tier:

- 750 MBps across several concurrent backups containing mostly large files.
- 100 MBps across several concurrent backups containing mostly small files.

Generally, you can expect the following restore rates:

- 250 MBps across several concurrent restores containing mostly large files.
- 100 MBps across several concurrent restores containing mostly small files.

Backing up SnapLock volumes

You can back up SnapLock volumes for additional data protection. When you restore a SnapLock volume, the volume's original settings—such as the default retention, minimum retention, and maximum retention—are preserved. Write once, read many (WORM) settings and Legal Hold are also preserved.

> **Note**
>
> You can't back up a SnapLock FlexGroup volume.

You can restore a SnapLock volume's backup as a SnapLock or a non-SnapLock volume. However, you can't restore a non-SnapLock volume's backup as a SnapLock volume.

For more information, see How SnapLock works.

Creating user-initiated backups

The following procedure describes how to create a user-initiated backup of a volume.

You cannot create a volume backup if the volume is offline. For more information, see Viewing offline volumes.

To create a user-initiated backup (console)

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. Navigate to **File systems** and choose the ONTAP file system that you want to back up a volume for.
3. Choose the **Volumes** tab.
4. Choose the volume you want to back up.
5. From **Actions**, choose **Create backup**.
6. In the **Create backup** dialog box that opens, provide a name for your backup. Backup names can be a maximum of 256 Unicode characters, including letters, white space, numbers, and the special characters . + - = _ : /
7. Choose **Create backup**.

You have now created a backup of one of your file system's volumes. You can see all of your backups in the Amazon FSx console by choosing **Backups** in the left side navigation. You can search for the name you gave your backup, and the table filters to only show matching results.

When you create a user-initiated backup as this procedure described, it has the type `USER_INITIATED`, and it has the `CREATING` status until it is fully available.

Copying backups within the same AWS account

You can copy volume backups on FSx for ONTAP file systems using the AWS Management Console, CLI, and API, as described in the following procedures.

To copy a backup within the same account (cross-Region or in-Region) using the console

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. In the navigation pane, choose **Backups**.

3. In the **Backups** table, choose the backup that you want to copy, and then choose **Copy backup**.
4. In the **Settings** section, do the following:
   - In the **Destination Region** list, choose a destination AWS Region to copy the backup to. The destination can be in another AWS Region (cross-Region copy) or within the same AWS Region (in-Region copy).
   - (Optional) Select **Copy Tags** to copy tags from the source backup to the destination backup. If you select **Copy Tags** and also add tags at step 6, all the tags are merged.
5. For **Encryption**, choose the AWS KMS encryption key to encrypt the copied backup.
6. For **Tags - optional**, enter a key and value to add tags for your copied backup. If you add tags here and also selected **Copy Tags** at step 4, all the tags are merged.
7. Choose **Copy backup**.

   Your backup is copied within the same AWS account to the selected AWS Region.
8. You can monitor the progress of the operation using the `ProgressPercent` property in the response of the `describe-backups` CLI command or the DescribeBackups API operation.

To copy a backup within the same account (cross-Region or in-Region) using the CLI

- Use the `copy-backup` CLI command or the CopyBackup API operation to copy a backup within the same AWS account. You can copy the backup either across AWS Regions or within an AWS Region.

  The following command copies a backup with an ID of `backup-0abc123456789cba7` from the `us-east-1` Region.

  ```
  aws fsx copy-backup \
    --source-backup-id backup-0abc123456789cba7 \
    --source-region us-east-1
  ```

  The response shows the description of the copied backup.

  You can view your backups on the Amazon FSx console or programmatically using the `describe-backups` CLI command or the DescribeBackups API operation.

Choosing between backup copies and NetApp SnapMirror

For cross-Region resilience, you can either copy backups to another AWS Region or use NetApp SnapMirror to replicate data to a second FSx for ONTAP file system. Which approach you choose depends on whether your primary goal is compliance or availability.

Copy backups to different AWS Regions or accounts if you have compliance requirements that mandate storing offline copies of your data. These offline copies aren't immediately impacted by security or availability incidents affecting the primary file system and its replicas. Backups are logically separated from a file system, so your backup data remains secure and unaffected if your file system is compromised. Copying backups within and across AWS Regions and accounts is the simplest way to protect your data from these types of events. You don't need to provision and manage secondary file systems or maintain a NetApp SnapMirror relationship.

Use NetApp SnapMirror to replicate data across FSx for ONTAP file systems for cross-Region disaster recovery and improve the availability of your data. You can configure replication with a Recovery Point Objective (RPO) as low as 5 minutes, compared to 60 minutes with backups. You can also achieve a Recovery Time Objective (RTO) in single-digit minutes, compared to minutes to hours with backups. The RTO for backups depends on the size of your backup. With NetApp SnapMirror, you get the lowest recovery times in the event of a disaster affecting the primary AWS Region. For more information, see Replicating your data using NetApp SnapMirror.

Restoring a backup to a new volume

The following procedures describe how to restore an FSx for ONTAP backup to a new volume using the AWS Management Console and AWS CLI. When restoring a volume to a second-generation file system, you can monitor the progress using the AWS Management Console, AWS CLI, and API.

To restore a volume backup to a new volume (Console)

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. In the navigation pane, choose **Backups**, and then choose the FSx for ONTAP volume backup that you want to restore.
3. In the upper right **Actions** menu, choose **Restore backup**. The **Create volume from backup page appears.**
4. Choose the FSx for ONTAP **File system** and **Storage virtual machine** that you want to restore the backup to from the dropdown menus.

5. In the upper right **Actions** menu, choose **Restore backup**. The **Create volume from backup page appears.**
6. Choose the FSx for ONTAP **File system** and **Storage virtual machine** that you want to restore the backup to from the dropdown menus.
7. Under **Volume details**, there are several selections. First, enter the **Volume name**. You can use up to 203 alphanumeric or underscore (_) characters.
8. For **Volume size**, enter any whole number in the range of 20–314572800 to specify the size in mebibytes (MiB).
9. For **Volume type**, choose **Read-Write (RW)** to create a volume that is readable and writable or **Data Protection (DP)** to create a volume that is read-only and can be used as the destination of a NetApp SnapMirror or SnapVault relationship. For more information, see Volume types.
10. For **Junction path**, enter a location within the file system to mount the volume. The name must have a leading forward slash, for example `/vol3`.
11. For **Storage efficiency**, choose **Enabled** to enable the ONTAP storage-efficiency features (deduplication, compression, and compaction). For more information, see Storage efficiency.
12. For **Volume security style**, choose either **Unix (Linux)**, **NTFS**, or **Mixed**. A volume's security style determines whether preference is given to NTFS or UNIX ACLs for multi-protocol access. The MIXED mode is not required for multi-protocol access and is only recommended for advanced users.
13. For **Snapshot policy**, choose a snapshot policy for the volume. For more information about snapshot policies, see Snapshot policies.

    If you choose **Custom policy**, you must specify the policy's name in the **custom-policy** field. The custom policy must already exist on the SVM or in the file system. You can create a custom snapshot policy with the ONTAP CLI or REST API. For more information, see Create a Snapshot Policy in the NetApp ONTAP Product Documentation.
14. For **Tiering policy cooling period**, valid values are 2-183 days. A volume's tiering policy cooling period defines the number of days before data that has not been accessed is marked cold and moved to capacity pool storage. This setting only affects the `Auto` and `Snapshot-only` policies.
15. In the **Advanced** section, for **SnapLock Configuration**, you can leave the default **Disabled** setting or choose **Enabled** to configure a SnapLock volume. For more information about configuring a SnapLock Compliance volume or a SnapLock Enterprise volume, see Understanding SnapLock Compliance and Understanding SnapLock Enterprise. For more information about SnapLock, see Protecting your data with SnapLock.

16. Choose **Confirm** to create the volume.
17. If you are restoring the backup to a second-generation file system, you can monitor the backup restore progress on the **Updates** tab on the **Volume** page. For more information, see Monitoring progress when restoring a backup.

To restore a backup to a new volume (CLI)

Use the create-volume-from-backup CLI command, or the equivalent CreateVolumeFromBackup API command to restore a volume backup to a new volume.

- ```
  $ aws fsx create-volume-from-backup --backup-id backup-08e6fc1133fff3532 \
        --name demo --ontap-configuration JunctionPath=/demo,SizeInMegabytes=100000,\
        StorageVirtualMachineId=svm-0f04a9c7c27e1908b,TieringPolicy={Name=ALL}
  ```

  The system response for a successful restore request to restore a backup to a second-generation file system looks as follows. The response includes the `"AdministrativeActions"` object which provides status and progress information about request..

  ```
  {
        "Volume": {
            "CreationTime": 1692721488.428,
            "FileSystemId": "fs-07ab735385276ed60",
            "Lifecycle": "CREATING",
            "Name": "demo",
            "OntapConfiguration": {
                "FlexCacheEndpointType": "NONE",
                "JunctionPath": "/demo",
                "SizeInMegabytes": 100000,
                "StorageEfficiencyEnabled": true,
                "StorageVirtualMachineId": "svm-0f04a9c7c27e1908b",
                "StorageVirtualMachineRoot": false,
                "TieringPolicy": {
                    "Name": "ALL"
                },
                "OntapVolumeType": "DP",
                "SnapshotPolicy": "default",
                "CopyTagsToBackups": false,
            },
  ```
  ```

```
          "ResourceARN": "arn:aws:fsx:us-east-1:752825163408:volume/
fs-07ab735385276ed60/fsvol-0b6ec764c9c5f654a",
          "VolumeId": "fsvol-0b6ec764c9c5f654a",
          "VolumeType": "ONTAP",
  --->    "AdministrativeActions": [
              {
                  "AdministrativeActionType": "DOWNLOAD_DATA_FROM_BACKUP",
                  "RequestTime": 1685729972.069,
                  "Status": "PENDING"
              }
          ]                 <----
      }
  }
```

The system response for a successful request to restore a backup to a first-generation file system looks as follows.

```
{
      "Volume": {
          "CreationTime": 1692721488.428,
          "FileSystemId": "fs-07ab735385276ed60",
          "Lifecycle": "CREATING",
          "Name": "demo",
          "OntapConfiguration": {
              "FlexCacheEndpointType": "NONE",
              "JunctionPath": "/demo",
              "SizeInMegabytes": 100000,
              "StorageEfficiencyEnabled": true,
              "StorageVirtualMachineId": "svm-0f04a9c7c27e1908b",
              "StorageVirtualMachineRoot": false,
              "TieringPolicy": {
                  "Name": "ALL"
              },
              "OntapVolumeType": "DP",
              "SnapshotPolicy": "default",
              "CopyTagsToBackups": false,
          },
          "ResourceARN": "arn:aws:fsx:us-east-1:752825163408:volume/
fs-07ab735385276ed60/fsvol-0b6ec764c9c5f654a",
          "VolumeId": "fsvol-0b6ec764c9c5f654a",
          "VolumeType": "ONTAP",
      }
```

```
}
```

When restoring a volume to a second-generation file system, you can monitor the progress using the AWS Management Console, AWS CLI, and API.

Restoring a subset of data

You can restore a subset of data from a backup while it is being restored to a new volume on second-generation file systems without having to wait until the entire backup data set has been fully restored.

The following procedure lists the steps to take when you need to recover a subset of data when restoring a backup, and can't wait for the entire restore to complete:

To restore a subset of data while restoring a backup

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. In the **Backups** page, locate the backup that contains the version of the data that you want to restore.
3. In the upper right **Actions** menu, choose **Restore backup**. The **Create volume from backup page appears.**
4. Choose the FSx for ONTAP **File system** and **Storage virtual machine** that you want to restore the backup to from the dropdown menus.
5. Under **Volume details**, configure the volume to meet your needs.
6. Choose **Confirm** to create the volume.
7. Monitor the progress of the backup restore.
8. Mount the volume being restored when it reports a lifecycle status of `CREATED`.
9. Locate the subset of the data on the volume you need to copy.
10. Copy the data to the existing volume that your application uses.
11. Once the required data from the backup has been copied over to the target location, you can delete the volume being restored before it completes to optimize utilization of file system resources.

Monitoring progress when restoring a backup

You can monitor the progress when restoring a volume backup to second-generation file system in the AWS Management Console, AWS CLI, and API. As with all Amazon FSx administrative actions, a backup restore status is available in the console, CLI, and API for 30 days after the operation is completed.

To monitor progress when restoring a backup (console)

Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.

1. In the left navigation menu, choose **Volumes**.
2. Choose the volume that the backup is being restored to.
3. Choose the **Updates** tab.
4. The **Backup restore Update type** provides the following information:

   - **PENDING** indicates that the file metadata is being downloaded onto the volume. The volume's **Lifecycle state** is **CREATING**.
   - **IN_PROGRESS** indicates that the volume is available and clients can mount the volume with read-only access to data. The **Progress %** shows the percentage of data that has been downloaded to the volume.
   - **COMPLETED** indicates that all data has been downloaded to the volume, and the backup restore is complete. Clients now have read-write access. For `RW` volumes, the volume's type changes from `DP` to `RW` at this point.

To monitor progress when restoring a backup (CLI)

- When you restore a backup to a new volume on a second-generation FSx for ONTAP file system, you can monitor the progress of the restore using the `describe-volumes` CLI command.

  When restoring a backup to a second-generation file system, the response includes the `AdministrativeActions` object, which provides status information about the data downloading process. The

```
$ aws fsx describe-volumes
{
    “Volumes”: [
```

```
        {
            “CreationTime”: 1691686114.674,
            “FileSystemId”: fs-029ff92192bd4d375,
            “LifeCycle”: “CREATING”,
            “Name”: vol1,
            “OntapConfiguration”: {
                   “FlexCacheEndpointType”: “NONE”,
                   “JunctionPath”: “/vol1”,
                   “SizeInMegabytes”: 100000,
                   “StorageEfficiencyEnabled”: true,
                   “StorageVirtualMachineId”: “svm-0ed1d714019426ca9”,
                   “StorageVirtualMachineRoot”: false,
                   “TieringPolicy”: {
                    “Name”: “ALL”
                   },
                   “OntapVolumeType”: “DP”,
                   “SnapshotPolicy”: “default”,
                   “CopyTagsToBackups”: false,
                  },
                  “ResourceARN”: “arn:aws:fsx:us-east-1:630831496844:volume/
fs-08ac75f715c6aec76/fsvol-094c015af930790fa”,
                  “VolumeId”: “fsvol-094c015af930790fa”,
                  “VolumeType”: “ONTAP”,
                  “AdministrativeActions”: [
                         {
                          “AdministrativeActionType”: “DOWNLOAD_DATA_FROM_BACKUP”,
                          “RequestTime”: 1685729972.069,
                          “Status”: “PENDING”
                         }
                  ]
    }
```

Once Amazon FSx loads all of the file metadata onto the restored volume, these fields have the following values:

- `"LifeCycle": "CREATED"` – indicates that the volume is ready to be mounted.
- `"OntapVolumeType": "DP"` – indicates that the volume is read-only while the file data is downloading.
- `"ProgressPercent` –shows the percentage of file data that is loaded onto the volume.
- `"Status": "IN_PROGRESS"` – downloading the file data to the volume is in progress.

At this stage in the restore process you can mount the volume with read-only access to all the data in the backup that you are restoring.

When Amazon FSx has completed downloading all the file data onto the new volume, clients have full read-write access if this is `RW` volume. The indicators have the following values:

- `"LifeCycle": "CREATED"` – unchanged
- `"OntapVolumeType": "RW"` – indicates that clients have full read-write access.
- `"Status": "COMPLETED"` – indicates that the restore is complete.

If the restore process fails, the `AdminstrativeAction > Status` will have a value of `FAILED`. An error message is provided in the `FailureDetails` object. For more information, see AdministrativeActionFailureDetails in the Amazon FSx API Reference

Deleting backups

You can delete both automatic daily backups and user-initiated backups of your volumes using the Amazon FSx console, Amazon FSx API, or AWS Command Line Interface (AWS CLI). Deleting a backup is a permanent, unrecoverable action. Any data in a deleted backup is also deleted. Do not delete a backup unless you're sure you won't need that backup again in the future. You can't delete a backup if the source volume is offline.

You can delete a volume while it is being restored from a backup on all FSx for ONTAP file systems. Deleting a volume during the restore effectively cancels the in-progress restore operation.

> **Note**
>
> Amazon FSx doesn't support deleting the most recent `AVAILABLE` backup of an ONTAP volume unless all other backups of the volume have been deleted.

To delete backups created using AWS Backup, see Deleting backups in the AWS Backup Developer Guide.

To delete a backup (console)

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.

2. From the console dashboard, choose **Backups** from the left side navigation.
3. Choose the backup that you want to delete from the **Backups** table, and then choose **Delete backup**.
4. In the **Delete backups** dialog box that opens, confirm that the ID of the backup shown is the backup that you want to delete.
5. Confirm that the check box is checked for the backup that you want to delete.
6. Choose **Delete backups**.

Your backup and all included data are now permanently and irrecoverably deleted.

To delete a backup (CLI)

- Use the delete-backup CLI command or the equivalent DeleteBackup API action to delete an FSx for ONTAP volume backup, as shown in the following example.

```
$ aws fsx delete-backup --backup-id backup-a0123456789abcdef
```

The system response includes the ID of the backup being deleted, and its lifecycle status with a value of `DELETED`, indicating that the request was successful.

```
{
    "BackupId": "backup-a0123456789abcdef",
    "Lifecycle": "DELETED"
}
```

Protecting your data with snapshots

A *snapshot* is a read-only image of an Amazon FSx for NetApp ONTAP volume at a point in time. Snapshots offer protection against accidental deletion or modification of files in your volumes. With snapshots, your users can easily view and restore individual files or folders from an earlier snapshot to undo changes, recover deleted content, and compare file versions.

A snapshot contains the data that has changed since the last snapshot which consumes the file system's SSD storage capacity. Snapshots are not included in any volume backups. Snapshots are enabled by default on your volumes using the `default` snapshot policy. Snapshots are stored in the `.snapshot` directory at the root of a volume. You can store a maximum of 1,023 snapshots

per volume at any point in time. Once you reach this limit, you must delete an existing snapshot before a new snapshot of your volume can be created.

Topics

- Snapshot policies
- Restoring files from snapshots
- Viewing the common snapshot
- Updating your volume's snapshot reserve
- Disabling automatic snapshots
- Deleting snapshots
- Deleting snapshots
- Snapshot reserve

Snapshot policies

The snapshot policy defines how the system creates snapshots for a volume. The policy specifies when to create snapshots, how many copies to retain, and how to name them. There are three built-in snapshot policies for FSx for ONTAP:

- `default`
- `default-1weekly`
- none

By default, every volume is associated with the file system's `default` snapshot policy. We recommend using this policy for most workloads.

The `default` policy automatically creates snapshots on the following schedule, with the oldest snapshot copies deleted to make room for newer copies:

- A maximum of six hourly snapshots taken five minutes past the hour.
- A maximum of two daily snapshots taken Monday through Saturday at 10 minutes after midnight.
- A maximum of two weekly snapshots taken every Sunday at 15 minutes after midnight.

> **Note**
>
> Snapshot times are based on the file system's time zone, which defaults to Coordinated Universal Time (UTC). You can set an FSx for ONTAP file system's time zone by using the `timezone -timezone time_zone` ONTAP CLI command. For more information about accessing the ONTAP CLI, see Using the NetApp ONTAP CLI.

The `default-1weekly` policy works in the same way as the `default` policy, except that it only retains one snapshot from the weekly schedule.

The none policy doesn't take any snapshots. You can assign this policy to volumes to prevent automatic snapshots from being taken.

You can also create a custom snapshot policy using the ONTAP CLI or REST API. For more information, see Create a Snapshot Policy in the *NetApp ONTAP Product Documentation*. You can choose a snapshot policy while creating or updating a volume in the Amazon FSx console, the AWS CLI, or the Amazon FSx API. For more information, see Creating volumes and Updating volumes.

Restoring files from snapshots

Using the snapshots on your Amazon FSx file system, you can quickly restore previous versions of individual files or folders.

If you use Linux and macOS clients, you can view snapshots in the `.snapshot` directory at the root of a volume. If you use Windows clients, you can view snapshots in the `Previous Versions` tab of Windows Explorer (when right-clicking on a file or folder).

To restore a file from a snapshot (Linux and macOS clients)

1. If the original file still exists and you do not want it overwritten by the file in a snapshot, then use your Linux or macOS client to rename the original file or move it to a different directory.
2. In the `.snapshot` directory, locate the snapshot that contains the version of the file that you want to restore.
3. Copy the file from the `.snapshot` directory to the directory in which the file originally existed.

To restore a file from a snapshot (Windows clients)

Users on Windows clients can restore files to previous versions using the familiar Windows File Explorer interface.

1. To restore a file, users choose the file to restore, then choose **Restore previous versions** from the context (right-click) menu.
2. Users can then view and restore a previous version from the **Previous Versions** list.

Data in snapshots is read-only. If you want to make modifications to files and folders listed in the **Previous Versions** tab, you must save a copy of the files and folders that you want to modify to a writable location and make modifications to the copies.

Viewing the common snapshot

The common snapshot is used to maintain incrementality between your backups. This procedure explains how to identity the common snapshot on your volume.

To view a volume's common snapshot

- To determine which snapshot is a volume's common snapshot, use the **volume snapshot show** ONTAP CLI command.

  ```
  volume snapshot show -volume volume-name
  ```

  In the output, the name of the common snapshot has the format of `backup-id`, where *id* is a 17 digit alphanumeric string, as shown in the following example:

  ```
  FsxIdabc12345::> volume snapshot show -volume test_vol
                                    ---Blocks---
  Vserver Volume    Snapshot                    Size     Total% Used%
  -------- -------- -------------------------- -------- ------ -----
  dest-svm test_vol
                   snap1                        144KB    0%     3%
                   snap2                        832KB    0%    16%
           --->    backup-abcdef0123456789a    4.87MB    0%    53% <---
                   weekly.2024-05-26_0015      5.02MB    0%    54%
                   weekly.2024-06-02_0015      2.22MB    0%    34%
                   daily.2024-06-04_0010        284KB    0%     6%
                   daily.2024-06-05_0010       4.29MB    0%    50%
  ```

```
                    hourly.2024-06-05_0705       168KB     0%      4%
8 entries were displayed.
```

> **Important**
>
> Do not delete the common snapshot on the volume because it is used to maintain incrementality between your backups. Deleting a volume's common snapshot will cause the next backup to be a full backup of the volume instead of an incremental backup.

Updating your volume's snapshot reserve

You can change the amount of snapshot reserve on a volume using the NetApp ONTAP CLI or API, described in the following procedure.

1. To access the ONTAP CLI, establish an SSH session on the management port of the Amazon FSx for NetApp ONTAP file system or SVM by running the following command. Replace *management_endpoint_ip* with the IP address of the file system's management port.

   ```
   [~]$ ssh fsxadmin@management_endpoint_ip
   ```

   For more information, see Managing file systems with the ONTAP CLI.

2. Use the volume modify ONTAP CLI command to change the percent of disk space used for the Snapshot copy reserve. Replace the following placeholder values with your data:

   - *svm_name* — use your SVM's name.
   - *vol_name* — use your volume's name.
   - *percent* — the percent of disk space you want to reserve for Snapshot copies.

   ```
   ::> volume modify -vserver svm_name -volume vol_name -percent-snapshot-
   space percent
   ```

   The following example changes the snapshot reserve for vol1 to 25% of the volume's storage capacity.

```
::> volume modify -vserver vs0 -volume vol1 -percent-snapshot-space 25
```

Disabling automatic snapshots

Automatic snapshots are enabled by the default snapshot policy for volumes in your FSx for ONTAP file system. If you don't need snapshots of your data (for example, if you're using test data), you can disable snapshots by setting the volume's snapshot policy to none using the AWS Management Console, AWS CLI and API, and the ONTAP CLI, as described in the following procedures.

To disable automatic snapshots (AWS console)

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. Navigate to **File systems** and choose the ONTAP file system that you want to update a volume for.
3. Choose the **Volumes** tab.
4. Choose the volume that you want to update.
5. For **Actions**, choose **Update volume**.

   The **Update volume** dialog box displays with the volume's current settings.
6. For **Snapshot policy**, choose **None**.
7. Choose **Update** to update the volume.

To disable automatic snapshots (AWS CLI)

- Use the update-volume AWS CLI command (or the equivalent UpdateVolume API command), to set the `SnapshotPolicy` to none, as shown in the following example.

```
aws fsx update-volume \
    --volume-id fsvol-1234567890abcdefa \
    --name new_vol \
    --ontap-configuration CopyTagsToBackups=true,JunctionPath=/new_vol, \
           SizeInMegabytes=2048,SnapshotPolicy=none, \
           StorageEfficiencyEnabled=true, \
           TieringPolicy=all
```

To disable automatic snapshots (ONTAP CLI)

Set the volume's snapshot policy to use the none default policy to turn off automatic snapshots.

1. Use the volume snapshot policy show ONTAP CLI command to show the none policy.

```
::> snapshot policy show -policy none

Vserver: FsxIdabcdef01234567892
                         Number of Is
Policy Name              Schedules Enabled Comment
------------------------ --------- ------- ---------------------------------
none                               0 false   Policy for no automatic snapshots.
    Schedule               Count     Prefix                 SnapMirror Label
    ---------------------- -----     ---------------------- ------------------
    -                          -     -                      -
```

2. Use the volume modify ONTAP CLI command to set the volume's snapshot policy to none to disable automatic snapshots. Replace the following placeholder values with your data:

   - *svm_name* — use your SVM's name.
   - *vol_name* — use your volume's name.

   When prompted to continue, enter **y**.

```
::> volume modify -vserver svm_name -volume vol_name -snapshot-policy none

Warning: You are changing the Snapshot policy on volume "vol_name" to "none".
 Snapshot copies on this volume
        that do not match any of the prefixes of the new Snapshot policy will not
 be deleted. However, when
        the new Snapshot policy takes effect, depending on the new retention
 count, any existing Snapshot copies
        that continue to use the same prefixes might be deleted. See the 'volume
 modify' man page for more information.
Do you want to continue? {y|n}: y
Volume modify successful on volume vol_name of Vserver svm_name.
```

Deleting snapshots

Snapshots consume storage capacity only for the data on a volume that has changed since the last snapshot. For this reason, if your workload writes data rapidly, snapshots from old data can take up a significant amount of a volume's storage capacity.

For example, the `volume show-space` ONTAP CLI command output shows 140 KB of `User Data`. However, the volume had 9.8 GB of `User Data` before the user data was deleted. Even if you've deleted the files from your volume, a snapshot might still reference old user data. Because of this, `Snapshot Reserve` and `Snapshot Spill` in the prior example take up a total of 9.8 GB of space, even though there is virtually no user data on the volume.

To free up space on volumes, you can delete older snapshots that you no longer need. Because snapshots are incremental, you do not reclaim the amount of storage equal to the size of the snapshot when you delete it. You can see the amount of storage you can reclaim when deleting a snapshot by using the volume snapshot compute-reclaimable -vserver ONTAP CLI command, using your data to replace *`svm_name`*, *`vol_name`*, and *`snapshot_name`*.

```
fsid8970abc52::> volume snapshot compute-reclaimable -vserver svm_name -volume vol_name
 -snapshot snapshot_name
A total of 667648 bytes can be reclaimed.
```

You can delete snapshots either by creating a snapshot auto-delete policy or by manually deleting snapshots. Deleting a snapshot deletes the changed data stored on the snapshot.

Deleting snapshots

Use the **volume snapshot delete** ONTAP CLI command to manually delete snapshots, replacing the following placeholder values with your data:

- Replace *`svm_name`* with the name of the SVM that the volume is created on.
- Replace *`vol_name`* with name of the volume.
- Replace *`snapshot_name`* with the name of the snapshot. This command supports wildcard characters (*) for *`snapshot_name`*. Therefore, you can delete all hourly snapshots, for example, by using `hourly*`.

Important

If you have Amazon FSx backups enabled, Amazon FSx retains a snapshot for the most recent Amazon FSx backup of each volume. Those snapshots are used to maintain incrementality between backups, and must not be deleted by using this method. For more information, see Viewing the common snapshot.

```
FsxIdabcdef01234567892::> volume snapshot delete -vserver svm_name -volume vol_name -
snapshot snapshot_name
```

Creating a Snapshot autodelete policy

You can create a policy to automatically delete snapshots when the amount of available space in your volume is running low. Use the volume snapshot autodelete modify ONTAP CLI command to establish an autodelete policy for a volume.

When using this command, use your data to replace the following placeholder values:

- Replace *svm_name* with the name of the SVM that the volume is created on.
- Replace *vol_name* with name of the volume.

For `-trigger`, assign one of the following values:

- `volume` – Use `volume` if you want the threshold at which snapshots are deleted to correspond to a total used-volume capacity threshold. The used-volume capacity thresholds that trigger snapshot deletion are determined by the size of your volume, with the threshold scaling from 85–98 percent used capacity. Smaller volumes have a smaller threshold, and larger volumes have a larger one.
- `snap_reserve` – Use `snap_reserve` if you want snapshots to be deleted based on what can be held in your snapshot reserve.

```
::> volume snapshot autodelete modify -vserver svm_name -volume vol_name -enabled true
 -trigger [volume|snap_reserve]
```

For more information, see the volume snapshot autodelete modify command in the *NetApp ONTAP Documentation Center*.

Snapshot reserve

Snapshot copy reserve sets a specific percent of a volume's storage capacity for storing Snapshot copies, with a default value of 5 percent. The Snapshot copy reserve must have sufficient space allocated for the Snapshot copies, including volume backups. If the Snapshot copies exceeds the Snapshot reserve space, you must delete existing Snapshot copies from the active file system to recover the storage capacity for the use of the file system. You can also modify the percent of disk space that is allotted to Snapshot copies.

Whenever Snapshots consume more than 100% of the Snapshot reserve, they begin to occupy primary SSD storage space. This process is called Snapshot spill. When the Snapshots continue to occupy the active file system space, the file system is at risk of becoming full. If the file system becomes full due to Snapshot spill, you can create files only after you delete enough Snapshots.

When enough disk space is available for snapshots in the snapshot reserve, deleting files from the primary SSD tier frees disk space for new files, while the Snapshot copies that reference those files consume only the space in the Snapshot copy reserve.

Because there is no way to prevent Snapshots from consuming disk space greater than the amount reserved for them (the Snapshot reserve), it is important to reserve enough disk space for Snapshots so that the primary SSD tier always has space available to create new files or modify existing ones.

If a snapshot is created when the disks are full, deleting files from the primary SSD tier does not create any free space because all that data is also referenced by the newly created Snapshot. You must delete the Snapshot in order to free up storage in order to create or update any files.

You can modify the amount of Snapshot reserve on a volume using the NetApp ONTAP CLI. For more information, see Updating your volume's snapshot reserve.

Protecting your data with Autonomous Ransomware Protection

Autonomous Ransomware Protection (ARP) is a NetApp ONTAP AI-driven feature that monitors and protects your data against ransomware and malware attacks if your Windows or Linux clients become compromised. Using machine learning, ARP becomes familiar with your FSx for ONTAP file systems to proactively detect abnormal activity. ARP is available for all new and existing FSx for ONTAP file systems in all AWS Regions where Amazon FSx for NetApp ONTAP is available.

How ARP works

You can enable ARP on a per-volume basis or by default on all new volumes in an SVM using the ONTAP CLI or REST API. For more information about enabling ARP, see Enabling Autonomous Ransomware Protection.

Because ARP's AI is trained on a comprehensive dataset, it doesn't need a learning period for ARP to run on FlexVol volumes, and therefore starts in active mode right away. ARP AI also comes with an automatic update capability to ensure constant protection and resilience against the latest threats. In active mode, ARP monitors incoming data and activity on the volume to identify potential ransomware and malware attacks. For more information, see What ARP looks for. If ARP detects any abnormal activity, an ONTAP snapshot is automatically created to help you recover your data as close as possible to the time of the potential attack. The snapshot will have a prefix of `Anti_ransomware_backup`, so it's easy to identify. If it's determined that the attack probability is moderate, ONTAP will generate an Events Management System (EMS) message for you to review. For more information, see How to respond to a suspected attack with ARP and Understanding EMS alerts for Autonomous Ransomware Protection.

The performance overhead for ARP is minimal for most workloads. If your volumes have read-intensive workloads, NetApp recommends protecting no more than 150 such volumes per file system. If you exceed this number, the IOPS for that workload might drop by up to 4%. If your volumes have write-intensive workloads, NetApp recommends protecting no more than 60 such volumes per file system. Otherwise, the IOPS for that workload might drop by up to 10%. For more information about performance, see Amazon FSx for NetApp ONTAP performance.

There is no additional cost for enabling ARP on your FSx for ONTAP file system.

What ARP looks for

ARP looks for signs that your Windows or Linux clients are compromised. In particular, ARP looks for the following types of activity on the volume:

- Changes in entropy, which means differences in the randomness of data in a file.
- Changes in file extension types, which means that the new extension isn't consistent with the normally used extension type. The default is 20 files with file extensions not previously observed in the volume.
- Changes in file IOPS, which means a surge in abnormal volume activity with encrypted data.

You can modify the ransomware detection parameters for your volume if necessary. For example, if your volume hosts many types of file extensions. For more information, see Manage ONTAP Autonomous Ransomware Protection attack detection parameters in the NetApp Documentation Center.

> **Note**
>
> ARP doesn't prevent rogue administrators with credentials from accessing your FSx for ONTAP file system. AWS recommends a layered security approach including AWS Backup, ONTAP snapshots, and SnapLock.

How to respond to a suspected attack with ARP

If ARP detects an attack, it will generate a snapshot that can be used as a recovery point. The snapshot is locked and can't be deleted by normal means. Depending on the severity of the attack, it will also generate an EMS alert that shows the affected volume, the attack probability, and the attack timeline. If you want to receive alerts for the creation of a new snapshot or the observation of a new file extension on your volume, you can configure ARP to send these alerts. For more information, see Configure ARP alerts in the NetApp Documentation Center.

You can generate a report to view detailed information on a suspected attack. After you review the report, you can tell ONTAP if the alert was generated by a false positive or a suspected attack. If you label the alert as a suspected attack, you should determine the scope of the attack and then recover data from the ARP-created snapshot. If you label the attack as a false positive, the ARP-created snapshot is automatically deleted. For more information, see Responding to Autonomous Ransomware Protection alerts.

We recommend monitoring your file system's EMS messages and the status of your volumes in the ONTAP CLI and REST API. For more information about EMS messages for ARP, see Understanding EMS alerts for Autonomous Ransomware Protection.

Topics

- Enabling Autonomous Ransomware Protection
- Responding to Autonomous Ransomware Protection alerts
- Understanding EMS alerts for Autonomous Ransomware Protection

Enabling Autonomous Ransomware Protection

The following procedures explain how to use the ONTAP CLI to enable Autonomous Ransomware Protection (ARP) active mode as well as how to verify that ARP is enabled. For more information about ARP, see How ARP works.

Enabling ARP in active mode

To enable ARP in active mode on an existing volume using the ONTAP CLI

- Run the following command. Replace *vol_name* and *svm_name* with your own information.

  ```
  security anti-ransomware volume enable -volume vol_name -vserver svm_name
  ```

  For more information about this command, see security anti-ransomware volume enable in the NetApp documentation center.

Enabling ARP by default at the SVM level

To enable ARP by default on an existing SVM using the ONTAP CLI

- Run the following command. Replace *svm_name* with your own information.

  ```
  vserver modify -vserver svm_name -anti-ransomware-default-volume-state dry-run
  ```

  For more information about this command, see vserver modify in the NetApp documentation center.

Verifying ARP's status

To verify the status of ARP using the ONTAP CLI

- Run the following command.

  ```
  security anti-ransomware volume show
  ```

  For more information about this command, see security anti-ransomware volume show in the NetApp documentation center.

You can temporarily suspend (and then resume) ARP if you're anticipating heavy workload events. For more information, see Pause ONTAP Autonomous Ransomware Protection to exclude workload events from analysis in the NetApp Documentation Center.

Responding to Autonomous Ransomware Protection alerts

The following procedures explain how to use the ONTAP CLI to view Autonomous Ransomware Protection (ARP) alerts, generate attack reports, and take action on reports. For more information about how ARP detects and responds to attacks, see What ARP looks for and How to respond to a suspected attack with ARP.

Viewing ARP alerts

To view an ARP alert on a volume using the ONTAP CLI

- Run the following command. Replace *svm_name* and *vol_name* with your own information.

  ```
  security anti-ransomware volume show -vserver svm_name -volume vol_name
  ```

  After running the command, you'll see output similar to the following example:

  ```
  Vserver Name: fsx
  Volume Name: vol1
  State: enabled
  Attack Probability: moderate
  Attack Timeline: 9/14/2021 01:03:23
  Number of Attacks: 1
  ```

  For more information about this command, see `security anti-ransomware volume show` in the NetApp documentation center.

Generating ARP reports

To generate ARP reports using the ONTAP CLI

- Run the following command. Replace *vol_name* and */file_location/* with your own information. After you generate the report, you can view it on a client system.

```
security anti-ransomware volume attack generate-report -volume vol_name -dest-
path /file_location/
```

For more information about this command, see security anti-ransomware volume attack generate-report in the NetApp documentation center.

Taking action on ARP reports

To take action on a false positive attack from an ARP report using the ONTAP CLI

- Run the following command. Replace *svm_name*, *vol_name*, and *[extension identifiers]* with your own information.

```
security anti-ransomware volume attack clear-suspect -vserver svm_name -
volume vol_name [extension identifiers] -false-positive true
```

For more information about this command, see security anti-ransomware volume attack clear-suspect in the NetApp documentation center.

> **Note**
>
> When you mark an alert as a false positive, it updates the ransomware profile. After doing so, you won't receive an alert about that particular scenario again.

To take action on a potential attack from an ARP report using the ONTAP CLI

- Run the following command. Replace *svm_name*, *vol_name*, and *[extension identifiers]* with your own information.

```
security anti-ransomware volume attack clear-suspect -vserver svm_name -
volume vol_name [extension identifiers] -false-positive false
```

For more information about this command, see security anti-ransomware volume attack clear-suspect in the NetApp documentation center.

Understanding EMS alerts for Autonomous Ransomware Protection

You can use NetApp ONTAP's Events Management System (EMS) to monitor events related to ARP including potential attacks. For more information about ARP and how it detects attacks, see How ARP works and What ARP looks for.

The following table contains all of the alerts related to ARP. For more information about EMS, see Monitoring FSx for ONTAP EMS events.

EMS message name	EMS message description
`arw.analytics.ext.report`	This message occurs when anti-ransomware analytics generate or update the **suspicious file extensions** report for a volume.
`arw.analytics.high.entropy`	This message occurs when the number of high entropy data log messages (pertaining to ransomware detection and analysis) cross the predefined threshold for a volume.
`arw.analytics.probability`	This message occurs when an anti-rans omware attack probability has changed from `low` to `high` on a volume.
`arw.analytics.report`	This message occurs when an anti-rans omware analytics report is generated or updated for a volume.
`arw.analytics.suspects`	This message occurs when a list of suspects generated by anti-ransomware analytics grows to a point where further investigation is needed.
`arw.new.file.extn.seen`	This message occurs when a new file extension is observed in an anti-ransomware enabled volume. Its purpose is to promptly notify the user about the observed extension, which enables timely investigation.

EMS message name	EMS message description
`arw.snapshot.created`	This message occurs when a new ARP snapshot is created in an anti-ransomware enabled volume. Additionally, it provides information about the reason why the snapshot was created.
`arw.volume.state`	This message occurs when the anti-rans omware state of a volume is changed.
`arw.vserver.state`	This message occurs when the anti-rans omware state of an SVM is changed.

Protecting your data with SnapLock

SnapLock is a feature that allows you to protect your files by transitioning them to a write once, read many (WORM) state, which prevents modification or deletion for a specified retention period. You can use SnapLock to meet regulatory compliance, to protect business-critical data from ransomware attacks, and to provide an additional layer of protection for your data against alteration or deletion.

Amazon FSx for NetApp ONTAP supports the Compliance and Enterprise modes of retention with SnapLock. For more information, see Understanding SnapLock Compliance and Understanding SnapLock Enterprise.

You can create SnapLock volumes on FSx for ONTAP file systems created on or after July 13, 2023. Existing file systems will get SnapLock support during an upcoming weekly maintenance window.

Topics

- How SnapLock works
- Understanding SnapLock Compliance
- Understanding SnapLock Enterprise
- Understanding the SnapLock retention period
- Committing files to WORM state

How SnapLock works

SnapLock can help you meet regulatory and governance purposes by preventing your files from being deleted, changed, or renamed. When you create a SnapLock volume, you commit your files to write once, read many (WORM) storage and set retention periods for the data. Your files can be stored in a non-erasable, non-writable state for a designated period, or indefinitely.

> **Important**
>
> You must specify whether a volume will use SnapLock settings at the time of creation. A non-SnapLock volume can't be converted to a SnapLock volume after creation.

Retention modes

SnapLock has two retention modes: Compliance and Enterprise. Amazon FSx for NetApp ONTAP supports both of them. They have different use cases and some of the features differ, but they both protect your data from modification or deletion using the WORM model. The following table explains some of the similarities and differences between these retention modes.

SnapLock feature	Understanding SnapLock Compliance	Understanding SnapLock Enterprise
Description	Files transitioned to WORM on a Compliance volume can't be deleted until their retention periods expire.	Files transitioned to WORM on an Enterprise volume can be deleted by authorized users before their retention periods expire using privileged delete.
Use cases	• To address government or industry-specific mandates such as SEC Rule 17a-4(f), FINRA Rule 4511, and CFTC Regulation 1.31. • To protect against ransomware attacks.	• To advance an organization's data integrity and internal compliance. • To test retention settings before using SnapLock Compliance.

SnapLock feature	Understanding SnapLock Compliance	Understanding SnapLock Enterprise
Autocommit	Yes	Yes
Event-based retention (EBR)[1]	Yes	Yes
Legal Hold[1]	Yes	No
Using privileged delete	No	Yes
Volume-append mode	Yes	Yes
SnapLock audit log volumes	Yes	Yes

Note

[1]EBR and Legal Hold operations are supported in the ONTAP CLI and REST API.

Note

FSx for ONTAP supports tiering data to the capacity pool on all SnapLock volumes, regardless of the SnapLock type. For more information, see Volume data tiering.

SnapLock administrator

You must have SnapLock administrator privileges to perform certain actions on SnapLock volumes. SnapLock administrator privileges are defined in the `vsadmin-snaplock` role in the ONTAP CLI. You must be a cluster administrator to create a storage virtual machine (SVM) administrator account with the SnapLock administrator role.

You can perform the following actions with the `vsadmin-snaplock` role in the ONTAP CLI:

- Manage your own user account, local password, and key information
- Manage volumes, except moving volumes
- Manage quotas, qtrees, snapshot copies, and files

- Perform SnapLock actions, including privileged delete and Legal Hold
- Configure Network File System (NFS) and Server Message Block (SMB) protocols
- Configure Domain Name System (DNS), Lightweight Directory Access Protocol (LDAP), and Network Information Service (NIS) services
- Monitor jobs

The following procedure details how to create a SnapLock administrator in the ONTAP CLI. You must be logged in as a cluster administrator on a secure connection, such as Secure Shell Protocol (SSH) to perform this task.

To create an SVM administrator account with the vsadmin-snaplock role in the ONTAP CLI

- Run the following command. Replace *SVM_name* and *SnapLockAdmin* with your own information.

```
cluster1::> security login create -vserver SVM_name -user-or-group-
name SnapLockAdmin -application ssh -authentication-method password -role vsadmin-
snaplock
```

For more information, see ONTAP roles and users.

SnapLock audit log volumes

A SnapLock audit log volume contains SnapLock audit logs, which contain timestamps of events such as when a SnapLock administrator was created, when privileged delete operations were executed, or when a Legal Hold was placed on files. The SnapLock audit log volume is a non-erasable record of events.

You must create a SnapLock audit log volume in the same SVM as the SnapLock volume for the following actions:

- To turn on or turn off privileged delete on a SnapLock Enterprise volume.
- To apply Legal Hold on a file in a SnapLock Compliance volume.

Warning

- The minimum retention period for a SnapLock audit log volume is six months. Until this retention period expires, the SnapLock audit log volume and the SVM and file system that are associated with it can't be deleted even if the volume was created in SnapLock Enterprise mode.
- If a file is deleted using privileged delete and its retention period is longer than the retention period of the volume, then the audit log volume inherits the file's retention period. For example, if a file that has a retention period of 10 months is deleted using privileged delete and the retention period of the audit log volume is six months, the retention period of the audit log volume is extended to 10 months.

You can have only one active SnapLock audit log volume in an SVM, but it can be shared by multiple SnapLock volumes in the SVM. To mount a SnapLock audit log volume successfully, set the junction path to `/snaplock_audit_log`. No other volumes can use this junction path, including volumes that aren't audit log volumes.

You can find SnapLock audit logs in the `/snaplock_log` directory under the root of the audit log volume. Privileged delete operations are logged in the `privdel_log` subdirectory. Legal Hold begin and end operations are logged in `/snaplock_log/legal_hold_logs/`. All other logs are stored in the `system_log` subdirectory.

You can create a SnapLock audit log volume with the Amazon FSx console, the AWS CLI, the Amazon FSx API, and the ONTAP CLI and REST API.

Note

A data protection (DP) volume can't be used as a SnapLock audit log volume.

To turn on the SnapLock audit log volume with the Amazon FSx API, use `AuditLogVolume` in the `CreateSnaplockConfiguration`. In the Amazon FSx console, for **Audit log volume**, choose **Enabled**. Make sure that the **Junction path** is set to `/snaplock_audit_log`.

Accessing your data in a SnapLock volume

You can use open file protocols such as NFS and SMB to access your data in a SnapLock volume. There is no performance impact from writing data to a SnapLock volume or from reading data that's protected by WORM.

You can copy files across SnapLock volumes with NFS and SMB, but they won't retain their WORM properties on the destination SnapLock volume. You must recommit the copied files to WORM to prevent them from being modified or deleted. For more information, see Committing files to WORM state.

You can also replicate SnapLock data with SnapMirror, but the source and destination volumes must be SnapLock volumes with the same retention mode (for example, both must be Compliance or Enterprise).

SnapLock and SSD capacity decrease operations

Consider these points about SSD decreases before creating a SnapLock volume:

- Amazon FSx will reject SSD capacity decrease requests on file systems that contain SnapLock volumes.
- You can't create SnapLock volumes during an SSD capacity decrease operation.

These limitations exist because ONTAP enforces a minimum retention period of 6 months for the SnapLock audit log volume, which would prevent file system deletion during that period if a SnapLock volume were moved as part of an SSD decrease operation.

If you need to decrease SSD capacity on a file system with SnapLock volumes, you would need to migrate your data to a new file system with smaller SSD capacity. For more information about SSD capacity decrease operations, including limitations and considerations, see Updating file system SSD storage and IOPS.

Understanding SnapLock Compliance

This section describes use cases and considerations for the SnapLock Compliance retention mode.

You might choose the Compliance retention mode for the following use cases.

- You can use SnapLock Compliance to address government or industry-specific mandates such as SEC Rule 17a-4(f), FINRA Rule 4511, and CFTC Regulation 1.31. SnapLock Compliance on

Amazon FSx for NetApp ONTAP was assessed for these mandates and regulations by Cohasset Associates. For more information, see the *Compliance Assessment Report for Amazon FSx for NetApp ONTAP*.

- You can use SnapLock Compliance to complement or enhance a comprehensive data protection strategy to combat ransomware attacks.

Here are some important items to consider about the SnapLock Compliance retention mode.

- After a file is transitioned to the write once, read many (WORM) state on a SnapLock Compliance volume, it can't be deleted before its retention period expires by any user.
- A SnapLock Compliance volume can only be deleted when the retention periods of all WORM files on the volume have expired, and the WORM files have been deleted from the volume.
- You can't rename a SnapLock Compliance volume after creation.
- You can use SnapMirror to replicate WORM files, but the source volume and destination volume must have the same retention mode (for example, both must be Compliance).
- A SnapLock Compliance volume can't be converted to a SnapLock Enterprise volume, and the reverse.

Understanding SnapLock Enterprise

This section describes use cases and considerations for the SnapLock Enterprise retention mode.

You might choose the SnapLock Enterprise retention mode for the following use cases.

- You can use SnapLock Enterprise to authorize only specific users to delete files.
- You can use SnapLock Enterprise to advance your organization's data integrity and internal compliance.
- You can use SnapLock Enterprise to test retention settings before using SnapLock Compliance.

Here are some important items to consider about the SnapLock Enterprise retention mode.

- You can use SnapMirror to replicate WORM files, but the source volume and destination volume must have the same retention mode (for example, both must be Enterprise).
- A SnapLock volume can't be converted from Enterprise to Compliance, or from Compliance to Enterprise.

- SnapLock Enterprise doesn't support Legal Hold.

Using privileged delete

One of the key differences between SnapLock Enterprise and SnapLock Compliance is that a SnapLock administrator can turn on privileged delete on a SnapLock Enterprise volume to allow a file to be deleted before the file's retention period expires. The SnapLock administrator is the only user who can delete files from a SnapLock Enterprise volume that has active retention policies placed on it. For more information, see SnapLock administrator.

You can turn on or turn off privileged delete with the Amazon FSx console, the AWS CLI, the Amazon FSx API, and the ONTAP CLI and REST API. To turn on privileged delete, you must first create a SnapLock audit log volume in the same SVM as the SnapLock volume. For more information, see SnapLock audit log volumes.

To turn on privileged delete with the Amazon FSx API, use `PrivilegedDelete` in the `CreateSnaplockConfiguration`. In the Amazon FSx console, for **Privileged Delete**, choose **Enabled**.

> **Note**
>
> You can't issue a privileged delete command to delete a write once, read many (WORM) file that has an expired retention period. You can issue a normal delete operation after the retention period expires.

You can opt to turn off privileged delete permanently, but this action is irreversible. If privileged delete is permanently turned off, you don't need to have a SnapLock audit log volume associated with the SnapLock Enterprise volume.

To permanently turn off privileged delete with the Amazon FSx API, use `PrivilegedDelete` in the `CreateSnaplockConfiguration`. In the Amazon FSx console, for **Privileged Delete**, choose **Permanently disabled**.

Bypassing SnapLock Enterprise mode

If you are using the Amazon FSx console or Amazon FSx API, you must have the IAM `fsx:BypassSnapLockEnterpriseRetention` permission to delete a SnapLock Enterprise volume that contains WORM files with active retention policies.

For more information, see Deleting SnapLock volumes.

Understanding the SnapLock retention period

When you create a SnapLock volume, you can set a default retention period for the volume, or you can set the retention period for write once, read many (WORM) files explicitly. During the retention period, you can't delete or modify WORM-protected files. The retention period is used to calculate the retention time. For example, if you transition a file to WORM on July 14, 2023 at midnight and set the retention period to five years, then the retention time would be until July 14, 2028 at midnight.

For more information about WORM, see Committing files to WORM state.

Retention period policies

The retention period is determined by values that you assign to the following parameters:

- Default retention – The default retention period that's assigned to a WORM file if you don't provide an explicit retention period for it.
- Minimum retention – The shortest retention period that can be assigned to a WORM file.
- Maximum retention – The longest retention period that can be assigned to a WORM file.

> **Note**
>
> Even after the retention period expires, you can't modify a WORM file. You can only delete it or set a new retention period to turn on WORM protection again.

You can specify the retention period using several different units of time. The following table lists the specific ranges that are supported.

Type	Value	Notes
Seconds	0 - 65,535	
Minutes	0 - 65,535	
Hours	0 - 24	

Type	Value	Notes
Days	0 - 365	
Months	0 -12	
Years	0 - 100	
Infinite	-	Retains the files forever. Available for **Default retention**, **Maximum retention**, and **Minimum retention**.
Unspecified[1]	-	Retains the files until you set a retention period. Available for **Default retention** only.

Note

[1]When you transition files to WORM with an unspecified retention period, they are given the minimum retention period that is configured for the SnapLock volume. When you transition the WORM-protected files to an absolute retention time, the new retention period must be greater than the minimum period that you set on the files previously.

Expired retention period

After a WORM file's retention period expires, you can delete the file or set a new retention period to turn WORM protection back on. WORM files aren't automatically deleted after their retention period expires. You still can't modify the content of a WORM file, even after its retention period has expired.

Setting the retention period of a SnapLock volume

You can set the retention period of a SnapLock volume with the Amazon FSx console, the AWS CLI, the Amazon FSx API, and the ONTAP CLI and REST API.

To set the retention period with the Amazon FSx API, use the `SnaplockRetentionPeriod` configuration. In the Amazon FSx console, for **Retention period**, enter values for **Default retention**, **Minimum retention**, and **Maximum retention**. Then choose a corresponding **Unit** for each.

Committing files to WORM state

This section discusses how you can transition your files to a write once, read many (WORM) state. It also discusses volume-append mode, which is a way to write data incrementally to WORM-protected files.

Autocommit

You can use autocommit to transition files to WORM if they haven't been modified for a period of time that you specify. You can turn on autocommit with the Amazon FSx console, the AWS CLI, the Amazon FSx API, and the ONTAP CLI and REST API.

You can specify an autocommit period between five minutes and 10 years. The following table lists the specific ranges that are supported.

Unit	Value
Minutes	5 - 65,535
Hours	1 - 65,535
Days	1 - 3,650
Months	1 - 120
Years	1 - 10

To turn on autocommit with the Amazon FSx API, use `AutocommitPeriod` in the `CreateSnaplockConfiguration`. In the Amazon FSx console, for **Autocommit**, choose **Enabled**. Then, for **Autocommit period**, enter a value and choose a corresponding **Autocommit unit**.

You can specify a value between 5 minutes and 10 years.

Volume-append mode

You can't modify existing data in a WORM-protected file. However, SnapLock allows you to maintain protection for existing data using WORM-appendable files. For example, you can generate log files or preserve audio or video streaming data while writing data to them incrementally. You can turn volume-append mode on or off with the Amazon FSx console, the AWS CLI, the Amazon FSx API, and the ONTAP CLI and REST API.

Requirements for updating volume-append mode

- The SnapLock volume must be unmounted.
- The SnapLock volume must be empty of snapshot copies and user data.

To turn on volume-append mode with the Amazon FSx API, use `VolumeAppendModeEnabled` in the `CreateSnaplockConfiguration`. In the Amazon FSx console, for **Volume append mode**, choose **Enabled**.

Event-based retention (EBR)

You can use event-based retention (EBR) to create custom policies with associated retention periods. For example, you can transition all files in a specified path to WORM and set the retention period for one year with the `snaplock event-retention policy create` and `snaplock event-retention apply` commands. When you use EBR, you must specify a volume, directory, or file. The retention period that you select when you create the EBR policy is applied to all files in the specified path.

EBR is supported by the ONTAP CLI and REST API.

> **Note**
>
> ONTAP doesn't support EBR with FlexGroup volumes.

The following procedures explain how to create, apply, modify, and delete an EBR policy. You must be a SnapLock administrator (have the `vsadmin-snaplock` role) to complete these tasks in the ONTAP CLI. For more information, see SnapLock administrator.

Creating an EBR policy in the ONTAP CLI

To create an EBR policy in the ONTAP CLI

- Run the following command. Replace *p1* and *"10 years"* with your own information.

```
vs1::> snaplock event-retention policy create -name p1 -retention-period "10 years"
```

Applying an EBR policy in the ONTAP CLI

To apply an EBR policy in the ONTAP CLI

- Run the following command. Replace *p1* and *slc* with your own information. You can add a path after the forward slash (/) if you want to specify a particular path for the EBR policy. Otherwise, this command applies the EBR policy to all files on the volume.

```
vs1::> snaplock event-retention apply -policy-name p1 -volume slc -path /
```

Modifying an EBR policy in the ONTAP CLI

To modify an EBR policy in the ONTAP CLI

- Run the following command. Replace *p1* and *"5 years"* with your own information.

```
vs1::> snaplock event-retention policy modify -name p1 -retention-period "5 years"
```

Deleting an EBR policy in the ONTAP CLI

To delete an EBR policy in the ONTAP CLI

- Run the following command. Replace *p1* with your own information.

```
vs1::> snaplock event-retention policy delete -name p1
```

Related commands in the *NetApp Documentation Center*:

- snaplock event-retention abort

- snaplock event-retention show-vservers
- snaplock event-retention show
- snaplock event-retention policy show

Legal Hold

You can retain WORM files for an indefinite period of time using Legal Hold. Legal Hold is generally used for litigation purposes. A WORM file that's subject to a Legal Hold can't be deleted until the Legal Hold is lifted.

Legal Hold is supported by the ONTAP CLI and REST API.

> **Note**
>
> ONTAP doesn't support Legal Hold with FlexGroup volumes.

The following procedures explain how to start and end a Legal Hold. You must be a SnapLock administrator (have the `vsadmin-snaplock` role) to complete these tasks in the ONTAP CLI. For more information, see SnapLock administrator.

Starting a Legal Hold on a file in a SnapLock Compliance volume with the ONTAP CLI

To start a Legal Hold on a file in a SnapLock Compliance volume with the ONTAP CLI

- Run the following command. Replace *litigation1*, *slc_vol1*, and *file1* with your own information.

```
vs1::> snaplock legal-hold begin -litigation-name litigation1 -volume slc_vol1 -
path /file1
```

Starting a Legal Hold on all files in a SnapLock Compliance volume with the ONTAP CLI

To start a Legal Hold on all files in a SnapLock Compliance volume with the ONTAP CLI

- Run the following command. Replace *litigation1* and *slc_vol1* with your own information.

```
vs1::> snaplock legal-hold begin -litigation-name litigation1 -volume slc_vol1 -
path /
```

Ending a Legal Hold on a file in a SnapLock Compliance volume with the ONTAP CLI

To end a Legal Hold on a file in a SnapLock Compliance volume with the ONTAP CLI

- Run the following command. Replace *litigation1*, *slc_vol1*, and *file1* with your own information.

```
vs1::> snaplock legal-hold end -litigation-name litigation1 -volume slc_vol1 -
path /file1
```

> **Note**
>
> We recommend that you monitor the `-operation-status` with the `snaplock legal-hold show` command when issuing a Legal Hold to make sure that it doesn't fail.

Ending a Legal Hold on all files in a SnapLock Compliance volume with the ONTAP CLI

To end a Legal Hold on all files in a SnapLock Compliance volume with the ONTAP CLI

- Run the following command. Replace *litigation1* and *slc_vol1* with your own information.

```
vs1::> snaplock legal-hold end -litigation-name litigation1 -volume slc_vol1 -
path /
```

> **Note**
>
> We recommend that you monitor the `-operation-status` with the `snaplock legal-hold show` command when issuing a Legal Hold to make sure that it doesn't fail.

Related commands in the *NetApp Documentation Center*:

- snaplock legal-hold abort
- snaplock legal-hold dump-files
- snaplock legal-hold dump-litigations
- snaplock legal-hold show

Replicating your data with FlexCache

FlexCache is NetApp ONTAP's remote caching capability that brings datasets closer to clients, improving access performance and reducing costs. It simplifies file distribution and reduces WAN costs. When you create a FlexCache volume, it initially copies only the metadata from the origin file system. This approach is faster and more space-efficient than a full data copy, consuming only a fraction of the storage capacity.

How FlexCache works

A FlexCache volume is a sparsely-populated cache that provides access to data stored in an origin volume. The cache can be located in a different, optionally remote, file system. Instead of copying all data from the origin volume, FlexCache copies data only as needed. FlexCache volumes are best suited for read-intensive workflows with infrequent data changes because any changes to the origin data require the cache to be refreshed.

You can use FlexCache with FSx for ONTAP in the following configurations:

Origin volume	FlexCache volume
On-premise NetApp ONTAP	FSx for ONTAP
FSx for ONTAP	On-premise NetApp ONTAP
FSx for ONTAP	FSx for ONTAP

FlexCache write modes

FlexCache volumes support two modes of operation for write operations: write-around mode and write-back mode.

In write-around mode, which is the default mode, writes are forwarded from the cache to the origin volume. The write operation isn't acknowledged to the client until after the data is committed to storage at the origin volume and the origin acknowledges the write back to the cache. Because each write must traverse the network between the cache and origin, this mode has higher latency than write-back mode.

In write-back mode, introduced in ONTAP 9.15.1, writes are committed to storage at the cache location and immediately acknowledged to the client. The data is then asynchronously written to the origin volume. This mode enables writes to perform at near-local speeds, which can significantly improve performance for distributed workloads.

Use write-back mode for write-heavy workloads that require low-latency cache writes. Use write-around mode for read-heavy workloads that are not latency-sensitive, or when your origin file system has more than 10 FlexCache origin volumes.

FlexCache volume creation overview

Creating a FlexCache volume consists of the following steps:

1. Gather source and destination logical interfaces (LIFs)
2. Establish cluster peering between the origin and cache file systems
3. Create a storage virtual machine (SVM) peering relationship
4. Create the FlexCache volume and select a write mode
5. Mount the FlexCache volume on your clients

For detailed instructions, see Creating a FlexCache.

Creating a FlexCache

Using the following procedures, you will create a FlexCache volume on an Amazon FSx for NetApp ONTAP file system, that is backed by an origin volume located in an on-premises NetApp ONTAP cluster.

Using the ONTAP CLI

You will use the ONTAP CLI to create and manage a FlexCache configuration on your FSx for ONTAP file system.

The commands in these procedures use the following aliases for the cluster, SVM, and volume :

- `Cache_ID` – the cache cluster's ID (in the format FSxIdabcdef1234567890a)
- `Origin_ID` – the origin cluster's ID
- `CacheSVM` – the cache SVM name
- `OriginSVM` – the origin SVM name
- `OriginVol` – the origin volume name
- `CacheVol` – the FlexCache volume name

The procedures in this section use the following NetApp ONTAP CLI commands.

- `network interfaces show`
- `cluster peer` commands
- `volume flexcache create`

Prerequisites

Before you begin using the procedures in the following sections, be sure that you have met the following prerequisites:

- The source and destination file systems are connected in the same VPC, or are in networks that are peered using Amazon VPC, AWS Transit Gateway, Direct Connect, or Site-to-Site VPN. For more information, see Accessing data from within the AWS Cloud and What is VPC peering? in the Amazon VPC Peering Guide.
- The VPC security group for the FSx for ONTAP file system has inbound and outbound rules allowing ICMP as well as TCP on ports 11104 and 11105 for your inter-cluster endpoints (LIFs).
- You have created a destination FSx for ONTAP file system with an SVM, but you have not created the volume that will be used as a FlexCache. For more information, see Creating file systems.

Record the source and destination inter-cluster LIFs

1. For the FSx for ONTAP file system that is the destination cluster:
    a. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
    b. Choose **File systems**, then choose the FSx for ONTAP file system that is the destination cluster to open the file system details page.

c. In **Administration**, find the **Inter-cluster endpoint - IP addresses**, and record the value.

> **Note**
>
> For scale-out file systems, there are two inter-cluster endpoint IP addresses for each high-availability (HA) pair.

2. For the on-premises source cluster, retrieve the inter-cluster LIF IP addresses using the following ONTAP CLI command:

```
Origin::> network interface show -role intercluster
Logical                         Network
Vserver     Interface  Status   Address/Mask
----------- ---------- -------  ------------
OriginSVM
            inter_1     up/up   10.0.0.36/24
            inter_2     up/up   10.0.1.69/24
```

3. Save the `inter_1` and `inter_2 IP` addresses. They are referenced in the `OriginSVM` alias as `origin_inter_1` and `origin_inter_2` and the `CacheSVM` alias as `cache_inter_1` and `cache_inter_2`.

Establish cluster peering between the origin and cache

Establish a cluster peer relationship on the **Cache** and **Source** cluster using the **cluster peer create** ONTAP CLI command. You will provide the inter-cluster IP addresses that you saved previously in the Record the source and destination inter-cluster LIFs procedure. When prompted, you will be asked to create a *`cluster-peer-passphrase`* that you will need to enter in when you establish cluster peering on the **Origin** cluster.

1. Set up cluster peering on the `Cache` cluster (your FSx for ONTAP file system).

   a. To access the ONTAP CLI, establish an SSH session on the management port of the Amazon FSx for NetApp ONTAP file system or SVM by running the following command. Replace *`management_endpoint_ip`* with the IP address of the file system's management port.

   ```
   [~]$ ssh fsxadmin@management_endpoint_ip
   ```

For more information, see Managing file systems with the ONTAP CLI.

b. Use the following command, and record the password that you create. For scale-out file systems, provide the `inter_1` and `inter_2` IP addresses for each HA pair.

```
FSx-Cache::> cluster peer create -address-family ipv4 -peer-
addrs origin_inter_1,origin_inter_2

Enter the passphrase: cluster-peer-passphrase
Confirm the passphrase: cluster-peer-passphrase
Notice: Now use the same passphrase in the "cluster peer create" command in the
 other cluster.
```

2. Use the following command to set up cluster peering on the `source` (on-premises) cluster. You'll need to enter the passphrase you created in the previous step to authenticate. For scale-out file systems, you'll need to provide the inter-cluster IP address for each HA pair.

```
Origin::> cluster peer create -address-family ipv4 -peer-
addrs cache_inter_1,cache_inter_2

Enter the passphrase: cluster-peer-passphrase
Confirm the passphrase: cluster-peer-passphrase
```

3. On the `source` cluster, verify that cluster peering was set up successfully using the following command. In the output, `Availability` should be set to `Available`.

```
Origin::> cluster peer show

Peer Cluster Name     Availability    Authentication
-------------------   -------------   --------------
Cache_ID              Available       ok
```

If the output does not show `Available`, repeat the previous steps on the `source` and `cache` clusters.

Configure storage virtual machine (SVM) peering

After you have established cluster peering successfully, the next step is to create an SVM peering relationship on the cache cluster (Cache) using the **vserver peer** command. Additional aliases used in the following procedure are as follows:

- *CacheLocalName* – the name used to identify the cache SVM when configuring SVM peering on the origin SVM.
- *OriginLocalName* – the name used to identify the origin SVM when configuring SVM peering on the cache SVM.

1. On the cache SVM, use the following command to create an SVM peering relationship.

```
FSx-Cache::> vserver peer create -vserver CacheSVM -peer-vserver OriginSVM -peer-
cluster Origin_ID -local-name OriginLocalName -application flexcache
```

2. On the source cluster, use the following command to accept the SVM peering relationship.

```
Origin::> vserver peer accept -vserver OriginSVM -peer-vserver CacheSVM -local-
name CacheLocalName
```

3. Verify that the SVM peering was successful using the following command; Peer State should be set to peered in the response.

```
Origin::> vserver peer show

Vserver      Peer Vserver    Peer State    Peering Cluster    Remote Applications

------------ --------------- ------------- ------------------
 ------------------------
OriginSVM    CacheSVM        peered        FSx-Cache          flexcache
```

Create the FlexCache volume

After successfully creating the SVM peering relationship, the next step is to create the FlexCache volume on the cache SVM. The FlexCache volume must be a FlexGroup. You will also choose a mode of operation for your FlexCache volume. For more information, see FlexCache write modes.

1. On the cache cluster, use the following ONTAP CLI command to create your FlexCache volume. The example creates a 2 TB FlexCache volume named *CacheVol*.

   - To create a write-around FlexCache volume, use the following command.

```
FSx-Cache::> volume flexcache create -vserver CacheSVM -size 2t -volume CacheVol
 -origin-volume OriginVol -origin-vserver OriginSVM -junction-path /flexcache -
aggr-list aggr1
```

- To create a write-back FlexCache volume, use the following command.

```
FSx-Cache::> volume flexcache create -vserver CacheSVM -size 2t -volume CacheVol
 -origin-volume OriginVol -origin-vserver OriginSVM -junction-path /flexcache -
aggr-list aggr1 -is-writeback-enabled true
```

> **Note**
>
> You can use the volume flexcache config modify -is-writeback-enabled {true|false} command to modify the write mode. Before using this command, make sure you enter ONTAP CLI advanced mode by using the set -privilege advanced command.

2. Verify the FlexCache relationship between the FlexCache volume and the origin volume.

- For a FlexCache write-around volume, your output will look similar to the following example.

```
FSx-Cache::> volume flexcache show

Vserver   Volume      Size     Origin-Vserver  Origin-Volume  Origin-Cluster
-------   ----------  -------  --------------  -------------  --------------
CacheSVM  CacheVol    2TB      OriginSVM       OriginVol      Origin
```

- For a FlexCache write-back volume, your output will look similar to the following example.

```
FSx-Cache::> volume flexcache show

Vserver   Volume      Size     Origin-Vserver  Origin-Volume  Origin-Cluster
 Writeback
-------   ----------  -------  --------------  -------------  --------------
 ---------
CacheSVM  CacheVol    2TB      OriginSVM       OriginVol      Origin
 true
```

Mount the FlexCache volume

Once the FlexCache volume becomes AVAILABLE, NFSv3, NFSv4, and SMB clients can mount it. Once the FlexCache is mounted, clients have access to the entire dataset on the on-premise origin volume.

- To create a mount point and mount the FlexCache, run the following commands on the client:

```
$ sudo mkdir -p /fsx/CacheVol
$ sudo mount -t nfs management.fs-01d2f606463087f6d.fsx.us-east-1.amazonaws.com:/
CacheVol /fsx/CacheVol
```

Replicating your data using NetApp SnapMirror

You can use NetApp SnapMirror to schedule periodic replication of your FSx for ONTAP file system to or from a second file system. This capability is available for both in-Region and cross-Region deployments.

NetApp SnapMirror replicates data at high speeds, so you get high data availability and fast data replication across ONTAP systems, whether you're replicating between two Amazon FSx file systems in AWS, or from on-premises to AWS. Replication can be scheduled as frequently as every 5 minutes, although intervals should be carefully chosen based on RPOs (Recovery Point Objectives), RTOs (Recovery Time Objectives), and performance considerations.

When you replicate data to NetApp storage systems and continually update the secondary data, your data is kept current and remains available whenever you need it. No external replication servers are required. For more information about using NetApp SnapMirror to replicate your data, see Learn about NetApp Replication in the *NetApp Console documentation*.

You can create a data protection (DP) destination volume for NetApp SnapMirror using the Amazon FSx console, the AWS CLI, and the Amazon FSx API, in addition to the NetApp ONTAP CLI and REST API. For information about creating a destination volume using the Amazon FSx console and AWS CLI, see Creating volumes.

You can use NetApp Console or the ONTAP CLI to schedule replication for your file system.

Note

There are two types of SnapMirror replication: Volume-level SnapMirror and SVM Disaster Recovery (SVMDR). Only volume-level SnapMirror replication is supported by FSx for ONTAP. Synchronous SnapMirror, including StrictSync, is not supported.

Using NetApp Console to schedule replication

You can use NetApp Console to set up replication with SnapMirror on your FSx for ONTAP file system. For more information, see Set up data replication in NetApp Replication in the *NetApp Console documentation*.

Using the ONTAP CLI to schedule replication

You can use the ONTAP CLI to configure scheduled volume replication. For information, see Managing SnapMirror volume replication in the *NetApp ONTAP Documentation Center*.

AWS billing and usage reports for FSx for ONTAP

AWS provides two usage reports for FSx for ONTAP:

- The AWS billing report is a high-level view of all activity for AWS services that you're using, including FSx for ONTAP.
- The AWS usage report is a summary of activity for a specific service, aggregated by hour, day, or month. It also includes usage charts that provide a graphical representation of your FSx for ONTAP usage.

> **Note**
>
> Like other AWS services, FSx for ONTAP charges you for only what you use. For more information, see Amazon FSx for NetApp ONTAP Pricing.

View the AWS billing report for FSx for ONTAP

You can view a summary of your AWS usage and charges, listed by service, on the **Bills** page in the AWS Billing and Cost Management console.

To view the AWS billing report

1. Sign in to the AWS Management Console and open the AWS Billing and Cost Management console at https://console.aws.amazon.com/costmanagement/.
2. In the navigation pane, choose **Bills**.
3. Choose a **Billing period** (for example, August 2024).
4. To see Amazon FSx charges, on the **Charges by service** tab, enter **FSx** in the filter by service text field, and then expand **FSx** to view charges by AWS Region.

   Charges for FSx for ONTAP file systems appear under *Amazon FSx CreateFileSystem:ONTAP* entries in the report.
5. To download the detailed billing report in CSV format, choose **Download all to CSV** at the top of the **Bills** page.

For more information about your AWS bill, see Viewing your bill in the AWS Billing User Guide.

The billing report includes the following usage types that apply to FSx for ONTAP file systems:

First generation FSx for ONTAP file systems

Charge type	Units	Description
ONTAP Single-AZ SSD storage	GB-Month	The amount of SSD storage provisioned on a first-generation Single-AZ ONTAP file system
ONTAP Multi-AZ SSD storage	GB-Month	The amount of SSD storage provisioned on a first-generation Multi-AZ FSx for ONTAP file system
ONTAP Single-AZ throughput capacity	MBps-Month	The amount of throughput capacity provisioned on a first-generation Single-AZ FSx for ONTAP file system
ONTAP Multi-AZ throughput capacity	MBps-Month	The amount of throughput capacity provisioned on a first-generation Multi-AZ FSx for ONTAP file system
Provisioned ONTAP Single-AZ SSD IOPS	IOPS-Month	The amount of provisioned SSD IOPS on a first-generation Single-AZ FSx for ONTAP file system
Provisioned ONTAP Multi-AZ SSD IOPS	IOPS-Month	The amount of provisioned SSD IOPS on a first-generation Multi-AZ FSx for ONTAP file system

Second generation FSx for ONTAP file systems

Charge type	Units	Description
ONTAP Single-AZ-2 SSD storage	GB-Month	The amount of SSD storage provisioned on a second-generation Single-AZ FSx for ONTAP file system
ONTAP Multi-AZ-2 SSD storage	GB-Month	The amount of SSD storage provisioned on a second-generation Multi-AZ FSx for ONTAP file system
ONTAP Single-AZ-2 throughput capacity	MBps-Month	The amount of throughput capacity provisioned on a second-generation Single-AZ FSx for ONTAP file system
ONTAP Multi-AZ-2 throughput capacity	MBps-Month	The amount of throughput capacity provisioned on a second-generation Multi-AZ FSx for ONTAP file system
Provisioned ONTAP Single-AZ-2 SSD IOPS	IOPS-Month	The amount of provisioned SSD IOPS on a second-generation Single-AZ FSx for ONTAP file system
Provisioned ONTAP Multi-AZ-2 SSD IOPS	IOPS-Month	The amount of provisioned SSD IOPS on a second-generation Multi-AZ FSx for ONTAP file system

All FSx for ONTAP filesystems

Charge type	Units	Description
ONTAP standard capacity pool storage	GB-Month	The amount of capacity pool storage used by the FSx for ONTAP file system.
ONTAP backup storage	GB-Month	The amount of storage capacity used for backups
SnapLock usage	GB-Month	The amount of storage capacity used by SnapLock volumes
Read requests to ONTAP standard capacity pool storage	Operations	The number of read requests made to standard capacity pool storage on an FSx for ONTAP file system
Write requests to ONTAP standard capacity pool storage	Operations	The number of write requests made to standard capacity pool storage on an FSx for ONTAP file system

View the AWS usage report for FSx for ONTAP

AWS provides an FSx usage report that is more detailed than the billing report. The usage report provides aggregate usage data by hour, day, or month, and it lists operations by region and usage type.

To view the AWS usage report

1. Sign in to the AWS Management Console and open the AWS Billing and Cost Management console at https://console.aws.amazon.com/costmanagement/.
2. In the navigation pane, choose **Cost Explorer**.
3. Under the **Report parameters** section, choose the **Date range** and granularity for your report.

4. Leave **Group by > dimension** set to **Service**.
5. Under **Filters > Service**, choose **FSx**
6. Choose the **Usage type**. See the table following this procedure for a list of FSx for ONTAP usage types.
7. Make any additional filter selections for your report.
8. To download the report details to a file, choose **Download as CSV**.

The following table lists the FSx for ONTAP usages types that you can use to filter the report to view usage data for ONTAP file systems. For more information about using the Cost Explorer, see Analyzing your costs and usage with AWS Cost Explorer in the AWS Cost Management User Guide.

First generation FSx for ONTAP file systems

Usage Type	Units	Description
region-Storage.SAZ_2N:SSD	GB-Month	The amount of SSD storage provisioned on a first-generation Single-AZ FSx for ONTAP file system.
region-Storage.MAZ:SSD	GB-Month	The amount of SSD storage provisioned on a first-generation Multi-AZ FSx for ONTAP file system.
region-ThroughputCapacity.SAZ_2N	MiBps-Mo	The amount of throughput capacity provisioned on a first-generation Single-AZ FSx for ONTAP file system.
region-ThroughputCapacity.MAZ	MiBps-Mo	The amount of throughput capacity provisioned on a first-generation Multi-AZ FSx for ONTAP file system.
region-ProvisionedSSDIOPS.SAZ_2N	IOPS-Mo	The amount of SSD IOPS provisioned above 3 IOPS per GiB of SSD

Usage Type	Units	Description
		storage on a first-generation Single-AZ FSx for ONTAP file system.
region-ProvisionedSSDIOPS.MAZ	IOPS-Mo	The amount of SSD IOPS provision ed above 3 IOPS per GiB of SSD storage on a first-generation Multi-AZ FSx for ONTAP file system.

Second generation FSx for ONTAP file systems

Usage Type	Units	Description
region-Storage.SAZ_2N2:SSD	GB-Month	The amount of SSD storage provisioned on a second-ge neration Single-AZ FSx for ONTAP file system.
region-Storage.MAZ2:SSD	GB-Month	The amount of SSD storage provisioned on a second-ge neration Multi-AZ FSx for ONTAP file system.
region-ThroughputCapacit y.SAZ_2N2	MiBps-Mo	The amount of throughput capacity provisioned on a second-generation Single-AZ FSx for ONTAP file system.
region-ThroughputCapacity.MAZ2	MiBps-Mo	The amount of throughput capacity provisioned on a second-generation Multi-AZ FSx for ONTAP file system.
region-ProvisionedSSDIOP S.SAZ_2N2	IOPS-Mo	The amount of SSD IOPS provision ed above 3 IOPS per GiB of SSD storage on a second-generation

Usage Type	Units	Description
		Single-AZ FSx for ONTAP file system.
region-ProvisionedSSDIOPS.MAZ2	IOPS-Mo	The amount of SSD IOPS provisioned above 3 IOPS per GiB of SSD storage on a second-generation Multi-AZ FSx for ONTAP file system.

All FSx for ONTAP file systems

Usage Type	Units	Description
region-Storage.SAZ_2N:CPoolStd	GB-Mo	The amount of standard capacity pool storage used on a first or second generation Single-AZ FSx for ONTAP file system.
region-Storage.MAZ:CPoolStd	GB-Mo	The amount of standard capacity pool storage used on a first or second generation Multi-AZ FSx for ONTAP file system.
region-BackupUsage	GB-Month	The amount of storage capacity used for backups.
region-SnaplockUsage	GB-Month	The amount of storage capacity used by SnapLock volumes.
region-Requests.SAZ_2N:CPoolStdRd	Operations	The number of read requests made to standard capacity pool storage on a Single-AZ FSx for ONTAP file system.
	Operations	The number of write requests made to standard capacity pool

Usage Type	Units	Description
region-Requests.SAZ_2N:CPoolStdWr		storage on a Single-AZ FSx for ONTAP file system.
region-Requests.MAZ:CPoolStdRd	Operations	The number of read requests made to standard capacity pool storage on a Multi-AZ FSx for ONTAP file system.
region-Requests.MAZ:CPoolStdWr	Operations	The number of write requests made to standard capacity pool storage on a Multi-AZ FSx for ONTAP file system.

Monitoring Amazon FSx for NetApp ONTAP

You can use the following services and tools to monitor Amazon FSx for NetApp ONTAP usage and activity:

- **Amazon CloudWatch** – You can monitor file systems using Amazon CloudWatch, which automatically collects and processes raw data from FSx for ONTAP into readable metrics. These statistics are retained for a period of 15 months so that you can access historical information and see how your file system is performing. You can also set alarms based on your metrics over a specified time period and perform one or more actions based on the value of the metrics relative to thresholds that you specify.
- **ONTAP EMS events** – You can monitor your FSx for ONTAP file system by using events generated by ONTAP's Events Management System (EMS). EMS events are notifications of occurrences in your file system, such as iSCSI LUN creation or automatic sizing of volumes.
- **NetApp Data Infrastructure Insights** – You can monitor configuration, capacity, and performance metrics for your FSx for ONTAP file systems using the NetApp Data Infrastructure Insights service. You can also create alerts based on metric conditions.
- **NetApp Harvest and NetApp Grafana** – You can monitor your FSx for ONTAP file system by using NetApp Harvest and NetApp Grafana. NetApp Harvest monitors ONTAP file systems by collecting performance, capacity, and hardware metrics from FSx for ONTAP file systems. Grafana provides a dashboard where the collected Harvest metrics can be displayed.
- **AWS CloudTrail** – You can use AWS CloudTrail to capture all API calls for Amazon FSx as events. These events provide a record of actions taken by a user, role, or AWS service in Amazon FSx.

Topics

- Monitoring with Amazon CloudWatch
- Monitoring FSx for ONTAP EMS events
- Monitoring with Data Infrastructure Insights
- Monitoring FSx for ONTAP file systems using Harvest and Grafana
- Monitoring FSx for ONTAP API Calls with AWS CloudTrail

Monitoring with Amazon CloudWatch

You can monitor file systems using Amazon CloudWatch, which collects and processes raw data from Amazon FSx for NetApp ONTAP into readable, near real-time metrics. These statistics are retained for a period of 15 months, so that you can access historical information to determine how your file system is performing. FSx for ONTAP metric data is automatically sent to CloudWatch at 1-minute periods by default. For more information about CloudWatch, see What is Amazon CloudWatch? in the *Amazon CloudWatch User Guide*.

> **Note**
>
> By default, FSx for ONTAP sends metric data to CloudWatch at 1-minute periods except for the following metrics that are sent in 5-minute intervals:
>
> - `FileServerDiskThroughputBalance`
> - `FileServerDiskIopsBalance`

CloudWatch metrics for FSx for ONTAP are organized into four categories, which are defined by the dimensions that are used to query each metric. For more information about dimensions, see Dimensions in the *Amazon CloudWatch User Guide*.

- **File system metrics**: File-system-level performance and storage capacity metrics.
- **File server metrics**: File-server-level metrics.
- **Detailed file system aggregate metrics**: Detailed file system metrics per aggregate.
- **Detailed file system metrics**: File-system-level storage metrics per storage tier (SSD and capacity pool).
- **Volume metrics**: Per-volume performance and storage capacity metrics.
- **Detailed volume metrics**: Per-volume storage capacity metrics by storage tier or by the type of data (user, snapshot, or other).

All CloudWatch metrics for FSx for ONTAP are published to the `AWS/FSx` namespace in CloudWatch.

Topics

- Accessing CloudWatch metrics

- Monitoring in the Amazon FSx console
- File system metrics
- Second-generation file system metrics
- Volume metrics

Accessing CloudWatch metrics

You can see Amazon CloudWatch metrics for Amazon FSx in the following ways:

- The Amazon FSx console
- The Amazon CloudWatch console
- The AWS Command Line Interface (AWS CLI) for CloudWatch
- The CloudWatch API

The following procedure explains how to view your file system's CloudWatch metrics with the Amazon FSx console.

To view CloudWatch metrics for your file system using the Amazon FSx console

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. In the left navigation pane, choose **File systems**, then choose the file system whose metrics you want to view.
3. On the **Summary** page, choose **Monitoring & performance** from the second panel to view graphs for your file system's metrics.

There are four tabs on the **Monitoring & performance** panel.

- Choose **Summary** (the default tab) to display any active warnings, CloudWatch alarms, and graphs for **File system activity**.
- Choose **Storage** to view storage capacity and utilization metrics.
- Choose **Performance** to view file server and storage performance metrics.
- Choose **CloudWatch alarms** to view graphs of any alarms configured for your file system.

The following procedure explains how to view your volume's CloudWatch metrics with the Amazon FSx console

To view CloudWatch metrics for your volume using the Amazon FSx console

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. In the left navigation pane, choose **Volumes**, then choose the volume whose metrics you want to view.
3. On the **Summary** page, choose **Monitoring** (the default tab) from the second panel to view graphs for your volume's metrics.

The following procedure explains how to view your file system's CloudWatch metrics with the Amazon CloudWatch console.

To view metrics using the Amazon CloudWatch console

1. On the **Summary** page of your file system, choose **Monitoring & performance** from the second panel to view graphs for your file system's metrics.
2. Choose **View in metrics** from the actions menu in the upper right of the graph that you want to view in the Amazon CloudWatch console. This opens the **Metrics** page in the Amazon CloudWatch console.

The following procedure explains how to add FSx for ONTAP file system metrics to a dashboard in the Amazon CloudWatch console.

To add metrics to a Amazon CloudWatch console

1. Choose the set of metrics (**Summary**, **Storage**, or **Performance**) in the **Monitoring & performance** panel of the Amazon FSx console.
2. Choose **Add to dashboard** in the upper right hand of the panel. This opens the Amazon CloudWatch console.
3. Select an existing CloudWatch dashboard from the list, or create a new dashboard. For more information, see Using Amazon CloudWatch dashboards in the *Amazon CloudWatch User Guide*.

The following procedure explains how to access your file system's metrics with the AWS CLI.

To access metrics from the AWS CLI

- Use the CloudWatch list-metrics CLI command with the `--namespace "AWS/FSx"` parameter. For more information, see the AWS CLI Command Reference.

The following procedure explains how to access your file system's metrics with the CloudWatch API.

To access metrics from the CloudWatch API

- Call the GetMetricStatistics API operation. For more information, see the Amazon CloudWatch API Reference.

Monitoring in the Amazon FSx console

The CloudWatch metrics reported by Amazon FSx provide valuable information about your FSx for ONTAP file systems and volumes.

Topics

- Monitoring file system metrics in the Amazon FSx console
- Monitoring volume metrics in the Amazon FSx console
- Performance warnings and recommendations
- Creating Amazon CloudWatch alarms to monitor Amazon FSx

Monitoring file system metrics in the Amazon FSx console

You can use the **Monitoring & performance** panel on your file system's dashboard in the Amazon FSx console to view the metrics that are described in the following table. For more information, see Accessing CloudWatch metrics.

Monitor g & perform ce	How do I...	Chart	Relevant metrics
Summar	...determine the amount of available storage capacity on my file system?	Available primary	`StorageCapacity {SSD} - StorageUsed {SSD}`

Monitoring & performance	How do I...	Chart	Relevant metrics
		storage capacity (bytes)	
	...determine my file system's total client throughput?	Total client throughput (bytes/sec)	SUM(`DataReadBytes` + `DataWriteBytes`)/ PERIOD (in seconds)
	...determine my file system's total client IOPS?	Total client IOPS (operations/sec)	SUM(`DataReadOperations` + `DataWriteOperations` + `MetadataOperations`)/PERIOD (in seconds)
	...determine the average latency for the read, write, and metadata operations of my file system?	Average latency (ms/operation)	Average read latency: `DataReadOperationTime` * 1000/`DataReadOperations` Average write latency: `DataWriteOperationTime` * 1000/`DataWriteOperations` Average metadata latency: `MetadataOperationTime` * 1000/`MetadataOperations`

Monitoring & performance	How do I...	Chart	Relevant metrics
Storage	...determine the distribution of used and free storage capacity on my file system?	Storage distribution	Primary tier available: `StorageCapacity {SSD} - StorageUsed {SSD}` Primary tier used: `StorageUsed {SSD}` Capacity pool used: `StorageUsed {StandardCapacityPool }`
	...determine the savings from storage efficiencies (compression, deduplication, and compaction)?	Storage efficiency savings	`StorageEfficiencySavings`
	...determine how much primary storage is available?	Available primary storage capacity (bytes)	`StorageCapacity {SSD} - StorageUsed {SSD}`
	...determine the percent of used primary storage for my file system?	Primary storage capacity utilization (percent)	`StorageUsed {SSD} * 100/StorageCapacity {SSD}`

Monitoring & performance	How do I...	Chart	Relevant metrics
File server performance	...determine if my file system is approaching its network throughput limit?	Network throughput – utilization (percent)	`NetworkThroughputUtilization`
	...determine if my file system is approaching its disk throughput limit?	Disk throughput – utilization (percent)	`FileServerDiskThroughputUtilization`
	...determine if my file system has exhausted its allowed burst credits for disk throughput?	Disk throughput – burst balance (percent)	`FileServerDiskThroughputBalance`
	...determine if my file system is approaching its file servers' SSD IOPS limit?	Disk IOPS – utilization (percent)	`FileServerDiskIopsUtilization`
	...determine if my file system has exhausted its file servers' allowed burst credits for disk SSD IOPS?	Disk IOPS – burst balance (percent)	`FileServerDiskIopsBalance`

Monitoring & performance	How do I...	Chart	Relevant metrics
	...determine the average utilization of the file system's CPU?	CPU utilization (percent)	`CPUUtilization`
	...determine if my workload is making efficient use of my file system's RAM and NVMe read caches?	Cache hit ratio (percent)	`FileServerCacheHitRatio`
Disk performance	...determine if my file system is approaching its currently provisioned SSD IOPS capacity?	Disk IOPS – utilization (SSD) (percent)	`DiskIopsUtilization`

Note

We recommend that you maintain an average throughput capacity utilization of any performance-related dimensions such as network utilization, CPU utilization, and SSD IOPS utilization to under 50%. This ensures that you have enough spare throughput capacity for unexpected spikes in your workload, as well as for any background storage operations (such as storage synchronization, data tiering, or backups).

Monitoring volume metrics in the Amazon FSx console

You can view the **Monitoring** panel on your volume's dashboard in the Amazon FSx console to see additional performance metrics. For more information, see Accessing CloudWatch metrics.

Monitoring	How do I...	Chart	Relevant metrics
	...determine my volume's available storage capacity?	Available storage capacity	`StorageCapacity`
	...determine my volume's total client throughput?	Total client throughput (bytes/sec)	SUM(`DataReadBytes` + `DataWriteBytes`)/ PERIOD (in seconds)
	...determine my volume's total client IOPS?	Total client IOPS (operations/sec)	SUM(`DataReadOperations` + `DataWriteOperations` + `MetadataOperations`)/PERIOD (in seconds)
	...determine how many read and write operations are coming from or going to the capacity pool tier?	Capacity Pool IOPS (operations/sec)	Read operations: `CapacityPoolReadOperations` Write operations: `CapacityPoolWriteOperations`
	...determine the average latency for the read, write, and metadata operations of my volume?	Average latency (ms/operation)	Average read latency: `DataReadOperationTime` * 1000/`DataReadOperations` Average write latency: `DataWriteOperationTime` * 1000/`DataWriteOperations`

Monitoring	How do I...	Chart	Relevant metrics
			Average metadata latency: `MetadataOperationTime * 1000/MetadataOperations`
	...determine the amount of files or inodes that are available on my volume?	Available files (inodes)	`FilesCapacity - FilesUsed`
	...determine the distribution of used and free storage capacity on my volume?	Storage distribution	`StorageCapacity - StorageUsed`

Performance warnings and recommendations

FSx for ONTAP displays a warning for CloudWatch metrics whenever one of these metrics has approached or crossed a predetermined threshold for multiple consecutive data points. These warnings provide you with actionable recommendations that you can use to optimize your file system's performance.

Warnings are accessible in several areas of the **Monitoring & performance** dashboard. All active or recent Amazon FSx performance warnings and any CloudWatch alarms configured for the file system that are in an ALARM state appear in the **Monitoring & performance** panel in the **Summary** section. The warning also appears in the section of the dashboard where the metric graph is displayed.

You can create CloudWatch alarms for any of the Amazon FSx metrics. For more information, see Creating Amazon CloudWatch alarms to monitor Amazon FSx.

Use performance warnings to improve file system performance

Amazon FSx provides actionable recommendations that you can use to optimize your file system's performance. These recommendations describe how you can address a potential performance bottle neck. You can take the recommended action if you expect the activity to continue, or if it's causing an impact to your file system's performance. Depending on which metric has triggered a

warning, you can resolve it by increasing either the file system's throughput capacity or storage capacity, as described in the following table.

Dashboard section	If there's a warning for this metric	Do this
Storage	Primary storage capacity utilization	Increase your file system's primary storage capacity if your file system isn't already at the maximum SSD storage capacity. For more information, see Updating storage capacity and provisioned IOPS. If your file system has multiple HA pairs and your primary storage capacity utilization is only higher for a subset of your file system's aggregates (the storage pools that make up your primary storage tier), then you can also rebalance your workload so that your primary storage capacity utilization is more evenly spread across your file system. For more informati on on rebalancing your workloads, see Balancing workloads across HA pairs. If you're currently performing an SSD decrease operation and utilization exceeds 80% on the new set of disks, you can either tier data to the capacity pool, delete data from volumes that have been redirected to the new disks, or submit a request to increase SSD capacity during the decrease operation. Amazon FSx will prioritize the increase request before resuming the decrease operation. For more information, see To decrease SSD storage capacity for a file system (console).
File server performan ce	Network throughput	Increase your file system's throughput capacity if your file system is not already at the maximum throughpu t capacity. For more information on updating throughput capacity, see Updating throughput capacity.
	Disk throughput	
	Disk IOPS	
	CPU utilization	

Dashboard section	If there's a warning for this metric	Do this
		If your file system has multiple HA pairs and utilization is high for only a subset of file servers, then you can also rebalance your workload so that your workload is more evenly utilizing the performance capabilities of each of your file system's HA pairs. For more information on rebalancing your workloads, see Balancing workloads across HA pairs.
Disk performance	Disk IOPS	Increase SSD IOPS if your file system is not already at the maximum SSD IOPS for your file system's current throughput capacity. For more information on updating your file system's provisioned IOPS, see Updating storage capacity and provisioned IOPS. If your file system has multiple HA pairs and your disk IOPS utilization is only higher for a subset of your file system's aggregates (the storage pools which make up your primary storage tier), then you can also rebalance your workload so that your disk IOPS are utilized more evenly across your file system. For more information on rebalancing your workloads, see Balancing workloads across HA pairs.

Note

During an SSD decrease operation, write-heavy workloads could experience a temporary performance degradation as the operation consumes disk and network resources. To minimize performance impact, maintain adequate headroom by ensuring ongoing workloads don't consistently consume more than 50% CPU, 50% disk throughput, or 50% SSD IOPS before initiating an SSD decrease operation.
Brief I/O pauses of up to 60 seconds might occur for each volume as client access is redirected to the new set of disks. These pauses are expected and normal during the cutover phase of the operation.

For more information about file system performance, see Amazon FSx for NetApp ONTAP performance.

Creating Amazon CloudWatch alarms to monitor Amazon FSx

You can create a CloudWatch alarm that sends an Amazon Simple Notification Service (Amazon SNS) message when the alarm changes state. An alarm watches a single metric over a time period that you specify. If needed, the alarm then performs one or more actions based on the value of the metric relative to a given threshold over a number of time periods. The action is a notification sent to an Amazon SNS topic or an Auto Scaling policy.

Alarms invoke actions for sustained state changes only. CloudWatch alarms don't invoke actions only because they are in a particular state; the state must have changed and been maintained for a specified number of periods. You can create an alarm from the Amazon FSx console or the Amazon CloudWatch console.

The following procedures describe how to create alarms using the Amazon FSx console, AWS Command Line Interface (AWS CLI), and API.

To set alarms using the Amazon FSx console

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. In the left navigation pane, choose **File systems**, and then choose the file system that you want to create the alarm for.
3. On the **Summary** page, choose **Monitoring & performance** from the second panel.
4. Choose the **CloudWatch alarms** tab.
5. Choose **Create CloudWatch alarm**. You are redirected to the CloudWatch console.
6. Choose **Select metric**.
7. In the **Metrics** section, choose **FSx**.
8. Choose a metric category:
   - **File System Metrics**
   - **Detailed File System Metrics**
   - **Volume Metrics**
   - **Detailed Volume Metrics**
9. Choose the metric you want to set the alarm for, and then choose **Select metric**.

10. In the **Conditions** section, choose the conditions you want for the alarm, and then choose **Next**.

    > **Note**
    >
    > Metrics might not be published during file system maintenance. To prevent unnecessary and misleading alarm condition changes and to configure your alarms so that they are resilient to missing data points, see Configuring how CloudWatch alarms treat missing data in the *Amazon CloudWatch User Guide*.

11. If you want CloudWatch to send you an email or Amazon SNS notification when the alarm state initiates the action, choose an alarm state for **Alarm state trigger**.

    For **Send a notification to the following SNS topic**, choose an option. If you choose **Create topic**, you can set the name and email addresses for a new email subscription list. This list is saved and appears in the field for future alarms. Choose **Next**.

    > **Note**
    >
    > If you use **Create topic** to create a new Amazon SNS topic, the email addresses must be verified before they receive notifications. Emails are sent only when the alarm enters an alarm state. If this alarm state change happens before the email addresses are verified, they don't receive a notification.

12. Fill in the **Alarm name** and **Alarm description** fields, and then choose **Next**.
13. On the **Preview and create** page, review the alarm that you're about to create, and then choose **Create alarm**.

To set alarms using the CloudWatch console

1. Open the CloudWatch console at https://console.aws.amazon.com/cloudwatch/.
2. Choose **Create Alarm** to start the **Create Alarm Wizard**.
3. Follow the procedure in **To set alarms using the Amazon FSx console**, beginning with step 6.

To set an alarm using the AWS CLI

- Call the put-metric-alarm CLI command. For more information, see the AWS CLI Command Reference.

To set an alarm using the CloudWatch API

- Call the PutMetricAlarm API operation. For more information, see the Amazon CloudWatch API Reference.

File system metrics

Your Amazon FSx for NetApp ONTAP file system metrics are classified as either **File system metrics** or **Detailed file system metrics**.

- **File system metrics** are aggregate performance and storage metrics for a single file system that take a single dimension, `FileSystemId`. These metrics measure network performance and storage capacity usage for your file system.
- **Detailed file system metrics** measure your file system's storage capacity and used storage in each storage tier (for example, SSD storage and capacity pool storage). Each metric includes a `FileSystemId`, `StorageTier`, and `DataType` dimension.

Note the following about when Amazon FSx publishes data points for these metrics to CloudWatch:

- For the utilization metrics (any metric whose name ends in *Utilization*, such as `NetworkThroughputUtilization`), there is a data point emitted each period for every active file server or aggregate. For example, Amazon FSx emits one minutely metric per active file server for `FileServerDiskIopsUtilization`, and one minutely metric per aggregate for `DiskIopsUtilization`.
- For all other metrics, there is a single data point emitted each period, corresponding to the total value of the metric across all of your active file servers (such as `DataReadBytes` for file server metrics) or all of your aggregates (such as `DiskReadBytes` for storage metrics).

Topics

- Network I/O metrics

- File server metrics
- Disk I/O metrics
- Storage capacity metrics
- Detailed file system metrics

Network I/O metrics

All of these metrics take one dimension, `FileSystemId`.

Metric	Description
`NetworkThroughputUtilization`	The percent utilization of network throughput for the file system. Note that this metric reflects the direction - i.e. inbound or outbound - that has the higher traffic flow. To see individual metrics for each direction, please refer to the NetworkReceivedBytes and NetworkSentBytes metrics. The `Average` statistic is the average network throughput utilization of the file system over a specified period. The `Minimum` statistic is the lowest network throughput utilization of the file system over a specified period. The `Maximum` statistic is the highest network throughput utilization of the file system over a specified period. Units: Percent Valid statistics: `Average`, `Minimum`, and `Maximum`
`NetworkSentBytes`	The number of bytes (network I/O) sent by the file system.

Metric	Description
	The Sum statistic is the total number of bytes sent by the file system over a specified period. To calculate sent throughput (bytes per second) for any statistic, divide the statistic by the seconds in the specified period. Units: Bytes Valid statistics: Sum
NetworkReceivedBytes	The number of bytes (network I/O) received by the file system. The Sum statistic is the total number of bytes received by the file system over a specified period. To calculate received throughput (bytes per second) for any statistic, divide the statistic by the seconds in the specified period. Units: Bytes Valid statistics: Sum

Metric	Description
DataReadBytes	The number of bytes (network I/O) from reads by clients to the file system. The Sum statistic is the total number of bytes associated with read operations during the specified period. To calculate the average throughput (bytes per second) for a period, divide the Sum statistic by the number of seconds in the specified period. Units: Bytes Valid statistics: Sum
DataWriteBytes	The number of bytes (network I/O) from writes by clients to the file system. The Sum statistic is the total number of bytes associated with write operations during the specified period. To calculate the average throughput (bytes per second) for a period, divide the Sum statistic by the number of seconds in the specified period. Units: Bytes Valid statistics: Sum

Metric	Description
DataReadOperations	The count of read operations (network I/O) from reads by clients to the file system. The Sum statistic is the total number of I/O operations that occurred over a specified period. To calculate the average read operations per second for a period, divide the Sum statistic by the number of seconds in the specified period. Units: Count Valid statistics: Sum
DataWriteOperations	The count of write operations (network I/O) from writes by clients to the file system. The Sum statistic is the total number of I/O operations that occurred over a specified period. To calculate the average write operations per second for a period, divide the Sum statistic by the number of seconds in the specified period. Units: Count Valid statistics: Sum

Metric	Description
MetadataOperations	The count of metadata operations (network I/O) by clients to the file system. The Sum statistic is the total number of I/O operations that occurred over a specified period. To calculate the average metadata operations per second for a period, divide the Sum statistic by the number of seconds in the specified period. Units: Count Valid statistics: Sum
DataReadOperationTime	The sum of total time spent within the file system for read operations (network I/O) from clients accessing data in the file system. The Sum statistic is the total number of seconds spent by read operations during the specified period. To calculate the average read latency for a period, divide the Sum statistic by the Sum of the DataReadOperations metric over the same period. Units: Seconds Valid statistics: Sum

Metric	Description
DataWriteOperationTime	The sum of total time spent within the file system for fulfilling write operations (network I/O) from clients accessing data in the file system. The Sum statistic is the total number of seconds spent by write operations during the specified period. To calculate the average write latency for a period, divide the Sum statistic by the Sum of the DataWrite Operations metric over the same period. Units: Seconds Valid statistics: Sum
CapacityPoolReadBytes	The number of bytes read (network I/O) from the file system's capacity pool tier. To ensure data integrity, ONTAP performs a read operation on the capacity pool immediately after performing a write operation. The Sum statistic is the total number of bytes read from the file system's capacity pool tier over a specified period. To calculate capacity pool bytes per second, divide the Sum statistic by the seconds in a specified period. Units: Bytes Valid statistics: Sum

Metric	Description
CapacityPoolReadOperations	The number of read operations (network I/O) from the file system's capacity pool tier. This translates to a capacity pool read request. To ensure data integrity, ONTAP performs a read operation on the capacity pool immediately after performing a write operation. The Sum statistic is the total number of read operations from the file system's capacity pool tier over a specified period. To calculate capacity pool requests per second, divide the Sum statistic by the seconds in a specified period. Units: Count Valid statistics: Sum
CapacityPoolWriteBytes	The number of bytes written (network I/O) to the file system's capacity pool tier. To ensure data integrity, ONTAP performs a read operation on the capacity pool immediately after performing a write operation. The Sum statistic is the total number of bytes written to the file system's capacity pool tier over a specified period. To calculate capacity pool bytes per second, divide the Sum statistic by the seconds in a specified period. Units: Bytes Valid statistics: Sum

Metric	Description
CapacityPoolWriteOperations	The number of write operations (network I/O) to the file system from the capacity pool tier. This translates to a write request. To ensure data integrity, ONTAP performs a read operation on the capacity pool immediately after performing a write operation. The Sum statistic is the total number of write operations to the file system's capacity pool tier over a specified period. To calculate capacity pool requests per second, divide the Sum statistic by the seconds in a specified period. Units: Count Valid statistics: Sum

File server metrics

All of these metrics take one dimension, FileSystemId.

Metric	Description
CPUUtilization	The percent utilization of the file system's CPU resources. The Average statistic is the average CPU utilization of the file system over a specified period. The Minimum statistic is the lowest CPU utilization of the file system over a specified period.

Metric	Description
	The `Maximum` statistic is the highest CPU utilization of the file system over a specified period. Units: Percent Valid statistics: `Average`, `Minimum`, and `Maximum`
`FileServerDiskThroughputUtilization`	The disk throughput between your file server and the primary tier, as a percentage of the provisioned limit determined by throughput capacity. The `Average` statistic is the average percent utilization of the file servers' disk throughput over a specified period. The `Minimum` statistic is the lowest percent utilization of the file servers' disk throughput over a specified period. The `Maximum` statistic is the highest utilization of the file servers' disk throughput over a specified period. Units: Percent Valid statistics: `Average`, `Minimum`, and `Maximum`

Metric	Description
FileServerDiskThroughputBalance	The percentage of available burst credits for disk throughput between your file server and the primary tier. This is valid for file systems that are provisioned with a throughput capacity of less than 512 MBps. The Average statistic is the average burst balance available over a specified period. The Minimum statistic is the minimum burst balance available over a specified period. The Maximum statistic is the maximum burst balance available over a specified period. Units: Percent Valid statistics: Average, Minimum, and Maximum

Metric	Description
FileServerDiskIopsBalance	The percentage of available burst credits for disk IOPS between your file server and the primary tier. This is valid for file systems that are provisioned with a throughput capacity of less than 512 MBps. The Average statistic is the average burst balance available over a specified period. The Minimum statistic is the minimum burst balance available over a specified period. The Maximum statistic is the maximum burst balance available over a specified period. Units: Percent Valid statistics: Average, Minimum, and Maximum

Metric	Description
`FileServerDiskIopsUtilization`	The percentage of IOPS utilization of available disk IOPS capacity for your file server. The `Average` statistic is the average disk IOPS utilization of the file system over a specified period. The `Minimum` statistic is the minimum disk IOPS utilization of the file system over a specified period. The `Maximum` statistic is the maximum disk IOPS utilization of the file system over a specified period. Units: Percent Valid statistics: `Average`, `Minimum`, and `Maximum`

Metric	Description
FileServerCacheHitRatio	The percentage of all read requests that are served by data in the file system's RAM and NVMe caches. A higher percentage means that more reads are served by the file system's read caches. Units: Percent The Average statistic is the average cache hit percent for the file system over a specified period. The Minimum statistic is the lowest cache hit percent for the file system over a specified period. The Maximum statistic is the highest cache hit percent for the file system over a specified period. Valid statistics: Average, Minimum, and Maximum

Disk I/O metrics

All of these metrics take one dimension, FileSystemId.

Metric	Description
DiskReadBytes	The number of bytes (disk I/O) from any disk reads to the file system's primary tier. The Sum statistic is the total number of bytes read from the file system over a specified period.

Metric	Description
	To calculate read disk throughput (bytes per second) for any statistic, divide the Sum statistic by the seconds in the specified period. Units: Bytes Valid statistics: Sum
DiskWriteBytes	The number of bytes (disk I/O) from any disk writes to the file system's primary tier. The Sum statistic is the total number of bytes written from the file system over a specified period. To calculate write disk throughput (bytes per second) for any statistic, divide Sum the statistic by the seconds in the specified period. Units: Bytes Valid statistics: Sum

Metric	Description
DiskIopsUtilization	The disk IOPS between your file server and storage volumes, as a percentage of the primary's tiers provisioned disk IOPS limit. The Average statistic is the average disk IOPS utilization of the file system over a specified period. The Minimum statistic is the minimum disk IOPS utilization of the file system over a specified period. The Maximum statistic is the maximum disk IOPS utilization of the file system over a specified period. Units: Percent Valid statistics: Average, Minimum, and Maximum
DiskReadOperations	The number of read operations (disk I/O) from the file system's primary tier. The Sum statistic is the total number of read operations from the primary tier over a specified period. Units: Count Valid statistics: Sum

Metric	Description
DiskWriteOperations	The number of write operations (disk I/O) to the file system's primary tier. The Sum statistic is the total number of write operations to the primary tier over a specified period. Units: Count Valid statistics: Sum

Storage capacity metrics

All of these metrics take one dimension, FileSystemId.

Metric	Description
StorageEfficiencySavings	The bytes saved from storage efficiency features (compression, deduplication, and compaction). The Average statistic is the average storage efficiency savings over a specified period. To calculate storage efficiency savings as a percentage of all data stored, over a one minute period, divide StorageEfficiencySavings by the sum of StorageEfficiencySavings and the StorageUsed file system metric, using the Sum statistic for StorageUsed . The Minimum statistic is the minimum storage efficiency savings over a specified period. The Maximum statistic is the maximum storage efficiency savings over a specified period.

Metric	Description
	Units: Bytes Valid statistics: `Average`, `Minimum`, and `Maximum`
`StorageUsed`	The total amount of physical data stored on the file system, on both the primary (SSD) tier and the capacity pool tier. This metric includes savings from storage-efficiency features, such as data compression and deduplication. Units: Bytes Valid statistics: `Average`, `Minimum`, and `Maximum`

Metric	Description
LogicalDataStored	The total amount of logical data stored on the file system, considering both the SSD tier and the capacity pool tier. This metric includes the total logical size of snapshots and FlexClones, but does not include storage efficiency savings achieved through compression, compaction, and deduplication. To compute storage-efficiency savings in bytes, take the Average of StorageUsed over a given period and subtract it from the Average of LogicalDataStored over the same period. To compute storage-efficiency savings as a percentage of total logical data size, take the Average of StorageUsed over a given period and subtract it from the Average of LogicalDataStored over the same period. Then divide the difference by the Average of LogicalDataStored over the same period. Units: Bytes Valid statistics: Average, Minimum, and Maximum

Detailed file system metrics

Detailed file system metrics are detailed storage-utilization metrics for each of your storage tiers. Detailed file system metrics all have the dimensions FileSystemId, StorageTier, and DataType.

- The StorageTier dimension indicates the storage tier that the metric measures, with possible values of SSD and StandardCapacityPool.

- The `DataType` dimension indicates the type of data that the metric measures, with the possible value `All`.

There is a row for each unique combination of a given metric and dimensional key-value pairs, with a description of what that combination measures.

Metric	Description
`StorageCapacityUtilization`	The storage capacity utilization for each of your file system's aggregates. There is one metric emitted each minute for each of your file system's aggregates. The `Average` statistic is the average amount of storage capacity utilization for your file system's performance tier over the specified period. The `Minimum` statistic is the lowest amount of storage capacity utilization for your file system's performance tier over the specified period. The `Maximum` statistic is the highest amount of storage capacity utilization for your file system's performance tier over the specified period. Units: Percent Valid statistics: `Average`, `Minimum`, and `Maximum`
`StorageCapacity`	The total storage capacity of the primary (SSD) tier. Units: Bytes

Metric	Description
	Valid statistics: `Maximum`
`StorageUsed`	The used physical storage capacity in bytes, specific to the storage tier. This value includes savings from storage-efficiency features, such as data compression and deduplication. Valid dimension values for `StorageTier` are `SSD` and `StandardCapacityPool`, corresponding to the storage tier that this metric measures. This metric also requires the `DataType` dimension with the value `All`. The `Average`, `Minimum`, and `Maximum` statistics are per-tier storage consumption in bytes for the given period. To calculate storage capacity utilization of your primary (SSD) storage tier, divide any of these statistics by the `Maximum` `StorageCapacity` over the same period, with the `StorageTier` dimension equal to `SSD`. To calculate the free storage capacity of your primary (SSD) storage tier in bytes, subtract any of these statistics from the `Maximum` `StorageCapacity` over the same period, with the dimension `StorageTier` equal to `SSD`. Units: Bytes Valid statistics: `Average`, `Minimum`, and `Maximum`

Second-generation file system metrics

The following metrics are provided for FSx for ONTAP second-generation file systems. For the metrics, a datapoint is emitted for each HA pair and for each aggregate (for storage utilization metrics).

> **Note**
>
> If you have a file system with multiple HA pairs, you can also use the single-HA pair file system metrics and the volume metrics.

Topics

- Network I/O metrics
- File server metrics
- Disk I/O metrics
- Detailed file system metrics

Network I/O metrics

All of these metrics take two dimensions, `FileSystemId` and `FileServer`.

- `FileSystemId` – Your file system's AWS resource ID.
- `FileServer` – The name of a file server (or *node*) in ONTAP (for example, `FsxId01234567890abcdef-01`). Odd-numbered file servers are preferred file servers (that is, they service traffic unless the file system has failed over to the secondary file server), while even-numbered file servers are secondary file servers (that is, they serve traffic only when their partner is unavailable). Because of this, secondary file servers typically show less utilization than preferred file servers.

Metric	Description
`NetworkThroughputUtilization`	Network throughput utilization as a percentage of available network throughput for your file system. This metric is equivalent to the maximum of `NetworkSentBytes` and

Metric	Description
	`NetworkReceivedBytes` as a percentage of the network throughput capacity of one HA pair for your file system. All traffic is considered in this metric, including background tasks (such as SnapMirror, tiering, and backups). There is one metric emitted each minute for each of your file system's file servers. The `Average` statistic is the average network throughput utilization for the given file server over the specified period. The `Minimum` statistic is the lowest network throughput utilization for the given file server over one minute, for the specified period. The `Maximum` statistic is the highest network throughput utilization for the given file server over one minute, for the specified period. Units: Percent Valid statistics: `Average`, `Minimum`, and `Maximum`

Metric	Description
NetworkSentBytes	The number of bytes (network IO) sent by your file system. All traffic is considered in this metric, including background tasks (such as SnapMirror, tiering, and backups). There is one metric emitted each minute for each of your file system's file servers. The Sum statistic is the total number of bytes sent over the network by the given file server over the specified period. The Average statistic is the average number of bytes sent over the network by the given file server over the specified period. The Minimum statistic is the lowest number of bytes sent over the network by the given file server over the specified period. The Maximum statistic is the highest number of bytes sent over the network by the given file server over the specified period. To calculate sent throughput (bytes per second) for any statistic, divide the statistic by the seconds in the specified period. Units: Bytes Valid statistics: Sum, Average, Minimum, and Maximum

Metric	Description
NetworkReceivedBytes	The number of bytes (network IO) received by your file system. All traffic is considered in this metric, including background tasks (such as SnapMirror, tiering, and backups). There is one metric emitted each minute for each of your file system's file servers. The Sum statistic is the total number of bytes received over the network by the given file server over the specified period. The Average statistic is the average number of bytes received over the network by the given file server each minute over the specified period. The Minimum statistic is the lowest number of bytes received over the network by the given file server each minute over the specified period. The Maximum statistic is the highest number of bytes received over the network by the given file server each minute over the specified period. To calculate received throughput (bytes per second) for any statistic, divide the statistic by the seconds in the period. Units: Bytes Valid statistics: Sum, Average, Minimum, and Maximum

File server metrics

All of these metrics take two dimensions, `FileSystemId` and `FileServer`.

Metric	Description
`CPUUtilization`	The percent utilization of the file system's CPU resources. There is one metric emitted each minute for each of your file system's file servers. The `Average` statistic is the average CPU utilization of the file system over a specified period. The `Minimum` statistic is the lowest CPU utilization for the given file server over the specified period. The `Maximum` statistic is the highest CPU utilization for the given file server over the specified period. Units: Percent Valid statistics: `Average`, `Minimum`, and `Maximum`
`FileServerDiskThroughputUtilization`	The disk throughput between your file server and aggregate, as a percentage of the provisioned limit determined by throughput capacity. All traffic is considered in this metric, including background tasks (such as SnapMirror, tiering, and backups). This metric is equivalent to the sum of `DiskReadBytes` and `DiskWriteBytes` as a percentage of the file server's disk throughput capacity of one HA pair for your file system. There is one

Metric	Description
	metric emitted each minute for each of your file system's file servers. The `Average` statistic is the average file server disk throughput utilization for the given file server over the specified period. The `Minimum` statistic is the lowest file server disk throughput utilization for the given file server over the specified period. The `Maximum` statistic is the highest file server disk throughput utilization for the given file server over the specified period. Units: Percent Valid statistics: `Average`, `Minimum`, and `Maximum`

Metric	Description
FileServerDiskIopsUtilization	The IOPS utilization of available disk IOPS capacity for your file server, as a percentag e of its disk IOPS limit. This differs from DiskIopsUtilization in that the utilization of disk IOPS out of the maximum that your file server can handle, as opposed to your provisioned disk IOPS. All traffic is considered in this metric, including backgroun d tasks (such as SnapMirror, tiering, and backups). There is one metric emitted each minute for each of your file system's file servers. The Average statistic is the average disk IOPS utilization for the given file server over the specified period. The Minimum statistic is the lowest disk IOPS utilization for the given file server over the specified period. The Maximum statistic is the highest disk IOPS utilization for the given file server over the specified period. Units: Percent Valid statistics: Average, Minimum, and Maximum

Metric	Description
FileServerCacheHitRatio	The percentage of all read requests which are served by data that resides in your file system's RAM or NVMe caches for each of your HA pairs (for example, the active file server in an HA pair). A higher percentage indicates a higher ratio of cached reads to total reads. All I/O is considered, including background tasks (such as SnapMirror, tiering, and backups). There is one metric emitted each minute for each of your file system's file servers. Units: Percent The Average statistic is the average cache hit ratio for one of your file system's HA pairs over the specified period. The Minimum statistic is the lowest cache hit ratio for one of your file system's HA pairs over the specified period. The Maximum statistic is the highest cache hit ratio for one of your file system's HA pairs over the specified period. Valid statistics: Average, Minimum, and Maximum

Disk I/O metrics

All of these metrics take two dimensions, FileSystemId and Aggregate.

- FileSystemId – Your file system's AWS resource ID.
- Aggregate – Your file system's performance tier consists of multiple storage pools called *aggregates*. There is one aggregate for each HA pair. For example, aggregate aggr1

maps to file server `FsxId01234567890abcdef-01` (the active file server) and file server `FsxId01234567890abcdef-02` (the secondary file server) in an HA pair.

Metric	Description
`DiskReadBytes`	The number of bytes (disk IO) from ay disk reads from this aggregate. All traffic is considered in this metric, including backgroun d tasks (such as SnapMirror, tiering, and backups). There is one metric emitted each minute for each of your file system's aggregates. During SSD capacity decrease operations, this metric is reported for both the original aggregate (`aggr1_old`) and the new smaller aggregate (`aggr1`). The `Sum` statistic is the total number of bytes read each minute from the given aggregate over the specified period. The `Average` statistic is the average number of bytes read each minute from the given aggregate over the specified period. The `Minimum` statistic is the lowest number of bytes read each minute from the given aggregate over the specified period. The `Maximum` statistic is the highest number of bytes read each minute from the given aggregate over the specified period. To calculate read disk throughput (bytes per second) for any statistic, divide the statistic by the seconds in the period.

Metric	Description
	Units: Bytes Valid statistics: Sum, `Average`, `Minimum`, and `Maximum`

Metric	Description
DiskWriteBytes	The number of bytes (disk IO) from any disk writes to this aggregate. All traffic is considered in this metric, including background tasks (such as SnapMirror, tiering, and backups). There is one metric emitted each minute for each of your file system's aggregates. During SSD capacity decrease operations, this metric is reported for both the original aggregate (aggr1_old) and the new smaller aggregate (aggr1). The Sum statistic is the total number of bytes written to the given aggregate over the specified period. The Average statistic is the average number of bytes written to the given aggregate each minute over the specified period. The Minimum statistic is the lowest number of bytes written to the given aggregate each minute over the specified period. The Maximum statistic is the highest number of bytes written to the given aggregate each minute over the specified period. To calculate write disk throughput (bytes per second) for any statistic, divide the statistic by the seconds in the specified period. Units: Bytes Valid statistics: Sum, Average, Minimum, and Maximum

Metric	Description
DiskIopsUtilization	The disk IOPS utilization of one aggregate, as a percentage of the aggregate's disk IOPS limit (that is, the file system's total IOPS divided by the number of HA pairs for your file system). This differs from FileServerDiskIops Utilization in that it is the utilization of provisioned disk IOPS against your provision ed IOPS limit, as opposed to the maximum disk IOPS supported by the file server (that is, dictated by your configured throughput capacity per HA pair). All traffic is considere d in this metric, including background tasks (such as SnapMirror, tiering, and backups). There is one metric emitted each minute for each of your file system's aggregates. During SSD capacity decrease operations, this metric is reported for both the original aggregate (aggr1_old) and the new smaller aggregate (aggr1). The Average statistic is the average disk IOPS utilization for the given aggregate over the specified period. The Minimum statistic is the lowest disk IOPS utilization for the given aggregate over the specified period. The Maximum statistic ii the highest disk IOPS utilization for the given aggregate over the specified period. Units: Percent

Metric	Description
	Valid statistics: `Average`, `Minimum`, and `Maximum`

Metric	Description
DiskReadOperations	The number of read operations (disk IO) to this aggregate. All traffic is considered in this metric, including background tasks (such as SnapMirror, tiering, and backups). There is one metric emitted each minute for each of your file system's aggregates. During SSD capacity decrease operations, this metric is reported for both the original aggregate (aggr1_old) and the new smaller aggregate (aggr1). The Sum statistic is the total number of read operations performed by the given aggregate over the specified period. The Average statistic is the average number of read operations performed each minute by the given aggregate over the specified period. The Minimum statistic is the lowest number of read operations performed each minute by the given aggregate over the specified period. The Maximum statistic is the highest number of read operations performed each minute by the given aggregate over the specified period. To calculate average disk IOPS over the period, use the Average statistic and divide the result by 60 (seconds). Units: Count Valid statistics: Sum, Average, Minimum, and Maximum

Metric	Description
DiskWriteOperations	The number of write operations (disk IO) to this aggregate. All traffic is considered in this metric, including background tasks (such as SnapMirror, tiering, and backups). There is one metric emitted each minute for each of your file system's aggregates. During SSD capacity decrease operations, this metric is reported for both the original aggregate (aggr1_old) and the new smaller aggregate (aggr1). The Sum statistic is the total number of write operations performed by the given aggregate over the specified period. The Average statistic is the average number of write operations performed each minute by the given aggregate over the specified period. To calculate average disk IOPS over the period, use the Average statistic and divide the result by 60 (seconds). Units: Count Valid statistics: Sum and Average

Detailed file system metrics

Detailed file system metrics are detailed storage-utilization metrics for each of your storage tiers. Detailed file system metrics have either the FileSystemId, StorageTier, and DataType dimensions, or the FileSystemId, StorageTier, DataType, and Aggregate dimensions.

- When the Aggregate dimension is not supplied, the metrics are for your entire file system. The StorageUsed and StorageCapacity metrics have a single data point each minute

corresponding to the file system's total consumed storage (per storage tier) and total storage capacity (for the SSD tier). Meanwhile, the `StorageCapacityUtilization` metric emits one metric each minute for each aggregate.

- When the `Aggregate` dimension is supplied, the metrics are for each aggregate.

The meaning of the dimensions are as follows:

- `FileSystemId` – Your file system's AWS resource ID.
- `Aggregate` – Your file system's performance tier consists of multiple storage pools called *aggregates*. There is one aggregate for each HA pair. For example, aggregate `aggr1` maps to file server `FsxId01234567890abcdef-01` (the active file server) and file server `FsxId01234567890abcdef-02` (the secondary file server) in an HA pair.
- `StorageTier` – Indicates the storage tier that the metric measures, with possible values of `SSD` and `StandardCapacityPool`.
- `DataType` – Indicates the type of data that the metric measures, with the possible value `All`.

There is a row for each unique combination of a given metric and dimensional key-value pairs, with a description of what that combination measures.

Metric	Description
`StorageCapacityUtilization`	The storage capacity utilization for a given file system aggregate. There is one metric emitted each minute for each of your file system's aggregates. The `Average` statistic is the average amount of storage capacity utilization for a given aggregate over the specified period. The `Minimum` statistic is the minimum amount of storage capacity utilization for a given aggregate over the specified period.

Metric	Description
	The `Maximum` statistic is the maximum amount of storage capacity utilization for a given aggregate over the specified period. During SSD capacity decrease operations, this metric is reported for both the original aggregate (`aggr1_old`) and the new smaller aggregate (`aggr1`). Units: Percent Valid statistics: `Average`, `Minimum`, and `Maximum`

Metric	Description
StorageCapacity	The storage capacity for a given file system aggregate. There is one metric emitted each minute for each of your file system's aggregates. The Average statistic is the average amount of storage capacity for a given aggregate over the specified period. The Minimum statistic is the minimum amount of storage capacity for a given aggregate over the specified period. The Maximum statistic is the maximum amount of storage capacity for a given aggregate over the specified period. During SSD capacity decrease operations, this metric is reported for both the original aggregate (aggr1_old) and the new smaller aggregate (aggr1). Units: Bytes Valid statistics: Average, Minimum, and Maximum

Metric	Description
StorageUsed	The used physical storage capacity in bytes, specific to the storage tier. This value includes savings from storage-efficiency features, such as data compression and deduplication. Valid dimension values for StorageTier are SSD and StandardCapacityPool , corresponding to the storage tier that this metric measures. There is one metric emitted each minute for each of your file system's aggregates. The Average statistic is the average amount of physical storage capacity consumed on the given storage tier by the given aggregate over the specified period. The Minimum statistic is the minimum amount of physical storage capacity consumed on the given storage tier by the given aggregate over the specified period. The Maximum statistic is the maximum amount of physical storage capacity consumed on the given storage tier by the given aggregate over the specified period. During SSD capacity decrease operations, this metric is reported for both the original aggregate (aggr1_old) and the new smaller aggregate (aggr1). Units: Bytes Valid statistics: Average, Minimum, and Maximum

Volume metrics

Your Amazon FSx for NetApp ONTAP file system can have one or more volumes that store your data. Each of these volumes has a set of CloudWatch metrics, classified as either **Volume metrics** or **Detailed volume metrics**.

- **Volume metrics** are per-volume performance and storage metrics that take two dimensions, `FileSystemId` and `VolumeId`. `FileSystemId` maps to the file system that the volume belongs to.
- **Detailed volume metrics** are per-storage-tier metrics that measure storage consumption per tier with the `StorageTier` dimension (with possible values of `SSD` and `StandardCapacityPool`) and per data type with the `DataType` dimension (with possible values of `User`, `Snapshot`, and `Other`). These metrics have the `FileSystemId`, `VolumeId`, `StorageTier`, and `DataType` dimensions.

Topics

- Network I/O metrics
- Storage capacity metrics
- Detailed volume metrics

Network I/O metrics

All of these metrics take two dimensions, `FileSystemId` and `VolumeId`.

Metric	Description
`DataReadBytes`	The number of bytes (network I/O) read from the volume by clients. The `Sum` statistic is the total number of bytes associated with read operations during the specified period. To calculate the average throughput (bytes per second) for a period, divide the `Sum` statistic by the number of seconds in the specified period. Units: Bytes

Metric	Description
	Valid statistics: Sum
DataWriteBytes	The number of bytes (network I/O) written to the volume by clients. The Sum statistic is the total number of bytes associated with write operations during the specified period. To calculate the average throughput (bytes per second) for a period, divide the Sum statistic by the number of seconds in the specified period. Units: Bytes Valid statistics: Sum
DataReadOperations	The number of read operations (network I/O) on the volume by clients. The Sum statistic is the total number of read operations during the specified period. To calculate the average read operations per second for a period, divide the Sum statistic by the number of seconds in the specified period. Units: Count Valid statistics: Sum

Metric	Description
DataWriteOperations	The number of write operations (network I/O) on the volume by clients. The Sum statistic is the total number of write operations during the specified period. To calculate the average write operations per second for a period, divide the Sum statistic by the number of seconds in the specified period. Units: Count Valid statistics: Sum
MetadataOperations	The number of I/O operations (network I/O) from metadata activities by clients to the volume. The Sum statistic is the total number of metadata operations during the specified period. To calculate the average metadata operations per second for a period, divide the Sum statistic by the number of seconds in the specified period. Units: Count Valid statistics: Sum

Metric	Description
DataReadOperationTime	The sum of total time spent within the volume for read operations (network I/O) from clients accessing data in the volume. The Sum statistic is the total number of seconds spent by read operations during the specified period. To calculate the average read latency for a period, divide the Sum statistic by the Sum of the DataReadOperations metric over the same period. Units: Seconds Valid statistics: Sum
DataWriteOperationTime	The sum of total time spent within the volume for fulfilling write operations (network I/O) from clients accessing data in the volume. The Sum statistic is the total number of seconds spent by write operations during the specified period. To calculate the average write latency for a period, divide the Sum statistic by the Sum of the DataWrite Operations metric over the same period. Units: Seconds Valid statistics: Sum

Metric	Description
MetadataOperationTime	The sum of total time spent within the volume for fulfilling metadata operations (network I/O) from clients that are accessing data in the volume. The Sum statistic is the total number of seconds spent by read operations during the specified period. To calculate the average latency for a period, divide the Sum statistic by the Sum of the MetadataOperations over the same period. Units: Seconds Valid statistics: Sum
CapacityPoolReadBytes	The number of bytes read (network I/O) from the volume's capacity pool tier. To ensure data integrity, ONTAP performs a read operation on the capacity pool immediately after performing a write operation. The Sum statistic is the total number of bytes read from the volume's capacity pool tier over a specified period. To calculate capacity pool bytes per second, divide the Sum statistic by the seconds in a specified period. Units: Bytes Valid statistics: Sum

Metric	Description
CapacityPoolReadOperations	The number of read operations (network I/O) from the volume's capacity pool tier. This translates to a capacity pool read request. To ensure data integrity, ONTAP performs a read operation on the capacity pool immediately after performing a write operation. The Sum statistic is the total number of read operations from the volume's capacity pool tier over a specified period. To calculate capacity pool requests per second, divide the Sum statistic by the seconds in a specified period. Units: Count Valid statistics: Sum
CapacityPoolWriteBytes	The number of bytes written (network I/O) to the volume's capacity pool tier. To ensure data integrity, ONTAP performs a read operation on the capacity pool immediately after performing a write operation. The Sum statistic is the total number of bytes written to the volume's capacity pool tier over a specified period. To calculate capacity pool bytes per second, divide the Sum statistic by the seconds in a specified period. Units: Bytes Valid statistics: Sum

Metric	Description
CapacityPoolWriteOperations	The number of write operations (network I/O) to the volume from the capacity pool tier. This translates to a write request. To ensure data integrity, ONTAP performs a read operation on the capacity pool immediately after performing a write operation. The Sum statistic is the total number of write operations to the volume's capacity pool tier over a specified period. To calculate capacity pool requests per second, divide the Sum statistic by the seconds in a specified period. Units: Count Valid statistics: Sum

Storage capacity metrics

All of these metrics take two dimensions, FileSystemId and VolumeId.

Metric	Description
StorageCapacity	The size of the volume in bytes. Units: Bytes Valid statistics: Maximum
StorageUsed	The used logical storage capacity of the volume. Units: Bytes Valid statistics: Average

Metric	Description
StorageCapacityUtilization	The storage capacity utilization of the volume. Units: Percent Valid statistics: Average
FilesUsed	The used files (number of files or inodes) on the volume. Units: Count Valid statistics: Average
FilesCapacity	The total number of inodes that can be created on the volume. Units: Count Valid statistics: Maximum

Detailed volume metrics

Detailed volume metrics take more dimensions than volume metrics, enabling more granular measurements of your data. All detailed volume metrics have the dimensions FileSystemId, VolumeId, StorageTier, and DataType.

- The StorageTier dimension indicates the storage tier that the metric measures, with possible values of All, SSD, and StandardCapacityPool.
- The DataType dimension indicates the type of data that the metric measures, with possible values of All, User, Snapshot, and Other.

The following table defines what the StorageUsed metric measures for the listed dimensions.

Metric	Description
StorageUsed	The amount of logical space used, in bytes. This metric measures different types of space consumption depending on the dimensions used with this metric. When setting StorageTier to SSD or StandardCapacityPool, and setting DataType to All, this metric measures the logical space usage for this volume for your SSD and capacity pool tiers, respectively. When setting the DataType dimension to User, Snapshot, or Other, and setting StorageTier to All, this metric measures the logical space usage for each respective type of data. The Snapshot data consumption includes the snapshot reserve, which is 5% of the volume's size by default. Units: Bytes Valid statistics: Average, Minimum, and Maximum
StorageCapacityUtilization	The percentage of the volume's used physical disk space. Units: Percent Valid statistics: Maximum

Monitoring FSx for ONTAP EMS events

You can monitor FSx for ONTAP file system events using NetAPP ONTAP's native Events Management System (EMS). You can view these events using the NetApp ONTAP CLI.

Topics

- Overview of EMS events
- Viewing EMS events
- EMS event forwarding to a Syslog server

Overview of EMS events

EMS events are automatically generated notifications that alert you when a predefined condition occurs in your FSx for ONTAP file system. These notifications keep you informed so that you can prevent or correct issues that can lead to larger problems, such as storage virtual machine (SVM) authentication issues or full volumes.

By default, events are logged in the Event Management System log. Using EMS, you can monitor events such as user password changes, a constituent within a FlexGroup approaching full capacity, a Logical Unit Number (LUN) was manually brought online or offline, or a volume automatically resizing.

For more information about ONTAP EMS events, see ONTAP EMS Reference in the NetApp ONTAP Documentation Center. To display the event categories, use the document's left navigation pane.

> **Note**
>
> Only some ONTAP EMS messages are available for FSx for ONTAP file systems. To view a list of the available ONTAP EMS messages, use the NetApp ONTAP CLI event catalog show command.

EMS event descriptions contain event names, severity, possible causes, log messages, and corrective actions that can help you decide how to respond. For example, a wafl.vol.autoSize.fail event occurs when automatic sizing of a volume fails. According to the event description, the corrective action is to increase the maximum size of the volume while setting the autosize.

Viewing EMS events

Use the NetApp ONTAP CLI event log show command to display the contents of the events log. This command is available if you have the `fsxadmin` role on your file system. The command syntax is as follows:

```
event log show [event_options]
```

The most recent events are listed first. By default, this command displays EMERGENCY, ALERT, and ERROR severity-level events with the following information:

- **Time** – The time of the event.
- **Node** – The node on which the event occurred.
- **Severity** – The severity level of the event. To display NOTICE, INFORMATIONAL, or DEBUG severity-level events, use the `-severity` option.
- **Event** – The event name and message.

To display detailed information about events, use one or more of the event options listed in the following table.

Event option	Description
`-detail`	Displays additional event information.
`-detailtime`	Displays detailed event information in reverse chronological order.
`-instance`	Displays detailed information about all fields.
`-node` *`nodename`*`|local`	Displays a list of events for the node that you specify. Use this option with `-seqnum` to display detailed information.
`-seqnum` *`sequence_number`*	Selects the events that match this number in the sequence. Use with `-node` to display detailed information.
`-time` *`MM/DD/YYYY HH:MM:SS`*	Selects the events that happened at this specific time. Use the format: MM/

Event option	Description

	DD/YYYY HH:MM:SS [+-HH:MM]. You can specify a time range by using the `..` operator between two time statements.
	
	`event log show -time "04/17/2023 05:55:00".."04/17/2023 06:10:00"`
	
	Comparative time values are relative to the current time when you run the command. The following example shows how to display only events that occurred within the last minute:
	
	`event log show -time >1m`
	
	The month and date fields of this option are not zero-padded. These fields can be single digits; for example, `4/1/2023 06:45:00`.

Event option	Description
`-severity` *sev_level*	Selects the events that match the *sev_level* value, which must be one of the following: • `EMERGENCY` – Disruption • `ALERT` – Single point of failure • `ERROR` – Degradation • `NOTICE` – Information • `INFORMATIONAL` – Information • `DEBUG` – Debug information To display all events, specify severity as follows: `event log show -severity <=DEBUG`

Event option	Description
`-ems-severity` *ems_sev_level*	Selects the events that match the *ems_sev_level* value, which must be one of the following: • NODE_FAULT – Data corruption is detected or the node is unable to provide client service. • SVC_FAULT – A temporary loss of service—typically a transient software fault—is detected. • NODE_ERROR – A hardware error that's not immediately fatal is detected. • SVC_ERROR – A software error that's not immediately fatal is detected. • WARNING – A high-priority message that doesn't indicate a fault. • NOTICE – A normal-priority message that doesn't indicate a fault. • INFO – A low-priority message that doesn't indicate a fault. • DEBUG – A debugging message.

Event option	Description
	• VAR – A message with variable severity, selected at runtime. To display all events, specify severity as follows: `event log show -ems-severity <=DEBUG`
`-source` *text*	Selects the events that match the *text* value. The source is typically a software module.
`-message-name` *message_name*	Selects the events that match the *message_name* value. Message names are descriptive, so filtering output by message name displays messages of a specific type.
`-event` *text*	Selects the events that match the *text* value. The `event` field contains the full text of the event, including any parameters.
`-kernel-generation-num` *integer*	Selects the events that match the *integer* value. Only events that come from the kernel have kernel generation numbers.

Event option	Description
`-kernel-sequence-num` *integer*	Selects the events that match the *integer* value. Only events that come from the kernel have kernel sequence numbers.
`-action` *text*	Selects the events that match the *text* value. The `action` field describes what corrective action, if any, you must take to remedy the situation.
`-description` *text*	Selects the events that match the *text* value. The `description` field describes why the event happened and what it means.
`-filter-name` *filter_name*	Selects the events that match the *filter_name* value. Only events that are included by existing filters that match this value display.
`-fields` *fieldname* `,...`	Indicates that the command output also includes the specified field or fields. You can use `-fields ?` to choose the fields that you want to specify.

To view EMS events

1. To SSH into the NetApp ONTAP CLI of your file system, follow the steps documented in the Using the NetApp ONTAP CLI section of the *Amazon FSx for NetApp ONTAP User Guide*.

```
ssh fsxadmin@file-system-management-endpoint-ip-address
```

2. Use the `event log show` command to display the contents of the event log.

```
::> event log show
Time                 Node          Severity      Event
-------------------- ------------ ------------ -----------------------
6/30/2023 13:54:19  node1         NOTICE        vifmgr.portup: A link up event was
 received on node node1, port e0a.
6/30/2023 13:54:19  node1         NOTICE        vifmgr.portup: A link up event was
 received on node node1, port e0d.
```

For information about the EMS events returned by the `event log show` command, refer to the ONTAP EMS Reference in the NetApp ONTAP Documentation Center.

EMS event forwarding to a Syslog server

You can configure EMS events to forward notifications to a Syslog server. EMS event forwarding is used for real-time monitoring of your file system to determine and isolate root causes for a wide range of issues. If your environment doesn't already contain a Syslog server for event notifications, you must first create one. The Syslog destination must be specified by IP address; hostname-based destinations are not supported.

> **Note**
>
> Your Syslog destination must be located in the primary subnet that is used by your file system.

To configure EMS events to forward notifications to a Syslog server

1. To SSH into the NetApp ONTAP CLI of your file system, follow the steps documented in the Using the NetApp ONTAP CLI section of the *Amazon FSx for NetApp ONTAP User Guide*.

```
ssh fsxadmin@file-system-management-endpoint-ip-address
```

2. Use the event notification destination create command to create an event notification destination of type `syslog`, specifying the following attributes:

- *dest_name* – The name of the notification destination that is to be created (for example, `syslog-ems`). An event notification destination name must be 2 to 64 characters long. Valid characters are the following ASCII characters: A-Z, a-z, 0-9, "_", and "-". The name must start and end with: A-Z, a-z, or 0-9.
- *syslog_name* – The IP address of the Syslog server that Syslog messages are sent to. Hostnames are not supported.
- *transport_protocol* – The protocol used to send the events:
  - `udp-unencrypted` – User Datagram Protocol with no security. This is the default protocol.
  - `tcp-unencrypted` – Transmission Control Protocol with no security.
  - `tcp-encrypted` – Transmission Control Protocol with Transport Layer Security (TLS). When this option is specified, FSx for ONTAP verifies the identity of the destination host by validating its certificate.
- *port_number* – The Syslog server port that Syslog messages are sent to. The default value `syslog-port` parameter depends on the setting for the `syslog-transport` parameter. If `syslog-transport` is set to `tcp-encrypted`, the `syslog-port` default value is `6514`. If `syslog-transport` is set to `tcp-unencrypted`, `syslog-port` has the default value `601`. Otherwise, the default port is set to `514`.

```
::> event notification destination create -name dest_name -syslog syslog_name -
syslog-transport transport_protocol -syslog-port port_number
```

3. Use the event notification create command to create a new notification of a set of events defined by an event filter to the notification destination created in the previous step, specifying the following attributes:

- *node_name* – The name of the event filter. Events that are included in the event filter are forwarded to the destinations specified in the `-destinations` parameter.
- *dest_name* – The name of the existing notification destination that the event notifications are sent to.

```
::> event notification create -filter-name filter_name -destinations dest_name
```

4. If you selected TCP as the *transport_protocol*, you can use the `event notification destination check` command to generate a test message and verify your setup works. Specify the following attributes with the command:

   - *node_name* – The name of the node (for example, `FsxId07353f551e6b557b4-01`).
   - *dest_name* – The name of the existing notification destination that the event notifications are sent to.

```
::> set diag
::*> event notification destination check -node node_name -destination-
name dest_name
```

Monitoring with Data Infrastructure Insights

NetApp Data Infrastructure Insights (formerly Cloud Insights) is a NetApp service that you can use to monitor your Amazon FSx for NetApp ONTAP file systems alongside your other NetApp storage solutions. With Data Infrastructure Insights, you can monitor configuration, capacity, and performance metrics over time to understand your workload's trends and plan for future performance and storage capacity needs. You can also create alerts based on metric conditions that can integrate with your existing workflows and productivity tools.

> **Note**
>
> Data Infrastructure Insights isn't supported for second-generation file systems with more than one HA pair.

Data Infrastructure Insights provides:

- **A breadth of metrics and logs** – Collect configuration, capacity, and performance metrics. Understand how your workload is trending with predefined dashboards, alerts, and reports.
- **User analytics and ransomware protection** – With Cloud Secure and ONTAP snapshots you can audit, detect, stop, and repair incidents of user error and ransomware.
- **SnapMirror reporting** – Understand your SnapMirror relationships and set alerts on replication issues.

- **Capacity planning** – Understand the resource requirements of on-premises workloads to help you migrate your workload to a more efficient FSx for ONTAP configuration. You can also use these insights to plan for when more performance or capacity will be needed for your FSx for ONTAP deployment.

For more information, see Data Infrastructure Insights documentation in the NetApp ONTAP Product Documentation.

Monitoring FSx for ONTAP file systems using Harvest and Grafana

NetApp Harvest is an open source tool for gathering performance and capacity metrics from ONTAP systems, and is compatible with FSx for ONTAP. You can use Harvest with Grafana for an open source monitoring solution.

Getting started with Harvest and Grafana

The following section details how you can set up and configure Harvest and Grafana to measure your FSx for ONTAP file system's performance and storage capacity utilization.

You can monitor your Amazon FSx for NetApp ONTAP file system by using Harvest and Grafana. NetApp Harvest monitors ONTAP data centers by collecting performance, capacity, and hardware metrics from FSx for ONTAP file systems. Grafana provides a dashboard where the collected Harvest metrics can be displayed.

Supported Harvest dashboards

Amazon FSx for NetApp ONTAP exposes a different set of metrics than does on-premises NetApp ONTAP. Therefore, only the following out-of-the-box Harvest dashboards tagged with `fsx` are currently supported for use with FSx for ONTAP. Some of the panels in these dashboards may be missing information that is not supported.

- Harvest: Metadata
- ONTAP: Aggregate
- ONTAP: cDOT
- ONTAP: Cluster
- ONTAP: Compliance

- ONTAP: Datacenter
- ONTAP: Data Protection
- ONTAP: LUN
- ONTAP: Network
- ONTAP: Node
- ONTAP: Qtree
- ONTAP: Security
- ONTAP: SnapMirror
- ONTAP: SnapMirror Destinations
- ONTAP: SnapMirror Sources
- ONTAP: SVM
- ONTAP: Volume
- ONTAP: Volume by SVM
- ONTAP: Volume Deep Dive

The following Harvest dashboards are supported by FSx for ONTAP, but are not enabled by default in Harvest.

- ONTAP: FlexCache
- ONTAP: FlexGroup
- ONTAP: NFS Clients
- ONTAP: NFSv4 Storepool Monitors
- ONTAP: NFS Troubleshooting
- ONTAP: NVMe Namespaces
- ONTAP: SMB
- ONTAP: Workload

Unsupported Harvest dashboards

The following Harvest dashboards are *not* supported by FSx for ONTAP.

- ONTAP: Disk

- ONTAP: External Service Operation
- ONTAP: File Systems Analytics (FSA)
- ONTAP: Headroom
- ONTAP: Health
- ONTAP: MAV Request
- ONTAP: MetroCluster
- ONTAP: Power
- ONTAP: Shelf
- ONTAP: S3 Object Stores

CloudFormation template

To get started, you can deploy an CloudFormation template that automatically launches an Amazon EC2 instance running Harvest and Grafana. As an input to the CloudFormation template, you specify the `fsxadmin` user and the Amazon FSx management endpoint for the file system which will be added as part of this deployment. After the deployment is completed, you can log in to the Grafana dashboard to monitor your file system.

This solution uses CloudFormation to automate the deployment of the Harvest and Grafana solution. The template creates an Amazon EC2 Linux instance and installs Harvest and Grafana software. To use this solution, download the fsx-ontap-harvest-grafana.template CloudFormation template.

> **Note**
>
> Implementing this solution incurs billing for the associated AWS services. For more information, see the pricing details pages for those services.

Amazon EC2 instance types

When configuring the template, you provide the Amazon EC2 instance type. NetApp's recommendation for the instance size depends on how many file systems you monitor and the number of metrics you choose to collect. With the default configuration, for each 10 file systems you monitor, NetApp recommends:

- CPU: 2 cores
- Memory: 1 GB
- Disk: 500 MB (mostly used by log files)

Following are some sample configurations and the `t3` instance type you might choose.

File systems	CPU	Disk	Instance type
Under 10	2 cores	500 MB	`t3.micro`
10–40	4 cores	1000 MB	`t3.xlarge`
40+	8 cores	2000 MB	`t3.2xlarge`

For more information on Amazon EC2 instance types, see General purpose instances in the *Amazon EC2 User Guide*.

Instance port rules

When you set up your Amazon EC2 instance, make sure that ports 3000 and 9090 are open for inbound traffic for the security group that the Amazon EC2 Harvest and Grafana instance is in. Because the instance that is launched connects to an endpoint over HTTPS, it needs to resolve the endpoint, which needs port 53 TCP/UDP for DNS. Additionally, to reach the endpoint it needs port 443 TCP for HTTPS and Internet Access.

Deployment procedure

The following procedure configures and deploys the Harvest/Grafana solution. It takes about five minutes to deploy. Before you start, you must have an FSx for ONTAP file system running in an Amazon Virtual Private Cloud (Amazon VPC) in your AWS account, and the parameter information for the template listed below. For more information on creating a file system, see Creating file systems.

To launch the Harvest/Grafana solution stack

1. Download the fsx-ontap-harvest-grafana.template CloudFormation template. For more information on creating an CloudFormation stack, see Creating a stack on the AWS CloudFormation console in the *AWS CloudFormation User Guide*.

> **Note**
>
> By default, this template launches in the US East (N. Virginia) AWS Region. You must launch this solution in an AWS Region where Amazon FSx is available. For more information, see Amazon FSx endpoints and quotas in the *AWS General Reference.*

2. For **Parameters**, review the parameters for the template and modify them for the needs of your file system. This solution uses the following default values.

Parameter	Default	Description
InstanceType	`t3.micro`	The Amazon EC2 instance type. Following are the `t3` instance types. • `t3.micro` • `t3.small` • `t3.medium` • `t3.large` • `t3.xlarge` • `t3.2xlarge` For the complete list of allowed Amazon EC2 instance type values for this parameter, see the fsx-ontap-harvest-grafana.template.
KeyPair	No default value	The key pair that is used to access the Amazon EC2 instance.
SecurityGroup	No default value	The Security group ID for the Harvest/Grafana

Parameter	Default	Description
		Instance. Ensure Inbound ports 3000 and 9090, in addition to ports 53 and 443, are open from the clients you wish to use to access your Grafana dashboard.
Subnet Type	No default value	Specify the subnet type, either `public` or `private`. Use a `public` subnet for resources that must be connected to the internet, and a private subnet for resources that won't be connected to the internet. For more information, see Subnet types in the *Amazon VPC User Guide*.
Subnet	No default value	Specify the same subnet as your Amazon FSx for NetApp ONTAP file system's preferred subnet. You can find the file system's **Preferred subnet** ID in the Amazon FSx console, in the **Network & security** tab of the FSx for ONTAP file system details page
LatestLinuxAmiId	`/aws/service/ami-amazon-linux-latest/amzn2-ami-hvm-x86_64-gp2`	The latest version of the Amazon Linux 2 AMI in a given AWS Region.

Parameter	Default	Description
FSxEndPoint	No default value	The file system's Management endpoint IP address. You can find the file system's management endpoint **IP address** in the Amazon FSx console, in the **Administration** tab of the FSx for ONTAP file system details page.
SecretName	No default value	AWS Secrets Manager secret name containing the password for the file system's `fsxadmin` user. This is the password you provided when you created the file system.

3. Choose **Next**.
4. For **Options**, choose **Next**.
5. For **Review**, review and confirm the settings. You must select the check box acknowledging that the template create IAM resources.
6. Choose **Create** to deploy the stack.

You can view the status of the stack in the CloudFormation console in the **Status** column. You should see a status of **CREATE_COMPLETE** in about five minutes.

Logging in to Grafana

After the deployment has finished, use your browser to log in to the Grafana dashboard at the IP and port 3000 of the Amazon EC2 instance:

```
http://EC2_instance_IP:3000
```

When prompted, use the Grafana default user name (`admin`) and password (`pass`). We recommend that you change your password as soon as you log in.

For more information, see the NetApp Harvest page on GitHub.

Troubleshooting Harvest and Grafana

If you are encountering any data missing mentioned in Harvest and Grafana dashboards or are having trouble setting up Harvest and Grafana with FSx for ONTAP, check the following topics for a potential solution.

Topics

- SVM and volume dashboards are blank
- CloudFormation stack rolled back after timeout

SVM and volume dashboards are blank

If the CloudFormation stack deployed successfully and can contact Grafana but the SVM and volume dashboards are blank, use the following procedure to troubleshoot your environment. You will need SSH access to the Amazon EC2 instance that Harvest and Grafana is deployed on.

1. SSH into the Amazon EC2 instance that your Harvest and Grafana clients are running on.

   ```
   [~]$ ssh ec2-user@ec2_ip_address
   ```

2. Use the following command to open the `harvest.yml` file and:

   - Verify that an entry was created for your FSx for ONTAP instance as `Cluster-2`.
   - Verify that the entries for username and password match your `fsxadmin` credentials.

   ```
   [ec2-user@ip-ec2_ip_address ~]$ sudo cat /home/ec2-user/harvest_install/harvest/
   harvest.yml
   ```

3. If the password field is blank, open the file in an editor and update it with the `fsxadmin` password, as follows:

   ```
   [ec2-user@ip-ec2_ip_address ~]$ sudo vi /home/ec2-user/harvest_install/harvest/
   harvest.yml
   ```

4. Ensure the `fsxadmin` user credentials are stored in Secrets Manager in the following format for any future deployments, replacing *`fsxadmin_password`* with your password.

```
{"username" : "fsxadmin", "password" : "fsxadmin_password"}
```

CloudFormation stack rolled back after timeout

If you are unable to deploy the CloudFormation stack successfully and it is rolling back with errors, use the following procedure to resolve the issue. You will need SSH access to the EC2 instance deployed by the CloudFormation stack.

1. Redeploy the CloudFormation stack, making sure that automatic rollback is disabled.
2. SSH into the Amazon EC2 instance that your Harvest and Grafana clients are running on.

```
[~]$ ssh ec2-user@ec2_ip_address
```

3. Verfy that the docker containers were successfully started using the following command.

```
[ec2-user@ip-ec2_ip_address ~]$ sudo docker ps
```

In the response you should see five containers as follows:

```
CONTAINER ID   IMAGE                    COMMAND                  CREATED
 STATUS                          PORTS                     NAMES
6b9b3f2085ef   rahulguptajss/harvest   "bin/poller --config…"   8 minutes ago
 Restarting (1) 20 seconds ago                             harvest_cluster-2
3cf3e3623fde   rahulguptajss/harvest   "bin/poller --config…"   8 minutes ago   Up
 About a minute                                            harvest_cluster-1
708f3b7ef6f8   grafana/grafana         "/run.sh"                8 minutes ago   Up
 8 minutes                   0.0.0.0:3000->3000/tcp   harvest_grafana
0febee61cab7   prom/alertmanager       "/bin/alertmanager -…"   8
 minutes ago   Up 8 minutes                    0.0.0.0:9093->9093/tcp
 harvest_prometheus_alertmanager
1706d8cd5a0c   prom/prometheus         "/bin/prometheus --c…"   8 minutes ago   Up
 8 minutes                   0.0.0.0:9090->9090/tcp   harvest_prometheus
```

4. If the docker containers are not running, check for failures in the `/var/log/cloud-init-output.log` file as follows.

```
[ec2-user@ip-ec2_ip_address ~]$ sudo cat /var/log/cloud-init-output.log
     PLAY [Manage Harvest]
 ************************************************************

TASK [Gathering Facts] ************************************************************
ok: [localhost]

TASK [Verify images] ************************************************************
failed: [localhost] (item=prom/prometheus) => {"ansible_loop_var": "item",
 "changed": false, "item": "prom/prometheus",
"msg": "Error connecting: Error while fetching server API version: ('Connection
 aborted.', ConnectionResetError(104, 'Co
nnection reset by peer'))"}
failed: [localhost] (item=prom/alertmanager) => {"ansible_loop_var": "item",
 "changed": false, "item": "prom/alertmanage
r", "msg": "Error connecting: Error while fetching server API version: ('Connection
 aborted.', ConnectionResetError(104,
'Connection reset by peer'))"}
failed: [localhost] (item=rahulguptajss/harvest) => {"ansible_loop_var": "item",
 "changed": false, "item": "rahulguptajs
s/harvest", "msg": "Error connecting: Error while fetching server API version:
 ('Connection aborted.', ConnectionResetEr
ror(104, 'Connection reset by peer'))"}
failed: [localhost] (item=grafana/grafana) => {"ansible_loop_var": "item",
 "changed": false, "item": "grafana/grafana",
"msg": "Error connecting: Error while fetching server API version: ('Connection
 aborted.', ConnectionResetError(104, 'Co
nnection reset by peer'))"}

PLAY RECAP ************************************************************************
localhost                  : ok=1    changed=0    unreachable=0    failed=1
 skipped=0    rescued=0    ignored=0
```

5. If there are failures, execute the following commands to deploy the Harvest and Grafana containers.

```
[ec2-user@ip-ec2_ip_address ~]$ sudo su
     [ec2-user@ip-ec2_ip_address ~]$ cd /home/ec2-user/harvest_install
     [ec2-user@ip-ec2_ip_address ~]$ /usr/local/bin/ansible-playbook
 manage_harvest.yml
     [ec2-user@ip-ec2_ip_address ~]$ /usr/local/bin/ansible-playbook
 manage_harvest.yml --tags api
```

6. Validate the containers started successfully by running **sudo docker ps** and connecting to your Harvest and Grafana URL.

Monitoring FSx for ONTAP API Calls with AWS CloudTrail

Amazon FSx is integrated with AWS CloudTrail, a service that provides a record of actions taken by a user, role, or an AWS service in Amazon FSx. CloudTrail captures all Amazon FSx API calls for Amazon FSx for NetApp ONTAP as events. Captured calls include calls from the Amazon FSx console and from code calls to Amazon FSx API operations.

If you create a trail, you can enable continuous delivery of CloudTrail events to an Amazon S3 bucket, including events for Amazon FSx. If you don't configure a trail, you can still view the most recent events in the CloudTrail console in **Event history**. Using the information collected by CloudTrail, you can determine the request that was made to Amazon FSx. You can also determine the IP address from which the request was made, who made the request, when it was made, and additional details.

To learn more about CloudTrail, see the AWS CloudTrail User Guide.

Amazon FSx Information in CloudTrail

CloudTrail is enabled on your AWS account when you create the account. When API activity occurs in Amazon FSx, that activity is recorded in a CloudTrail event along with other AWS service events in **Event history**. You can view, search, and download recent events in your AWS account. For more information, see Viewing events with CloudTrail Event history.

For an ongoing record of events in your AWS account, including events for Amazon FSx, create a trail. A *trail* enables CloudTrail to deliver log files to an Amazon S3 bucket. By default, when you create a trail in the console, the trail applies to all AWS Regions. The trail logs events from all AWS Regions in the AWS partition and delivers the log files to the Amazon S3 bucket that you specify. Additionally, you can configure other AWS services to further analyze and act upon the event data collected in CloudTrail logs. For more information, see the following topics in the *AWS CloudTrail User Guide:*

- Creating a trail for your AWS account
- AWS service integrations with CloudTrail Logs
- Configuring Amazon SNS notifications for CloudTrail

- Receiving CloudTrail log files from multiple regions and Receiving CloudTrail log files from multiple accounts

All Amazon FSx API calls are logged by CloudTrail. For example, calls to the `CreateFileSystem` and `TagResource` operations generate entries in the CloudTrail log files.

Every event or log entry contains information about who generated the request. The identity information helps you determine the following:

- Whether the request was made with root or AWS Identity and Access Management (IAM) user credentials.
- Whether the request was made with temporary security credentials for a role or federated user.
- Whether the request was made by another AWS service.

For more information, see the CloudTrail userIdentity element in the *AWS CloudTrail User Guide.*

Understanding Amazon FSx Log File Entries

A *trail* is a configuration that enables delivery of events as log files to an Amazon S3 bucket that you specify. CloudTrail log files contain one or more log entries. An *event* represents a single request from any source and includes information about the requested action, the date and time of the action, request parameters, and so on. CloudTrail log files aren't an ordered stack trace of the public API calls, so they don't appear in any specific order.

The following example shows a CloudTrail log entry that demonstrates the `TagResource` operation when a tag for a file system is created from the console.

```
{
    "eventVersion": "1.05",
    "userIdentity": {
        "type": “Root”,
        "principalId": “111122223333”,
        "arn": "arn:aws:sts::111122223333:root”,
        "accountId": “111122223333”,
        "accessKeyId": "AKIAIOSFODNN7EXAMPLE”,
        "sessionContext": {
            "attributes": {
                "mfaAuthenticated": "false",
                "creationDate": "2018-11-14T22:36:07Z"
```

```
            }
        }
    },
    "eventTime": "2018-11-14T22:36:07Z",
    "eventSource": "fsx.amazonaws.com",
    "eventName": "TagResource",
    "awsRegion": "us-east-1",
    "sourceIPAddress": “192.0.2.0”,
    "userAgent": “console.amazonaws.com”,
    "requestParameters": {
        "resourceARN": "arn:aws:fsx:us-east-1:111122223333:file-system/fs-
ab12cd34ef56gh789”
    },
    "responseElements": null,
    "requestID": “aEXAMPLE-abcd-1234-56ef-b4cEXAMPLE51”,
    "eventID": “bEXAMPLE-gl12-3f5h-3sh4-ab6EXAMPLE9p”,
    "eventType": "AwsApiCall",
    "apiVersion": "2018-03-01",
    "recipientAccountId": “111122223333”
}
```

The following example shows a CloudTrail log entry that demonstrates the `UntagResource` action when a tag for a file system is deleted from the console.

```
{
    "eventVersion": "1.05",
    "userIdentity": {
        "type": “Root”,
        "principalId": "111122223333",
        "arn": "arn:aws:sts::111122223333:root",
        "accountId": "111122223333",
        "accessKeyId": "AKIAIOSFODNN7EXAMPLE",
        "sessionContext": {
            "attributes": {
                "mfaAuthenticated": "false",
                "creationDate": "2018-11-14T23:40:54Z"
            }
        }
    },
    "eventTime": "2018-11-14T23:40:54Z",
    "eventSource": "fsx.amazonaws.com",
    "eventName": "UntagResource",
    "awsRegion": "us-east-1",
```

```
    "sourceIPAddress": "192.0.2.0",
    "userAgent": "console.amazonaws.com",
    "requestParameters": {
        "resourceARN": "arn:aws:fsx:us-east-1:111122223333:file-system/fs-
ab12cd34ef56gh789"
    },
    "responseElements": null,
    "requestID": "aEXAMPLE-abcd-1234-56ef-b4cEXAMPLE51",
    "eventID": "bEXAMPLE-gl12-3f5h-3sh4-ab6EXAMPLE9p",
    "eventType": "AwsApiCall",
    "apiVersion": "2018-03-01",
    "recipientAccountId": "111122223333"
}
```

Working with Microsoft Active Directory in FSx for ONTAP

Amazon FSx works with Microsoft Active Directory to integrate with your existing environments. Active Directory is the Microsoft directory service that's used to store information about objects on the network, and to help administrators and users to find and use this information. These objects typically include shared resources, such as file servers and network user and computer accounts.

You can optionally join your FSx for ONTAP storage virtual machines (SVMs) to your Active Directory domain to provide user authentication and file- and folder-level access control. Server message block (SMB) clients can then use their existing user identities in Active Directory to authenticate themselves and access SVM volumes. Your users can use their existing identities to control access to individual files and folders. In addition, you can migrate your existing files and folders and their security access control list (ACL) configurations to Amazon FSx without any modifications.

If the Microsoft Active Directory domain infrastructure is not available, you can configure a Server Message Block (SMB) server in a workgroup on an SVM as an alternative to joining an SVM to a Microsoft Active Directory. For more information, see Setting up an SMB server in a workgroup.

When you join Amazon FSx for NetApp ONTAP to an Active Directory, you join the file system's SVMs to the Active Directory independently. This means that you can have a file system with some SVMs that are joined to an Active Directory, and other SVMs that are not.

After an SVM is joined to an Active Directory, you can update the following Active Directory configuration properties:

- DNS server IP addresses
- Self-managed Active Directory service account username and password

Topics

- Prerequisites for joining an SVM to a self-managed Microsoft AD
- Best practices for working with Active Directory
- How joining SVMs to Microsoft Active Directory works
- Managing SVM Active Directory configurations

Prerequisites for joining an SVM to a self-managed Microsoft AD

Before you join an FSx for ONTAP SVM to a self-managed Microsoft AD domain, make sure that your Active Directory and network meet the requirements described in the following sections.

Topics

- On-premises Active Directory requirements
- Network configuration requirements
- Active Directory service account requirements

On-premises Active Directory requirements

Make sure that you already have an on-premises or other self-managed Microsoft AD that you can join the SVM to. This Active Directory should have the following configuration:

- The Active Directory domain controller domain functional level is at Windows Server 2000 or higher.
- The Active Directory uses a domain name that's not in the Single Label Domain (SLD) format. Amazon FSx doesn't support SLD domains.
- If you have Active Directory sites defined, make sure that the subnets in the VPC that's associated with your FSx for ONTAP file system are defined in the same Active Directory sites, and that no conflicts exist between your VPC subnets and the subnets on your Active Directory sites.

> **Note**
>
> If you are using Directory Service, FSx for ONTAP doesn't support joining SVMs to the Simple Active Directory.

Network configuration requirements

Make sure that you have the following network configurations in place and associated information available to you.

Important

For an SVM to join Active Directory, you need to ensure that the ports documented in this topic allow traffic between all Active Directory Domain Controllers and both iSCSI IP addresses (iscsi_1 and iscsi_2 logical interfaces (LIFs)) on the SVM.

- The DNS server and Active Directory domain controller IP addresses.
- Connectivity between the Amazon VPC where you're creating the file system and your self-managed Active Directory using Direct Connect, Site-to-Site VPN, or AWS Transit Gateway.
- The security group and the VPC Network ACLs for the subnets on which you're creating the file system must allow traffic on the ports and in the directions shown in the following diagram.



The role of each port is described in the following table.

Protocol	Ports	Role
TCP/UDP	53	Domain Name System (DNS)

Protocol	Ports	Role
TCP/UDP	88	Kerberos authentication
TCP/UDP	389	Lightweight Directory Access Protocol (LDAP)
TCP	445	Directory Services SMB file sharing
TCP/UDP	464	Change/Set password
TCP	636	Lightweight Directory Access Protocol over TLS/SSL (LDAPS)

- These traffic rules should also be mirrored on the firewalls that apply to each of the Active Directory domain controllers, DNS servers, FSx clients, and FSx administrators.

> **Important**
>
> While Amazon VPC security groups require ports to be opened only in the direction that network traffic is initiated, most Windows firewalls and VPC network ACLs require ports to be open in both directions.

Active Directory service account requirements

Make sure that you have a service account in your self-managed Microsoft AD that has delegated permissions to join computers to the domain. A *service account* is a user account in your self-managed Active Directory that has been delegated certain tasks.

At a minimum, the service account must be delegated the following permissions in the OU to which you're joining the SVM:

- Ability to reset passwords
- Ability to restrict accounts from reading and writing data
- Ability to set the `msDS-SupportedEncryptionTypes` property on computer objects
- Validated ability to write to the DNS hostname
- Validated ability to write to the service principal name
- Ability to create and delete computer objects

- Validated ability to read and write Account Restrictions

These represent the minimum set of permissions that are required to join computer objects to your Active Directory. For more information, see the Windows Server documentation topic Error: Access is denied when non-administrator users who have been delegated control try to join computers to a domain controller.

You can store your Active Directory service account credentials in AWS Secrets Manager (recommended) and provide Amazon FSx with a secret ARN to join your Active Directory, or you can provide plaintext credentials.

To learn more about creating a service account with the correct permissions, see Delegating permissions to your Amazon FSx service account.

Important

Amazon FSx requires a valid service account throughout the lifetime of your Amazon FSx file system. Amazon FSx must be able to fully manage the file system and perform tasks that require it to unjoin and rejoin resources to your Active Directory domain. These tasks include replacing a failed file system or SVM, or patching NetApp ONTAP software. Keep your Active Directory configuration information up to date with Amazon FSx, including the service account credentials. To learn more, see Keeping your Active Directory configuration updated with Amazon FSx.

If this is your first time using AWS and FSx for ONTAP, make sure that you complete the initial setup steps before starting your Active Directory integration. For more information, see Setting up FSx for ONTAP.

Important

Don't move computer objects that Amazon FSx creates in the OU after your SVMs are created, or delete your Active Directory while your SVM is joined to it. Doing so will cause your SVMs to become misconfigured.

Best practices for working with Active Directory

Here are some suggestions and guidelines that you should consider when joining Amazon FSx for NetApp ONTAP SVMs to your self-managed Microsoft Active Directory. Note that these are recommended as best practices, but not required.

Topics

- Delegating permissions to your Amazon FSx service account
- Keeping your Active Directory configuration updated with Amazon FSx
- Using security groups to limit traffic within your VPC
- Creating outbound security group rules for your file system's network interface
- Storing Active Directory credentials using AWS Secrets Manager

Delegating permissions to your Amazon FSx service account

Make sure to configure the service account that you provide to Amazon FSx with the minimum permissions required. In addition, separate the Organizational Unit (OU) from other domain controller concerns.

To join Amazon FSx SVMs to your domain, make sure that the service account has delegated permissions. Members of the **Domain Admins** group have sufficient permissions to perform this task. However, as a best practice, use a service account that only has the minimum permissions necessary to do this. The following procedure demonstrates how to delegate only the permissions necessary to join FSx for ONTAP SVMs to your domain.

Perform this procedure on a machine that's joined to your directory and has the Active Directory User and Computers MMC snap-in installed.

To create a service account for your Microsoft Active Directory domain

1. Make sure that you're logged in as a domain administrator for your Microsoft Active Directory domain.
2. Open the **Active Directory User and Computers** MMC snap-in.
3. In the task pane, expand the domain node.
4. Locate and open the context (right-click) menu for the OU that you want to modify, and then choose **Delegate Control**.

5. On the **Delegation of Control Wizard** page, choose **Next**.
6. Choose **Add** to add a specific user or a specific group for **Selected users and groups**, and then choose **Next**.
7. On the **Tasks to Delegate** page, choose **Create a custom task to delegate**, and then choose **Next**.
8. Choose **Only the following objects in the folder**, and then choose **Computer objects**.
9. Choose **Create selected objects in this folder** and **Delete selected objects in this folder**. Then choose **Next**.
10. Under **Show these permissions**, ensure that **General** and **Property-specific** are selected.
11. For **Permissions**, choose the following:

    - **Reset Password**
    - **Read and write Account Restrictions**
    - **Validated write to DNS host name**
    - **Validated write to service principal name**
    - **Write msDS-SupportedEncryptionTypes**
12. Choose **Next**, and then choose **Finish**.
13. Close the **Active Directory User and Computers** MMC snap-in.

> **Important**
>
> Don't move computer objects that Amazon FSx creates in the OU after your SVMs are created. Doing so will cause your SVMs to become misconfigured.

Keeping your Active Directory configuration updated with Amazon FSx

For uninterrupted availability of your Amazon FSx SVMs, update an SVM's self-managed Active Directory (AD) configuration when you change your self-managed AD setup.

For example, suppose that your AD uses a time-based password reset policy. In this case, as soon as the password is reset, make sure to update the service account password with Amazon FSx. To do this, use the Amazon FSx console, Amazon FSx API, or AWS CLI. Similarly, if the DNS server IP addresses change for your Active Directory domain, as soon as the change occurs update the DNS server IP addresses with Amazon FSx.

If there's an issue with the updated self-managed AD configuration, the SVM state switches to **Misconfigured**. This state shows an error message and a recommended action beside the SVM description in the console, API, and CLI. If an issue with your SVM's AD configuration occurs, be sure to take the recommended corrective action for the configuration properties. If the issue is resolved, verify that your SVM's state changes to **Created**.

For more information, see Updating existing SVM Active Directory configurations using the AWS Management Console, AWS CLI, and API and Modify an Active Directory configuration using the ONTAP CLI.

Using security groups to limit traffic within your VPC

To limit network traffic in your virtual private cloud (VPC), you can implement the principle of least privilege in your VPC. In other words, you can limit permissions to the minimum ones necessary. To do this, use security group rules. To learn more, see Amazon VPC security groups.

Creating outbound security group rules for your file system's network interface

For greater security, consider configuring a security group with outbound traffic rules. These rules should allow outbound traffic only to your self-managed AD domains controllers or within the subnet or security group. Apply this security group to the VPC associated with your Amazon FSx file system's elastic network interface. To learn more, see File System Access Control with Amazon VPC.

Storing Active Directory credentials using AWS Secrets Manager

You can use AWS Secrets Manager to securely store and manage your Microsoft Active Directory domain join service account credentials. This approach eliminates the need to store sensitive credentials in plaintext in application code or configuration files, strengthening your security posture.

You can also configure IAM policies to manage access to your secrets, and set up automatic rotation policies for your passwords.

Store Active Directory credentials in AWS Secrets Manager (Console)

Step 1: Create a KMS key

Create a KMS key to encrypt and decrypt your Active Directory credentials in Secrets Manager.

To create a key

> **Note**
>
> For **Encryption Key**, create a new key, don't use the AWS default KMS key. Be sure to create the AWS KMS key in the same Region that contains the SVM that you want to join to your Active Directory.

1. Open the AWS KMS console at https://console.aws.amazon.com/kms.
2. Choose **Create key**.
3. For **Key Type**, choose **Symmetric**.
4. For **Key Usage**, choose **Encrypt and decrypt**.
5. For **Advanced options**, do the following:
   a. For **Key material origin**, choose **KMS**.
   b. For **Regionality**, choose **Single-Region key** and choose **Next**.
6. Choose **Next**.
7. For **Alias**, provide a name for the KMS key.
8. (Optional) For **Description**, provide a description of the KMS key.
9. (Optional) For **Tags**, provide a tag for the KMS key and choose **Next**.
10. (Optional) For **Key administrators**, provide the IAM users and roles authorized to manage this key.
11. For **Key deletion**, keep the box selected for **Allow key administrators** to delete this key and choose **Next**.
12. (Optional) For **Key users**, provide the IAM users and roles authorized to use this key in cryptographic operations. Choose **Next**.
13. For **Key policy**, choose **Edit** and include the following to the policy **Statement** to allow Amazon FSx to use the KMS key and choose **Next**. Make sure to replace the *us-west-2* to the AWS Region where the file system is deployed and *123456789012* to your AWS account ID.

```
{
    "Sid": "Allow FSx to use the KMS key",
    "Version": "2012-10-17",
    "Effect": "Allow",
```

```
    "Principal": {
        "Service": "fsx.amazonaws.com"
    },
    "Action": [
        "kms:Decrypt",
        "kms:DescribeKey"
    ],
    "Resource": "arn:aws:kms:us-west-2:123456789012:key/*",
    "Condition": {
        "StringEquals": {
            "kms:ViaService": "secretsmanager.us-west-2.amazonaws.com",
            "aws:SourceAccount": "123456789012"
        },
        "ArnLike": {
            "aws:SourceArn": [
                "arn:aws:fsx:us-west-2:123456789012:file-system/*",
                "arn:aws:fsx:us-west-2:123456789012:storage-virtual-machine/fs-*/
svm-*"
            ]
        }
    }
}
```

14. Choose **Finish**.

> **Note**
>
> You can set more granular access control by modifying the `Resource` and `aws:SourceArn` fields to target specific secrets and file systems.

Step 2: Create an AWS Secrets Manager secret

To create a secret

1. Open the Secrets Manager console at https://console.aws.amazon.com/secretsmanager/.
2. Choose **Store a new secret**.
3. For **Secret type**, choose **Other type of secret**.
4. For **Key/value pairs**, do the following to add your two keys:

    a. For the first key, enter `CUSTOMER_MANAGED_ACTIVE_DIRECTORY_USERNAME`.

b. For the value of the first key, enter only the username (without the domain prefix) of the AD user.

c. For the second key, enter `CUSTOMER_MANAGED_ACTIVE_DIRECTORY_PASSWORD`.

d. For the value of the second key, enter the password that you created for the AD user on your domain.

5. For **Encryption key**, enter the ARN of the KMS key that you created in a previous step and choose **Next**.
6. For **Secret name**, enter a descriptive name that helps you find your secret later.
7. (Optional) For **Description**, enter a description for the secret name.
8. For **Resource permission**, choose **Edit**.

   Add the following policy to the permission policy to allow Amazon FSx to use the secret, then choose **Next**. Make sure to replace the *us-west-2* to the AWS Region where the file system is deployed and *123456789012* to your AWS account ID.

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Effect": "Allow",
            "Principal": {
                "Service": "fsx.amazonaws.com"
            },
            "Action": [
                "secretsmanager:GetSecretValue",
                "secretsmanager:DescribeSecret"
            ],
            "Resource": "arn:aws:secretsmanager:us-west-2:123456789012:secret:*",
            "Condition": {
                "StringEquals": {
                    "aws:SourceAccount": "123456789012"
                },
                "ArnLike": {
                    "aws:SourceArn": [
                        "arn:aws:fsx:us-west-2:123456789012:file-system/*",
                        "arn:aws:fsx:us-west-2:123456789012:storage-virtual-
machine/fs-*/svm-*"
                    ]
                }
            }
```

```
        }
    ]
}
```

9. (Optional) You can configure Secrets Manager to rotate your credentials automatically. Choose **Next**.
10. Choose **Finish**.

Store Active Directory credentials in AWS Secrets Manager (CLI)

Step 1: Create a KMS key

Create a KMS key to encrypt and decrypt your Active Directory credentials in Secrets Manager.

To create a KMS key, use the AWS CLI command create-key.

In this command, set the `--policy` parameter to specify the key policy that defines permissions for the KMS key. The policy must include the following:

- The service principal for Amazon FSx, which is `fsx.amazonaws.com`.
- Required KMS actions: `kms:Decrypt` and `kms:DescribeKey`.
- Resource ARN pattern for your AWS Region and account.
- Condition keys that restrict key usage:
  - `kms:ViaService` to ensure requests come through Secrets Manager.
  - `aws:SourceAccount` to limit to your account.
  - `aws:SourceArn` to restrict to specific Amazon FSx file systems.

The following example creates a symmetric encryption KMS key with a policy that allows Amazon FSx to use the key for decryption and key description operations. The command automatically retrieves your AWS account ID and Region, then configures the key policy with these values to ensure proper access controls between Amazon FSx, Secrets Manager, and the KMS key. Make sure your AWS CLI environment is in the same region as the SVM that will join the Active Directory.

```
# Set region and get Account ID
REGION=${AWS_REGION:-$(aws configure get region)}
ACCOUNT_ID=$(aws sts get-caller-identity --query 'Account' --output text)

# Create Key
```

```
KMS_KEY_ARN=$(aws kms create-key --policy "{
  \"Version\": \"2012-10-17\",
  \"Statement\": [
    {
      \"Sid\": \"Enable IAM User Permissions\",
      \"Effect\": \"Allow\",
      \"Principal\": {
        \"AWS\": \"arn:aws:iam::$ACCOUNT_ID:root\"
      },
      \"Action\": \"kms:*\",
      \"Resource\": \"*\"
    },
    {
      \"Sid\": \"Allow FSx to use the KMS key\",
      \"Effect\": \"Allow\",
      \"Principal\": {
        \"Service\": \"fsx.amazonaws.com\"
      },
      \"Action\": [
        \"kms:Decrypt\",
        \"kms:DescribeKey\"
      ],
      \"Resource\": \"*\",
      \"Condition\": {
        \"StringEquals\": {
          \"kms:ViaService\": \"secretsmanager.$REGION.amazonaws.com\",
          \"aws:SourceAccount\": \"$ACCOUNT_ID\"
        },
        \"ArnLike\": {
          \"aws:SourceArn\": [
            \"arn:aws:fsx:$REGION:$ACCOUNT_ID:file-system/*\",
            \"arn:aws:fsx:$REGION:$ACCOUNT_ID:storage-virtual-machine/fs-*/svm-*\"]
        }
      }
    }
  ]
}" --query 'KeyMetadata.Arn' --output text)

echo "KMS Key ARN: $KMS_KEY_ARN"
```

> **Note**
>
> You can set more granular access control by modifying the `Resource` and `aws:SourceArn` fields to target specific secrets and file systems.

Step 2: Create an AWS Secrets Manager secret

To create a secret for Amazon FSx to access your Active Directory, use the AWS CLI command create-secret and set the following parameters:

- `--name`: The identifier for your secret.
- `--description`: A description of the secret's purpose.
- `--kms-key-id`: The ARN of the KMS key you created in Step 1 for encrypting the secret at rest.
- `--secret-string`: A JSON string containing your AD credentials in the following format:
  - `CUSTOMER_MANAGED_ACTIVE_DIRECTORY_USERNAME`: Your AD service account username without the domain prefix, such as `svc-fsx`. **Don't** provide the domain prefix, such as `CORP\svc-fsx`.
  - `CUSTOMER_MANAGED_ACTIVE_DIRECTORY_PASSWORD`: Your AD service account password
- `--region`: The AWS Region where your SVM will be created. This defaults to your configured region if `AWS_REGION` is not set.

After creating the secret, attach a resource policy using the put-resource-policy command, and set the following parameters:

- `--secret-id`: The name or ARN of the secret to attach the policy to. The following example uses **`FSxSecret`** as the `--secret-id`.
- `--region`: The same AWS Region as your secret.
- `--resource-policy`: A JSON policy document that grants Amazon FSx permission to access the secret. The policy must include the following:
  - The service principal for Amazon FSx, which is **`fsx.amazonaws.com`**.
  - Required Secrets Manager actions: `secretsmanager:GetSecretValue` and `secretsmanager:DescribeSecret`.
  - Resource ARN pattern for your AWS Region and account.
  - The following condition keys that restrict access:

- `aws:SourceAccount` to limit to your account.
- `aws:SourceArn` to restrict to specific Amazon FSx file systems.

The following example creates a secret with the required format and attaches a resource policy that allows Amazon FSx to use the secret. This example automatically retrieves your AWS account ID and Region, then configures the resource policy with these values to ensure proper access controls between Amazon FSx and the secret.

Make sure to replace the `KMS_KEY_ARN` with the ARN from the key you created in Step 1, `CUSTOMER_MANAGED_ACTIVE_DIRECTORY_USERNAME`, and `CUSTOMER_MANAGED_ACTIVE_DIRECTORY_PASSWORD` with your Active Directory service account credentials. Additionally, verify that your AWS CLI environment is configured for the same region as the SVM that will join the Active Directory.

```
# Set region and get account ID
REGION=${AWS_REGION:-$(aws configure get region)}
ACCOUNT_ID=$(aws sts get-caller-identity --query 'Account' --output text)

# Replace with your KMS key ARN from Step 1
KMS_KEY_ARN="arn:aws:kms:us-east-2:123456789012:key/1234542f-d114-555b-9ade-
fec3c9200d8e"

# Replace with your Active Directory credentials
AD_USERNAME="Your_Username"
AD_PASSWORD="Your_Password"

# Create the secret
SECRET_ARN=$(aws secretsmanager create-secret \
  --name "FSxSecret" \
  --description "Secret for FSx access" \
  --kms-key-id "$KMS_KEY_ARN" \
  --secret-string "{\"CUSTOMER_MANAGED_ACTIVE_DIRECTORY_USERNAME\":\"$AD_USERNAME\",
\"CUSTOMER_MANAGED_ACTIVE_DIRECTORY_PASSWORD\":\"$AD_PASSWORD\"}" \
  --region "$REGION" \
  --query 'ARN' \
  --output text)

echo "Secret created with ARN: $SECRET_ARN"

# Attach the resource policy with proper formatting
aws secretsmanager put-resource-policy \
```

```
  --secret-id "FSxSecret" \
  --region "$REGION" \
  --resource-policy "{
    \"Version\": \"2012-10-17\",
    \"Statement\": [
      {
        \"Effect\": \"Allow\",
        \"Principal\": {
          \"Service\": \"fsx.amazonaws.com\"
        },
        \"Action\": [
          \"secretsmanager:GetSecretValue\",
          \"secretsmanager:DescribeSecret\"
        ],
        \"Resource\": \"$SECRET_ARN\",
        \"Condition\": {
          \"StringEquals\": {
            \"aws:SourceAccount\": \"$ACCOUNT_ID\"
          },
          \"ArnLike\": {
            \"aws:SourceArn\": [
              \"arn:aws:fsx:$REGION:$ACCOUNT_ID:file-system/*\",
              \"arn:aws:fsx:$REGION:$ACCOUNT_ID:storage-virtual-machine/fs-*/svm-*\"]
          }
        }
      }
    ]
  }"

echo "Resource policy attached successfully"
```

Note

You can set more granular access control by modifying the `Resource` and `aws:SourceArn` fields to target specific secrets and file systems.

How joining SVMs to Microsoft Active Directory works

Your organization might manage identities and devices using an Active Directory, whether on-premises or in the cloud. With FSx for ONTAP, you can join your SVMs directly to your existing Active Directory domain in the following ways:

- Joining new SVMs to an Active Directory at creation:
  - Using the **Standard create** option in Amazon FSx console to create a new FSx for ONTAP file system, you can join the default SVM to a self-managed Active Directory. For more information, see To create a file system (console).
  - Using the Amazon FSx console, AWS CLI, or Amazon FSx API to create a new SVM on an existing FSx for ONTAP file system. For more information, see Creating storage virtual machines (SVM).
- Joining existing SVMs to an Active Directory:
  - Using the AWS Management Console, AWS CLI, and API to join an SVM to an Active Directory, and to reattempt joining an SVM to an Active Directory if the initial attempt to join failed. You can also update some Active Directory configuration properties for SVMs that are already joined to an Active Directory. For more information, see Managing SVM Active Directory configurations.
  - Using the NetApp ONTAP CLI or REST API to join, reattempt joining, and unjoining SVM Active Directory configurations. For more information, see Updating SVM Active Directory configurations using the NetApp CLI.

Important

- Amazon FSx only registers DNS records for an SVM if you use Microsoft DNS as the default DNS service. If you use a third-party DNS, you must set up DNS entries manually for your Amazon FSx SVMs after you create them.
- If you use AWS Managed Microsoft AD, you must specify a group such as AWS Delegated FSx Administrators, AWS Delegated Administrators, or a custom group with delegated permissions to the OU.

When you join an FSx for ONTAP SVM directly to a self-managed Active Directory, the SVM resides in the same Active Directory forest (the top-most logical container in an Active Directory configuration that contains domains, users, and computers) and in the same Active Directory domain as your users and existing resources, including existing file servers.

Information needed when joining an SVM to an Active Directory

You have to provide the following information about your Active Directory when joining an SVM to an Active Directory, regardless of the API operation you choose:

- The NetBIOS name of the Active Directory computer object to create for your SVM. This is the name of the SVM in Active Directory, which must be unique within your Active Directory. Don't use the NetBIOS name of the home domain. The NetBIOS name can't exceed 15 characters.
- The fully qualified domain name (FQDN) of your Active Directory. The FQDN can't exceed 255 characters.

  > **Note**
  >
  > The FQDN can't be in the Single Label Domain (SLD) format. Amazon FSx doesn't support SLD domains.

- Up to three IP addresses of the DNS servers or domain hosts for your domain.

  The DNS server IP addresses and Active Directory domain controller IP addresses can be in any IP address range, except:

  - IP addresses that conflict with Amazon Web Services-owned IP addresses in that AWS Region. For a list of AWS IP addresses by Region, see the AWS IP address ranges.
  - IP addresses in the following CIDR block range: 198.19.0.0/16
- Credentials for an Active Directory service account that Amazon FSx uses to join the SVM to your domain. You can provide these as either:
  - **Option 1:** AWS Secrets Manager secret ARN - The secret containing the username and password for a service account on your Active Directory domain. For more information, see Storing Active Directory credentials using AWS Secrets Manager.
  - **Option 2:** Plaintext credentials
    - **Service account username** – The user name of the service account in your existing Microsoft Active Directory. Don't include a domain prefix or suffix. For example, for `EXAMPLE\ADMIN`, use only `ADMIN`.
    - **Service account password** – The password for the service account.
- (Optional) The Organizational Unit (OU) in the domain that you join the SVM to.

> **Note**
>
> If you join your SVM to an AWS Directory Service Active Directory, you must provide an OU that's within the default OU that Directory Service creates for the directory objects that are related to AWS. This is because the Directory Service doesn't provide access to your Active Directory's default `Computers` OU. For example, if your Active Directory domain is `example.com`, you can specify the following OU: `OU=Computers,OU=example,DC=example,DC=com`.

- (Optional) The domain group that you are delegating authority to for performing administrative actions on your file system. For example, this domain group might manage Windows SMB file shares, take ownership of files and folders, and so on. If you don’t specify this group, Amazon FSx delegates this authority to the Domain Admins group in your Active Directory domain by default.

Managing SVM Active Directory configurations

This section describes how to use the AWS Management Console, AWS CLI, FSx API, and the ONTAP CLI to do the following:

- Joining an existing SVM to an Active Directory
- Modifying an existing SVM Active Directory configuration
- Removing SVMs from an Active Directory

To remove an SVM from an Active Directory, you must use the NetApp ONTAP CLI.

Topics

- Joining SVMs to Active Directory using the AWS Management Console, AWS CLI and API
- Updating existing SVM Active Directory configurations using the AWS Management Console, AWS CLI, and API
- Updating SVM Active Directory configurations using the NetApp CLI

Joining SVMs to Active Directory using the AWS Management Console, AWS CLI and API

Use the following procedure to join an existing SVM to an Active Directory. In this procedure, the SVM is *not* already joined to an Active Directory.

To join an SVM to an Active Directory (AWS Management Console)

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. Choose the SVM that you want to join to an Active Directory:

   - In the left navigation pane, choose **File systems**, and then choose the ONTAP file system with the SVM that you want to update.
   - Choose the **Storage virtual machines** tab.

   –Or–

   - To display a list of all of the available SVMs, in the left navigation pane, expand **ONTAP** and choose **Storage virtual machines**. A list of all SVMs in your account in the AWS Region is displayed.

   Select the SVM that you want to join to an Active Directory from the list.
3. On the upper right of the SVM **Summary** panel, choose **Actions** > **Join/Update Active Directory**. The **Join SVM to an Active Directory** window appears.
4. Enter the following information for the Active Directory that you are joining the SVM to:

   - The **NetBIOS name** of the Active Directory computer object to create for your SVM. This is the name of the SVM in Active Directory, which must be unique within your Active Directory. Don't use the NetBIOS name of the home domain. The NetBIOS name can't exceed 15 characters.
   - The **fully qualified domain name (FQDN)** of your Active Directory. The domain name can't exceed 255 characters.
   - **DNS server IP addresses** – The IPv4 or IPv6 addresses of the DNS servers for your domain.
   - **Service account credentials** – Choose how to provide your service account credentials:
     - **Option 1**: AWS Secrets Manager secret ARN - The secret containing the username and password for a service account on your Active Directory domain. For more information, see Storing Active Directory credentials using AWS Secrets Manager.

- **Option 2**: Plaintext credentials
  - **Service account username** – The user name of the service account in your existing Microsoft Active Directory. Don't include a domain prefix or suffix. For example, for `EXAMPLE\ADMIN`, use only `ADMIN`.
  - **Service account password** – The password for the service account.
  - **Confirm password** – The password for the service account.
- **Managed in Secrets Manager** (default) – Provide the ARN of an Secrets Manager secret that contains your service account credentials. The secret must contain the key-value pairs `CUSTOMER_MANAGED_ACTIVE_DIRECTORY_USERNAME` and `CUSTOMER_MANAGED_ACTIVE_DIRECTORY_PASSWORD`.
- (Optional) **Organizational Unit (OU)** – The distinguished path name of the organizational unit you want to join your SVM to.
- **Delegated file system administrators group** – The name of the group in your Active Directory that can administer your file system.

  If you are using AWS Managed Microsoft AD, you must specify a group such as AWS Delegated FSx Administrators, AWS Delegated Administrators, or a custom group with delegated permissions to the OU.

  If you are joining to a self-managed Active Directory, use the name of the group in your Active Directory. The default group is `Domain Admins`.

5. Choose **Join Active Directory** to join the SVM to the Active Directory using the configuration you provided.

To join an SVM to an Active Directory (AWS CLI)

- To join an FSx for ONTAP SVM to an Active Directory, use the update-storage-virtual-machine CLI command (or the equivalent UpdateStorageVirtualMachine API operation), as shown in the following example.

```
aws fsx update-storage-virtual-machine \
  --storage-virtual-machine-id svm-abcdef0123456789a\
  --active-directory-configuration
 SelfManagedActiveDirectoryConfiguration='{DomainName="corp.example.com", \
    OrganizationalUnitDistinguishedName="OU=FileSystems,DC=corp,DC=example,DC=com",
\
    FileSystemAdministratorsGroup="FSxAdmins",UserName="FSxService",\
```

```
    Password="password", \
    DnsIps=["10.0.1.18"]}',NetBiosName=amznfsx12345
```

After successfully creating the storage virtual machine, Amazon FSx returns its description in JSON format, as shown in the following example.

```
{
  "StorageVirtualMachine": {
    "ActiveDirectoryConfiguration": {
      "NetBiosName": "amznfsx12345",
      "SelfManagedActiveDirectoryConfiguration": {
        "UserName": "Admin",
        "DnsIps": [
          "10.0.1.3",
          "10.0.91.97"
        ],
        "OrganizationalUnitDistinguishedName": "OU=Computers,OU=customer-
ad,DC=customer-ad,DC=example,DC=com",
        "DomainName": "customer-ad.example.com"
      }
    }
    "CreationTime": 1625066825.306,
    "Endpoints": {
      "Management": {
        "DnsName": "svm-abcdef0123456789a.fs-0123456789abcdef0.fsx.us-
east-1.amazonaws.com",
        "IpAddressses": ["198.19.0.4"]
      },
      "Nfs": {
        "DnsName": "svm-abcdef0123456789a.fs-0123456789abcdef0.fsx.us-
east-1.amazonaws.com",
        "IpAddressses": ["198.19.0.4"]
      },
      "Smb": {
        "DnsName": "amznfsx12345",
        "IpAddressses": ["198.19.0.4"]
      },
      "SmbWindowsInterVpc": {
        "IpAddressses": ["198.19.0.5", "198.19.0.6"]
      },
      "Iscsi": {
        "DnsName": "iscsi.svm-abcdef0123456789a.fs-0123456789abcdef0.fsx.us-
east-1.amazonaws.com",
```

```
        "IpAddressses": ["198.19.0.7", "198.19.0.8"]
      }
    },
    "FileSystemId": "fs-0123456789abcdef0",
    "Lifecycle": "CREATED",
    "Name": "vol1",
    "ResourceARN": "arn:aws:fsx:us-east-1:123456789012:storage-virtual-machine/
fs-0123456789abcdef0/svm-abcdef0123456789a",
    "StorageVirtualMachineId": "svm-abcdef0123456789a",
    "Subtype": "default",
    "Tags": [],

  }
}
```

Updating existing SVM Active Directory configurations using the AWS Management Console, AWS CLI, and API

Use the following procedure to update the Active Directory configuration of an SVM that is already joined to an Active Directory.

To update an SVM Active Directory configuration (AWS Management Console)

1. Open the Amazon FSx console at https://console.aws.amazon.com/fsx/.
2. Choose the SVM to update as follows:

   - In the left navigation pane, choose **File systems**, and then choose the ONTAP file system with the SVM you want to update.
   - Choose the **Storage virtual machines** tab.

     –Or–

   - To display a list of all of the SVMs available, in the left navigation pane, expand **ONTAP** and choose **Storage virtual machines**.

   Select the SVM that you want to update from the list.
3. On the SVM **Summary** panel, choose **Actions** > **Join/Update Active Directory**. The **Update SVM Active Directory configuration** window appears.
4. You can update the following Active Directory configuration properties in this window.

- **DNS server IP addresses** – The IPv4 or IPv6 addresses of the DNS servers for your domain.
- **Service account credentials** – Choose how to provide your service account credentials:
  - **Option 1**: AWS Secrets Manager secret ARN - The secret containing the username and password for a service account on your Active Directory domain. For more information, see Storing Active Directory credentials using AWS Secrets Manager.
  - **Option 2**: Plaintext credentials
    - **Service account username** – The user name of the service account in your existing Microsoft Active Directory. Don't include a domain prefix or suffix. For example, for `EXAMPLE\ADMIN`, use only `ADMIN`.
    - **Service account password** – The password for the service account.
    - **Confirm password** – The password for the service account.

5. After you have entered your updates, choose **Update Active Directory** to make the changes.

Use the following procedure to update the Active Directory configuration of an SVM that is already joined to an Active Directory.

To update an SVM Active Directory configuration (AWS CLI)

- To update an SVM's Active Directory configuration with the AWS CLI or API, use the update-storage-virtual-machine CLI command (or the equivalent UpdateStorageVirtualMachine API operation), as shown in the following example.

```
aws fsx update-storage-virtual-machine \
    --storage-virtual-machine-id svm-abcdef0123456789a\
    --active-directory-configuration \
    SelfManagedActiveDirectoryConfiguration='{UserName="FSxService",\
    Password="password", \
    DnsIps=["10.0.1.18"]}'
```

Updating SVM Active Directory configurations using the NetApp CLI

You can use the NetApp ONTAP CLI to join and unjoin your SVM to an Active Directory, and to modify an existing SVM Active Directory configuration.

Joining an SVM to an Active Directory using the ONTAP CLI

You can join existing SVMs to an Active Directory using the ONTAP CLI, as described in the following procedure. You can do this even if your SVM is already joined to an Active Directory.

1. To access the ONTAP CLI, establish an SSH session on the management port of the Amazon FSx for NetApp ONTAP file system or SVM by running the following command. Replace *management_endpoint_ip* with the IP address of the file system's management port.

   ```
   [~]$ ssh fsxadmin@management_endpoint_ip
   ```

   For more information, see Managing file systems with the ONTAP CLI.

2. Create a DNS entry for your Active Directory by providing the full directory DNS name (`corp.example.com`) and at least one DNS server IP address.

   ```
   ::>vserver services name-service dns create -vserver svm_name -
   domains corp.example.com -name-servers dns_ip_1, dns_ip_2
   ```

   To verify the connection to your DNS servers, run the following command. Replace *svm_name* with your own information.

   ```
   FsxId0ae30e5b7f1a50b6a::>vserver services name-service dns check -vserver svm_name

                               Name Server
   Vserver       Name Server     Status       Status Details
   ------------- --------------- ------------ --------------------------
   svm_name      172.31.14.245   up           Response time (msec): 0
   svm_name      172.31.25.207   up           Response time (msec): 1
   2 entries were displayed.
   ```

3. To join your SVM to your Active Directory, run the following command. Note that you will must specify a `computer_name` that doesn't already exist in your Active Directory and provide the directory DNS name for `-domain`. For `-OU`, enter the OUs that you want the SVM to join, as well as the full DNS name in DC format.

   ```
   ::>vserver cifs create -vserver svm_name -cifs-server computer_name -
   domain corp.example.com -OU OU=Computers,OU=example,DC=corp,DC=example,DC=com
   ```

   To verify the status of your Active Directory connection, run the following command:

```
::>vserver cifs check -vserver svm_name

              Vserver : svm_name
                    Cifs NetBIOS Name : svm_netBIOS_name
                          Cifs Status : Running
                                 Site : Default-First-Site-Name
Node Name       DC Server Name  DC Server IP    Status   Status Details
--------------- --------------  --------------- ------   --------------
FsxId0ae30e5b7f1a50b6a-01
                corp.example.com
                                172.31.14.245   up       Response time (msec): 5
FsxId0ae30e5b7f1a50b6a-02
                corp.example.com
                                172.31.14.245   up       Response time (msec): 20
2 entries were displayed.
```

4. If you can't access shares after this join, determine whether the account you're using to access the share has permissions. For example, if you're using the default `Admin` account (a delegated administrator) with an AWS managed Active Directory, you will must run the following command in ONTAP. The `netbios_domain` corresponds with your Active Directory's domain name (for `corp.example.com`, the `netbios_domain` used here is `example`).

```
FsxId0123456789a::>vserver cifs users-and-groups local-group add-members -vserver
 svm_name -group-name BUILTIN\Administrators -member-names netbios_domain\admin
```

Modify an Active Directory configuration using the ONTAP CLI

You can use the ONTAP CLI to modify an existing Active Directory configuration.

1. To access the ONTAP CLI, establish an SSH session on the management port of the Amazon FSx for NetApp ONTAP file system or SVM by running the following command. Replace *`management_endpoint_ip`* with the IP address of the file system's management port.

   ```
   [~]$ ssh fsxadmin@management_endpoint_ip
   ```

   For more information, see Managing file systems with the ONTAP CLI.

2. Run the following command to temporarily bring down the SVM's CIFS server:

```
FsxId0123456789a::>vserver cifs modify -vserver svm_name -status-admin down
```

3. If you need to modify the DNS entries of your Active Directory, run the following command:

```
::>vserver services name-service dns modify -vserver svm_name -
domains corp.example.com -name-servers dns_ip_1,dns_ip_2
```

You can validate the connection status to your Active Directory's DNS servers using the `vserver services name-service dns check -vserver svm_name` command.

```
::>vserver services name-service dns check -vserver svm_name
                             Name Server
Vserver       Name Server    Status       Status Details
------------- -------------- ------------ --------------------------
svmciad       dns_ip_1       up           Response time (msec): 1
svmciad       dns_ip_2       up           Response time (msec): 1
2 entries were displayed.
```

4. If you need to modify the Active Directory configuration itself, you can change existing fields by using the following command, replacing:

- *computer_name*, if you want to modify the NetBIOS (machine account) name of the SVM.
- *domain_name*, if you want to modify the name of the domain. This should correspond with the DNS domain entry noted in Step 3 of this section (`corp.example.com`).
- `organizational_unit`, if you want to modify the OU (`OU=Computers,OU=example,DC=corp,DC=example,DC=com`).

You will need to reenter the Active Directory credentials that you used to join this device to the Active Directory.

```
::>vserver cifs modify -vserver svm_name -cifs-server computer_name -
domain domain_name -OU organizational_unit
```

You can verify the connection status of your Active Directory connection using the `vserver cifs check -vserver` *svm_name* command.

5. When you finish modifying your Active Directory and DNS configuration, bring the CIFS server back up by running the following command:

```
::>vserver cifs modify -vserver svm_name -status-admin up
```

Unjoin an Active Directory from your SVM using the NetApp ONTAP CLI

The NetApp ONTAP CLI can also be used to unjoin your SVM from an Active Directory by following the steps below:

1. To access the ONTAP CLI, establish an SSH session on the management port of the Amazon FSx for NetApp ONTAP file system or SVM by running the following command. Replace *management_endpoint_ip* with the IP address of the file system's management port.

   ```
   [~]$ ssh fsxadmin@management_endpoint_ip
   ```

   For more information, see Managing file systems with the ONTAP CLI.
2. Delete the CIFS server that unjoined your device from the Active Directory by running the following command. For ONTAP to delete the machine account for your SVM, provide the credentials that you originally used to join the SVM to the Active Directory.

   ```
   FsxId0123456789a::>vserver cifs modify -vserver svm_name -status-admin down
   ```
3. If you need to modify the DNS entries of your Active Directory, run the following command:

   ```
   FsxId0123456789a::vserver cifs delete -vserver svm_name

   In order to delete an Active Directory machine account for the CIFS server, you
    must supply the name and password of a Windows account with
   sufficient privileges to remove computers from the "CORP.ADEXAMPLE.COM" domain.

   Enter the user name: user_name

   Enter the password:

   Warning: There are one or more shares associated with this CIFS server
            Do you really want to delete this CIFS server and all its shares? {y|n}: y
   ```
4. Delete the DNS servers for your Active Directory by running the following command:

   ```
   ::vserver services name-service dns delete -vserver svm_name
   ```

If you see a warning like the following—indicating that dns should be removed as an ns-switch—and you don't plan to rejoin this device to an Active Directory, you can remove the ns-switch entries.

```
Warning: "DNS" is present as one of the sources in one or more ns-switch databases
 but no valid DNS configuration was found for Vserver
         "svm_name". Remove "DNS" from ns-switch using the "vserver services name-
service ns-switch" command. Configuring "DNS" as a source
         in the ns-switch setting when there is no valid configuration can cause
 protocol access issues.
```

5. (Optional) Remove the ns-switch entries for dns by running the following command. Verify the source order, then remove the dns entry for the hosts database by modifying the sources so that they contain only the other sources listed. In this example, the only other source is files.

```
::>vserver services name-service ns-switch show -vserver svm_name -database hosts

                    Vserver: svm_name
Name Service Switch Database: hosts
   Name Service Source Order: files, dns
```

```
::>vserver services name-service ns-switch modify -vserver svm_name -database hosts
 -sources files
```

6. (Optional) Remove the dns entry by modifying the sources for the database host to include only files.

```
::>vserver services name-service ns-switch modify -vserver svm_name -database hosts
 -sources files
```

Migrating to Amazon FSx for NetApp ONTAP

The following sections provide information on how to migrate your existing NetApp ONTAP file systems to Amazon FSx for NetApp ONTAP.

> **Note**
>
> If you plan to use the `All` tiering policy to migrate your data to the capacity pool tier, keep in mind that file metadata is always stored on the SSD tier, and that all new user data is first written to the SSD tier. When data is written to the SSD tier, the background tiering process will begin tiering your data to capacity pool storage, but the tiering process is not immediate and consumes network resources. You need to size your SSD tier to account for file metadata (3-7% of the size of user data), as a buffer for user data before it is tiered to capacity pool storage. We recommend that you do not exceed 80% utilization of your SSD tier.
>
> While migrating data, be sure to monitor your SSD tier using CloudWatch File system metrics to ensure that it is not filling faster than the tiering process can move data to the capacity pool storage.

Topics

- Migrating to FSx for ONTAP using NetApp SnapMirror
- Migrating to FSx for ONTAP using AWS DataSync

Migrating to FSx for ONTAP using NetApp SnapMirror

You can migrate your NetApp ONTAP file systems to Amazon FSx for NetApp ONTAP using NetApp SnapMirror.

NetApp SnapMirror employs block-level replication between two ONTAP file systems, replicating data from a specified source volume to a destination volume. We recommend using SnapMirror to migrate on-premise NetApp ONTAP file systems to FSx for ONTAP. NetApp SnapMirror's block-level replication is quick and efficient even for file systems with:

- Complex directory structures
- Over 50 million files

- Very small file sizes (on the order of kilobytes)

When you use SnapMirror to migrate to FSx for ONTAP, deduplicated and compressed data remains in those states, which reduces transfer times and reduces the amount of bandwidth required for migration. Snapshots that exist on the source ONTAP volumes are preserved when migrated to the destination volumes. Migrating your on-premises NetApp ONTAP file systems to FSx for ONTAP involves the following high level tasks:

1. Create the destination volume in Amazon FSx.
2. Gather source and destination logical interfaces (LIFs).
3. Establish cluster peering between the source and destination file systems.
4. Create an SVM peering relationship.
5. Create the SnapMirror relationship.
6. Maintain an updated destination cluster.
7. Cut over to your FSx for ONTAP file system.

The following diagram illustrates the migration scenario described in this section.



Topics

- Before you begin
- Create the destination volume

- Record the source and destination inter-cluster LIFs
- Establish cluster peering between source and destination
- Create an SVM peering relationship
- Create the SnapMirror relationship
- Transfer data to your FSx for ONTAP file system
- Cutting over to Amazon FSx

Before you begin

Before you begin using the procedures described in the following sections, be sure that you have met the following prerequisites:

- FSx for ONTAP prioritizes client traffic over background tasks including data tiering, storage efficiency, and backups. When migrating data, and as a general best practice, we recommend that you monitor your SSD tier's capacity to ensure it is not exceeding 80% utilization. You can monitor your SSD tier's utilization using CloudWatch File system metrics. For more information, see Volume metrics.
- If you set the destination volume's data tiering policy to `All` when migrating your data, all file metadata is stored on the primary SSD storage tier. File metadata is always stored on the SSD-based primary tier, regardless of the volume's data tiering policy. We recommend that you assume a ratio of 1 : 10 for primary tier : capacity pool tier storage capacity.
- The source and destination file systems are connected in the same VPC, or are in networks that are peered using Amazon VPC Peering, Transit Gateway, AWS Direct Connect or Site-to-Site VPN. For more information, see Accessing data from within the AWS Cloud and What is VPC peering? in the *Amazon VPC Peering Guide*.
- For cluster peering and SnapMirror to function correctly, every inter-cluster LIF on each cluster must be able to communicate with every inter-cluster LIF on the other cluster. If you are peering with an on-premises ONTAP cluster, ensure that all inter-cluster LIFs on all nodes of the on-premises cluster have network connectivity (routing and firewall rules) to all inter-cluster LIFs on the FSx for ONTAP file system, and vice versa. For more information, see Cluster peering prerequisites in NetApp's ONTAP user documentation.
- The VPC security group for the FSx for ONTAP file system has inbound and outbound rules allowing ICMP as well as TCP on ports 443, 10000, 11104, and 11105 for all inter-cluster endpoints (LIFs).

- Verify that the source and destination volumes are running compatible NetApp ONTAP versions before creating a SnapMirror data protection relationship. For more information, see Compatible ONTAP versions for SnapMirror relationships in NetApp's ONTAP user documentation. The procedures presented here use an on-premise NetApp ONTAP file system for the source.
- Your on-premises (source) NetApp ONTAP file system includes a SnapMirror license.
- You have created a destination FSx for ONTAP file system with an SVM, but you have not created a destination volume. For more information, see Creating file systems.

The commands in these procedures use the following cluster, SVM, and volume aliases:

- *`FSx-Dest`* – the destination (FSx) cluster's ID (in the format FSxIdabcdef1234567890a).
- *`OnPrem-Source`* – the source cluster's ID.
- *`DestSVM`* – the destination SVM name.
- *`SourceSVM`* – the source SVM name.
- Both the source and destination volume names are `vol1`.

> **Note**
>
> An FSx for ONTAP file system is referred to as a cluster in all of the ONTAP CLI commands.

The procedures in this section use the following NetApp ONTAP CLI commands.

- volume create command
- cluster commands
- vserver peer commands
- snapmirror commands

You will use the NetApp ONTAP CLI to create and manage a SnapMirror configuration on your FSx for ONTAP file system. For more information, see Using the NetApp ONTAP CLI.

Create the destination volume

You can create a data protection (DP) destination volume using the Amazon FSx console, the AWS CLI, and the Amazon FSx API, in addition to the NetApp ONTAP CLI and REST API. For information

about creating a destination volume using the Amazon FSx console and AWS CLI, see Creating volumes.

> **Note**
>
> ONTAP does not preserve post-process compression savings achieved at the source in the destination DP volume when the destination volume's tiering policy is `All`. To preserve post-process compression savings, you should set the destination volume tiering policy to `Auto` and enable inactive-data-compression on the destination file system to re-apply post-process compression savings at the destination.

In the following procedure, you will use the NetApp ONTAP CLI to create a destination volume on your FSx for ONTAP file system. You will need the `fsxadmin` password and the IP address or DNS name of the file system's management port.

1. Establish an SSH session with the destination file system using user `fsxadmin` and the password that you set when you created the file system.

   ```
   ssh fsxadmin@file-system-management-endpoint-ip-address
   ```

2. Create a volume on the destination cluster that has a storage capacity that is at least equal to the storage capacity of the source volume. Use `-type DP` to designate it as a destination for a SnapMirror relationship.

   If you plan to use data tiering, we recommended that you set `-tiering-policy` to `all`. This ensures that your data is immediately transferred to capacity pool storage and prevents you from running out of capacity on your SSD tier. After migration, you can switch `-tiering-policy` to `auto`.

   > **Note**
   >
   > File metadata is always stored on the SSD-based primary tier, regardless of the volume's data tiering policy.

   ```
   FSx-Dest::> vol create -vserver DestSVM -volume vol1 -aggregate aggr1 -size 1g -
   type DP -tiering-policy all
   ```

Record the source and destination inter-cluster LIFs

SnapMirror uses inter-cluster logical interfaces (LIFs), each with a unique IP address, to facilitate data transfer between source and destination clusters.

1. For the destination FSx for ONTAP file systems, you can retrieve the **Inter-cluster endpoint - IP addresses** from the Amazon FSx console by navigating to the **Administration** tab on your file system's details page.
2. For the source NetApp ONTAP cluster, retrieve the inter-cluster LIF IP addresses using the ONTAP CLI. Run the following command:

```
OnPrem-Source::> network interface show -role intercluster

Logical                         Network
Vserver     Interface  Status  Address/Mask
----------- ---------- ------- ------------
FSx-Dest
             inter_1    up/up  10.0.0.36/24
             inter_2    up/up  10.0.1.69/24
```

> **Note**
>
> For second-generation Single-AZ file systems, there are two inter-cluster IP addresses for each high-availability (HA) pair. Save these values for later.

Save the `inter_1` and `inter_2` IP addresses. They are referenced in the `FSx-Dest` as `dest_inter_1` and `dest_inter_2` and for `OnPrem-Source` as `source_inter_1` and `source_inter_2`.

Establish cluster peering between source and destination

Establish a cluster peer relationship on the destination cluster by providing the inter-cluster IP addresses. You will also need to create a passphrase which you will need to enter in when you establish cluster peering on the source cluster.

1. Set up peering on the destination cluster using the following command. For second-generation Single-AZ file systems, you'll need to provide each inter-cluster IP address.

```
FSx-Dest::> cluster peer create -address-family ipv4 -peer-
addrs source_inter_1,source_inter_2

Enter the passphrase:
Confirm the passphrase:
Notice: Now use the same passphrase in the "cluster peer create" command in the
 other cluster.
```

2. Next, establish the cluster peer relationship on the source cluster. You'll need to enter the passphrase you created above to authenticate. For second-generation Single-AZ file systems, you'll need to provide each inter-cluster IP address.

```
OnPrem-Source::> cluster peer create -address-family ipv4 -peer-
addrs dest_inter_1,dest_inter_2

Enter the passphrase:
Confirm the passphrase:
```

3. Verify the peering was successful using the following command on the source cluster. In the output, `Availability` should be set to `Available`.

```
OnPrem-Source::> cluster peer show

Peer Cluster Name  Availability   Authentication
-----------------  -------------- --------------
FSx-Dest           Available      ok
```

Create an SVM peering relationship

With cluster peering established, the next step is peering the SVMs. Create an SVM peering relationship on the destination cluster (FSx-Dest) using the `vserver peer` command. Additional aliases used in the following commands are as follows:

- `DestLocalName` – this is name used to identify the destination SVM when configuring SVM peering on the source SVM.
- `SourceLocalName` – this is the name used to identify the source SVM when configuring SVM peering on the destination SVM.

1. Use the following command to create an SVM peering relationship between the source and destination SVMs.

```
FSx-Dest::> vserver peer create -vserver DestSVM -peer-vserver SourceSVM -peer-
cluster OnPrem-Source -applications snapmirror -local-name SourceLocalName

 Info: [Job 207] 'vserver peer create' job queued
```

2. Accept the peering relationship on the source cluster:

```
OnPrem-Source::> vserver peer accept -vserver SourceSVM -peer-vserver DestSVM -
local-name DestLocalName

 Info: [Job 211] 'vserver peer accept' job queued
```

3. Verify the SVM peering status using the following command; `Peer State` should be set to `peered` in the response.

```
OnPrem-Source::> vserver peer show

            Peer      Peer   Peer      Peering       Remote
Vserver     Vserver   State  Cluster   Applications  Vserver
------- -------- ------ -------- ------------- ---------
svm01   destsvm1 peered FSx-Dest snapmirror    svm01
```

Create the SnapMirror relationship

Now that you have peered the source and destination SVMs, the next steps are to create and initialize the SnapMirror relationship on the destination cluster.

> **Note**
>
> Once you create and initialize a SnapMirror relationship, the destination volumes are read-only until the relationship is broken.

- Use the `snapmirror create` command to create the SnapMirror relationship on the destination cluster. The `snapmirror create` command must be used from the destination SVM.

You can optionally use `-throttle` to set the maximum bandwidth (in kB/sec) for the SnapMirror relationship.

```
FSx-Dest::> snapmirror create -source-path SourceLocalName:vol1 -destination-
path DestSVM:vol1 -vserver DestSVM -throttle unlimited

 Operation succeeded: snapmirror create for the relationship with destination
 "DestSVM:vol1".
```

Transfer data to your FSx for ONTAP file system

Now that the you've created the SnapMirror relationship, you can transfer data to the destination file system.

1. You can transfer data to the destination file system by running the following command on the destination file system.

   > **Note**
   >
   > Once you run this command, SnapMirror begins transferring snapshots of data from the source volume to the destination volume.

   ```
   FSx-Dest::> snapmirror initialize -destination-path DestSVM:vol1 -source-
   path SourceLocalName:vol1
   ```

2. If you are migrating data that is being actively used, you'll need to update your destination cluster so that it remains synced with your source cluster. To perform a one-time update to the destination cluster, run the following command.

   ```
   FSx-Dest::> snapmirror update -destination-path DestSVM:vol1
   ```

3. You can also schedule hourly or daily updates prior to completing the migration and moving your clients to FSx for ONTAP. You can establish a SnapMirror update schedule using the `snapmirror modify` command.

   ```
   FSx-Dest::> snapmirror modify -destination-path DestSVM:vol1 -schedule hourly
   ```

Cutting over to Amazon FSx

To prepare for the cut over to your FSx for ONTAP file system, do the following:

- Disconnect all clients that write to the source cluster.
- Perform a final SnapMirror transfer to ensure there is no data loss when cutting over.
- Break the SnapMirror relationship.
- Connect all clients to your FSx for ONTAP file system.

1. To ensure that all data from the source cluster is transferred to FSx for ONTAP file system, perform a final Snapmirror transfer.

```
FSx-Dest::> snapmirror update -destination-path DestSVM:vol1
```

2. Ensure that the data migration is complete by verifying that `Mirror State` is set to `Snapmirrored`, and `Relationship Status` is set to `Idle`. You also should ensure that the `Last Transfer End Timestamp` date is as expected, as it shows when the last transfer to the destination volume occurred.
3. Run the following command to show the SnapMirror status.

```
FSx-Dest::> snapmirror show -fields state,status,last-transfer-end-timestamp

Source     Destination   Mirror        Relationship Last Transfer End
Path       Path          State         Status       Timestamp
---------- -----------   ----------    -------      ---------------
Svm01:vol1 svm02:DestVol Snapmirrored  Idle         09/02 09:02:21
```

4. Disable any future SnapMirror transfers by using the `snapmirror quiesce` command.

```
FSx-Dest::> snapmirror quiesce -destination-path DestSVM:vol1
```

5. Verify that the `Relationship Status` has changed to `Quiesced` using `snapmirror show`.

```
FSx-Dest::> snapmirror show

Source            Destination   Mirror        Relationship
Path              Path          State         Status
-----------       ------------  ------------- --------
sourcesvm1:vol1   svm01:DestVol Snapmirrored  Quiesced
```

6. During migration, the destination volume is read-only. To enable read/write, you need to break the SnapMirror relationship and cut over to your FSx for ONTAP file system. Break the SnapMirror relationship using the following command.

```
FSx-Dest::> snapmirror break -destination-path DestSVM:vol1

Operation succeeded: snapmirror break for destination "DestSVM:vol1".
```

7. Once the SnapMirror replication has completed and you have broken the SnapMirror relationship, you can mount the volume to make the data available.

```
FSx-Dest::> vol mount -vserver fsx -volume vol1 -junction-path /vol1
```

The volume is now available with the data from the source volume fully migrated to the destination volume The volume is also available for clients to read and write to it. If you previously set the `tiering-policy` of this volume to `all`, you can change it to `auto` or `snapshot-only` and your data will automatically transition between storage tiers according to access patterns. To make this data accessible to clients and applications, see Accessing your FSx for ONTAP data.

Migrating to FSx for ONTAP using AWS DataSync

We recommend using AWS DataSync to transfer data between FSx for ONTAP file systems and non-ONTAP file systems, including FSx for Lustre, FSx for OpenZFS, FSx for Windows File Server, Amazon EFS, Amazon S3, and on-premises filers. If you're transferring files between FSx for ONTAP and NetApp ONTAP, we recommend using NetApp SnapMirror. AWS DataSync is a data transfer service that simplifies, automates, and accelerates moving and replicating data between self-managed storage systems and AWS storage services over the internet or Direct Connect. DataSync can transfer your file system data and metadata, such as ownership, timestamps, and access permissions.

You can use DataSync to transfer files between two FSx for ONTAP file systems, and also move data to a file system in a different AWS Region or AWS account. You can also use DataSync with FSx for ONTAP file systems for other tasks. For example, you can perform one-time data migrations, periodically ingest data for distributed workloads, and schedule replication for data protection and recovery.

In DataSync, a *location* is an endpoint for an FSx for ONTAP file system. For information about specific transfer scenarios, see Working with locations in the *AWS DataSync User Guide*.

Note

If you plan to use the `All` tiering policy to migrate your data to the capacity pool tier, keep in mind that file metadata is always stored on the SSD tier, and that all new user data is first written to the SSD tier. When data is written to the SSD tier, the background tiering process will begin tiering your data to capacity pool storage, but the tiering process is not immediate and consumes network resources. You need to size your SSD tier to account for file metadata (3-7% of the size of user data), as a buffer for user data before it is tiered to capacity pool storage. We recommend that you do not exceed 80% SSD utilization. While migrating data, be sure to monitor your SSD tier using CloudWatch File system metrics to ensure that it is not filling faster than the tiering process can move data to the capacity pool storage. You can also throttle DataSync transfers to a rate that is lower than the rate that tiering is occurring to ensure that your SSD tier does not exceed 80% utilization. For example, for file systems with a throughput capacity of at least 512 MBps, a 200 MBps throttle will typically balance out the data transfer and data tiering rates.

Prerequisites

To migrate data into your FSx for ONTAP setup, you need a server and network that meet the DataSync requirements. To learn more, see Requirements for DataSync in the *AWS DataSync User Guide*.

Basic steps for migrating files using DataSync

Transferring files from a source to a destination using DataSync involves the following basic steps:

- Download and deploy an agent in your environment and activate it (not required if transferring between AWS services).
- Create a source and destination location.
- Create a task.
- Run the task to transfer files from the source to the destination.

For more information, see the following topics in the *AWS DataSync User Guide*:

- Data transfer between self-managed storage and AWS
- Creating a location for Amazon FSx for NetApp ONTAP

Security in Amazon FSx for NetApp ONTAP

Cloud security at AWS is the highest priority. As an AWS customer, you benefit from data centers and network architectures that are built to meet the requirements of the most security-sensitive organizations.

Security is a shared responsibility between AWS and you. The shared responsibility model describes this as security *of* the cloud and security *in* the cloud:

- **Security of the cloud** – AWS is responsible for protecting the infrastructure that runs AWS services in the AWS Cloud. AWS also provides you with services that you can use securely. Third-party auditors regularly test and verify the effectiveness of our security as part of the AWS Compliance Programs. To learn about the compliance programs that apply to Amazon FSx for NetApp ONTAP, see AWS Services in Scope by Compliance Program.
- **Security in the cloud** – Your responsibility is determined by the AWS service that you use. You are also responsible for other factors including the sensitivity of your data, your company's requirements, and applicable laws and regulations.

This documentation helps you understand how to apply the shared responsibility model when using Amazon FSx. The following topics show you how to configure Amazon FSx to meet your security and compliance objectives. You also learn how to use other AWS services that help you to monitor and secure your Amazon FSx resources.

Topics

- Data protection in Amazon FSx for NetApp ONTAP
- Identity and access management for Amazon FSx for NetApp ONTAP
- AWS managed policies for Amazon FSx for NetApp ONTAP
- File System Access Control with Amazon VPC
- Compliance Validation for Amazon FSx for NetApp ONTAP
- Amazon FSx for NetApp ONTAP and interface VPC endpoints (AWS PrivateLink)
- Resilience in Amazon FSx for NetApp ONTAP
- Infrastructure security in Amazon FSx for NetApp ONTAP
- Use NetApp ONTAP Vscan with FSx for ONTAP
- ONTAP roles and users

Data protection in Amazon FSx for NetApp ONTAP

The AWS shared responsibility model applies to data protection in Amazon FSx for NetApp ONTAP. As described in this model, AWS is responsible for protecting the global infrastructure that runs all of the AWS Cloud. You are responsible for maintaining control over your content that is hosted on this infrastructure. You are also responsible for the security configuration and management tasks for the AWS services that you use. For more information about data privacy, see Data Privacy FAQ. For information about data protection in Europe, see the General Data Protection Regulation (GDPR) Center.

For data protection purposes, we recommend that you protect AWS account credentials and set up individual users with AWS IAM Identity Center or AWS Identity and Access Management (IAM). That way, each user is given only the permissions necessary to fulfill their job duties. We also recommend that you secure your data in the following ways:

- Use multi-factor authentication (MFA) with each account.
- Use SSL/TLS to communicate with AWS resources. We require TLS 1.2 and recommend TLS 1.3.
- Set up API and user activity logging with AWS CloudTrail. For information about using CloudTrail trails to capture AWS activities, see Working with CloudTrail trails in the *AWS CloudTrail User Guide*.
- Use AWS encryption solutions, along with all default security controls within AWS services.
- Use advanced managed security services such as Amazon Macie, which assists in discovering and securing sensitive data that is stored in Amazon S3.
- If you require FIPS 140-3 validated cryptographic modules when accessing AWS through a command line interface or an API, use a FIPS endpoint. For more information about the available FIPS endpoints, see Federal Information Processing Standard (FIPS) 140-3.

We strongly recommend that you never put confidential or sensitive information, such as your customers' email addresses, into tags or free-form text fields such as a **Name** field. This includes when you work with Amazon FSx or other AWS services using the console, API, AWS CLI, or AWS SDKs. Any data that you enter into tags or free-form text fields used for names may be used for billing or diagnostic logs. If you provide a URL to an external server, we strongly recommend that you do not include credentials information in the URL to validate your request to that server.

Data encryption in FSx for ONTAP

Amazon FSx for NetApp ONTAP supports encryption of data at rest and encryption of data in transit. Encryption of data at rest is automatically enabled when creating an Amazon FSx file system. Amazon FSx for NetApp ONTAP supports Kerberos-based encryption in transit over the NFS and SMB protocols if you're accessing data in a Storage Virtual Machine (SVM) that's joined to an Active Directory or to a domain using the Lightweight Directory Access Protocol (LDAP).

When to use encryption

If your organization is subject to corporate or regulatory policies that require encryption of data and metadata at rest, your data is automatically encrypted at rest. We also recommend that you enable encryption of data in transit by mounting your file system using encryption of data in transit.

For more information about data encryption with Amazon FSx for NetApp ONTAP, see Encryption of data at rest and Encrypting data in transit.

Encryption of data at rest

All Amazon FSx for NetApp ONTAP file systems and backups are encrypted at rest with keys managed using AWS Key Management Service (AWS KMS). Data is automatically encrypted before being written to the file system, and automatically decrypted as it is read. All backups are automatically encrypted at creation, and automatically decrypted when the backup is restored to a new volume. These processes are handled transparently by Amazon FSx, so you don't have to modify your applications.

Amazon FSx uses an industry-standard AES-256 encryption algorithm to encrypt Amazon FSx data and metadata at rest. For more information, see Cryptography Basics in the *AWS Key Management Service Developer Guide*.

> **Note**
>
> The AWS key management infrastructure uses Federal Information Processing Standards (FIPS) 140-2 approved cryptographic algorithms. The infrastructure is consistent with National Institute of Standards and Technology (NIST) 800-57 recommendations.

How Amazon FSx uses AWS KMS

Amazon FSx integrates with AWS KMS for key management. Amazon FSx uses KMS keys to encrypt your file system and any volume backups. You choose the KMS key used to encrypt and decrypt file systems and volume backups (both data and metadata). You can enable, disable, or revoke grants on this KMS key. This KMS key can be one of the two following types:

- **AWS-managed KMS key** – This is the default KMS key, and it's free to use.
- **Customer-managed KMS key** – This is the most flexible KMS key to use, because you can configure its key policies and grants for multiple users or services. For more information on creating KMS keys, see Creating Keys in the *AWS Key Management Service Developer Guide*.

> **Important**
>
> Amazon FSx accepts only symmetric encryption KMS keys. You can't use asymmetric KMS keys with Amazon FSx.

If you use a customer-managed KMS key as your KMS key for file data encryption and decryption, you can enable key rotation. When you enable key rotation, AWS KMS automatically rotates your key once per year. Additionally, with a customer-managed KMS key, you can choose when to disable, re-enable, delete, or revoke access to your KMS key at any time. For more information, see Rotating AWS KMS keys and Enabling and disabling keys in the *AWS Key Management Service Developer Guide*.

Amazon FSx key policies for AWS KMS

Key policies are the primary way to control access to KMS keys. For more information on key policies, see Using key policies in AWS KMS in the *AWS Key Management Service Developer Guide*. The following list describes all the AWS KMS-related permissions supported by Amazon FSx for encrypted at rest file systems and backups:

- **kms:Encrypt** – (Optional) Encrypts plaintext into ciphertext. This permission is included in the default key policy.
- **kms:Decrypt** – (Required) Decrypts ciphertext. Ciphertext is plain text that has been previously encrypted. This permission is included in the default key policy.

- **kms:ReEncrypt** – (Optional) Encrypts data on the server side with a new AWS KMS key, without exposing the plaintext of the data on the client side. The data is first decrypted and then re-encrypted. This permission is included in the default key policy.
- **kms:GenerateDataKeyWithoutPlaintext** – (Required) Returns a data encryption key encrypted under a KMS key. This permission is included in the default key policy under **kms:GenerateDataKey***.
- **kms:CreateGrant** – (Required) Adds a grant to a key to specify who can use the key and under what conditions. Grants are alternate permission mechanisms to key policies. For more information on grants, see Using Grants in the *AWS Key Management Service Developer Guide.* This permission is included in the default key policy.
- **kms:DescribeKey** – (Required) Provides detailed information about the specified KMS key. This permission is included in the default key policy.
- **kms:ListAliases** – (Optional) Lists all of the key aliases in the account. When you use the console to create an encrypted file system, this permission populates the list of KMS keys. We recommend using this permission to provide the best user experience. This permission is included in the default key policy.

Encrypting data in transit

This topic explains the different options available for encrypting your file data while it is in-transit between an FSx for ONTAP file system and connected clients. It also provides guidance to help you choose which encryption method is best suited for your workflow.

All data flowing across AWS Regions over the AWS global network is automatically encrypted at the physical layer before it leaves AWS secured facilities. All traffic between Availability Zones is encrypted. Additional layers of encryption, including those listed in this section, provide additional protections. For more information about how AWS provides protection for data flowing across AWS Regions, Available Zones, and instances, see Encryption in transit in the Amazon Elastic Compute Cloud User Guide for Linux Instances.

Amazon FSx for NetApp ONTAP supports the following methods for encrypting data in transit between FSx for ONTAP file systems and connected clients:

- Automatic Nitro-based encryption over all supported protocols and clients running on supported Amazon EC2 Linux and Windows instance types.
- Kerberos-based encryption over NFS and SMB protocols.

- IPsec-based encryption over NFS, iSCSI, and SMB protocols

All of the supported methods for encrypting data in transit use industry standard AES-256 cryptographic algorithms that provide enterprise strength encryption.

Topics

- Choosing a method for encrypting data in transit
- Encrypting data in transit with AWS Nitro System
- Encrypting data in-transit with Kerberos-based encryption
- Encrypting data in transit with IPsec encryption
- Enabling SMB encryption of data in transit
- Configuring IPsec using PSK authentication
- Configuring IPsec using certificate authentication

Choosing a method for encrypting data in transit

This section provides information that can help you decide which of the supported encryption in transit methods is best for your workflow. Refer back to this section as you explore the supported options described in detail in the sections that follow.

There are several factors to consider when choosing how you are going to encrypt data in transit between your FSx for ONTAP file system and connected clients. These factors include:

- The AWS Region that your FSx for ONTAP file system is running in.
- The instance type that the client is running on.
- The location of the client accessing your file system.
- Network performance requirements.
- The data protocol you want to encrypt.
- If you are using Microsoft Active Directory.

AWS Region

The AWS Region that your file system is running in determines whether or not you can use Amazon Nitro-based encryption. For more information, see Encrypting data in transit with AWS Nitro System.

Client instance type

You can use Amazon Nitro-based encryption if the client accessing your file system is running on any of the supported Amazon EC2 Mac, Linux or Windows instance types, and your workflow meets all other requirements for using Nitro-based encryption. There aren't any client instance type requirements for using Kerberos or IPsec encryption.

Client location

The location of the client accessing data with respect to the location of your file system impacts which in-transit encryption methods are available to use. You can use any of the supported encryption methods if the client and file system are located in the same VPC. The same is true if the client and file system are located in peered VPCs, as long as the traffic does not pass through a virtual network device or service, such as a transit gateway. Nitro-based encryption is not an available option if the client is not in the same or peered VPC, or if the traffic passes through a virtual network device or service.

Network performance

Using Amazon Nitro-based encrypted has no impact on network performance. This is because the supported Amazon EC2 instances utilize the offload capabilities of the underlying Nitro System hardware to automatically encrypt in-transit traffic between instances.

Using Kerberos or IPsec encryption has an impact on network performance. This is because both of these encryption methods are software-based, which requires the client and server to use compute resources to encrypt and decrypt in-transit traffic.

Data protocol

You can use Amazon Nitro-based encryption and IPsec encryption with all of the supported protocols – NFS, SMB, and iSCSI. You can use Kerberos encryption with the NFS and SMB protocols (with an Active Directory).

Active Directory

If you are using Microsoft Active Directory, you can use Kerberos encryption over the NFS and SMB protocols.

Use the following diagram to help you decide which encryption in-transit method to use.



IPsec encryption is the only option available when all of the following conditions apply to your workflow:

- You are using the NFS, SMB, or iSCSI protocol.
- Your workflow does not support using Amazon Nitro-based encryption.
- You are not using a Microsoft Active Directory domain.

Encrypting data in transit with AWS Nitro System

With Nitro-based encryption, data in-transit is encrypted automatically when clients accessing your file systems are running on supported Amazon EC2 Linux or Windows instance types in AWS Regions where it's available on FSx for ONTAP.

Using Amazon Nitro-based encryption has no impact on network performance. This is because the supported Amazon EC2 instances utilize the offload capabilities of the underlying Nitro System hardware to automatically encrypt in-transit traffic between instances.

Nitro-based encryption is enabled automatically when the supported client instance types are located in the same AWS Region and in the same VPC or in a VPC peered with the file system's VPC.

Additionally, if the client is in a peered VPC, then data cannot traverse a virtual network device or service (such as a transit gateway) in order for Nitro-based encryption to be automatically enabled. For more information about Nitro-based encryption, see the Encryption in transit section of the Amazon EC2 User Guide for Linux or Windows instance types.

The following table details the AWS Regions that Nitro-based encryption is available in.

Support for Nitro-based encryption

Generation	Deployment types	AWS Region
First-generation file systems[1]	Single-AZ 1, Multi-AZ 1	US East (N. Virginia), US East (Ohio), US West (Oregon), Asia Pacific (Malaysia), Asia Pacific (New Zealand), Asia Pacific (Taipei), Asia Pacific (Thailand), Europe (Ireland), Mexico (Central)
Second-generation file systems	Single-AZ 2, Multi-AZ 2	Nitro-based encryption is available in all AWS Regions where second-generation file systems are available. For more information, see Availability by AWS Region.

[1] First-generation file systems created on or after November 28, 2022 support Nitro-based in-transit encryption in the listed AWS Regions.

For more information about the AWS Regions where FSx for ONTAP is available, see Amazon FSx for NetApp ONTAP Pricing.

For more information about the performance specifications for FSx for ONTAP file systems, see Impact of throughput capacity on performance.

Encrypting data in-transit with Kerberos-based encryption

If you are using Microsoft Active Directory, you can use Kerberos-based encryption over the NFS and SMB protocols to encrypt data in-transit for child volumes of SVMs that are joined to a Microsoft Active Directory.

Encrypting data in transit over NFS using Kerberos

Encryption of data in-transit using Kerberos is supported for NFSv3 and NFSv4 protocols. To enable encryption in transit using Kerberos for the NFS protocol, see Using Kerberos with NFS for strong security in the NetApp ONTAP Documentation Center.

Encrypting data in transit over SMB using Kerberos

Encrypting data in transit over the SMB protocol is supported on file shares that are mapped on a compute instance that supports SMB protocol 3.0 or newer. This includes all Microsoft Windows versions from Microsoft Windows Server 2012 and later, and Microsoft Windows 8 and later. When enabled, FSx for ONTAP automatically encrypts data in transit using SMB encryption as you access your file system without the need for you to modify your applications.

FSx for ONTAP SMB supports 128 and 256 bit encryption, which is determined by the client session request. For descriptions of the different encryption levels, see the *Set the SMB server minimum authentication security level* section of Manage SMB with the CLI in the NetApp ONTAP Documentation Center.

> **Note**
>
> The client determines the encryption algorithm. Both NTLM and Kerberos authentication work with both 128 and 256 bit encryption. The FSx for ONTAP SMB Server accepts all standard Windows client requests, and the granular controls are handled by Microsoft Group Policy or Registry settings.

You use the ONTAP CLI to manage the encryption in transit settings on FSx for ONTAP SVMs and volumes. To access the NetApp ONTAP CLI, establish an SSH session on the SVM on which you are making encryption in transit settings, as described in Managing SVMs with the ONTAP CLI.

For instructions on how to enable SMB encryption on an SVM or volume, see Enabling SMB encryption of data in transit.

Encrypting data in transit with IPsec encryption

FSx for ONTAP supports using the IPsec protocol in transport mode to ensure data is continuously secure and encrypted, while in-transit. IPsec offers end-to-end encryption of data in-transit between clients and FSx for ONTAP file systems for all supported IP traffic – NFS, iSCSI, and SMB protocols. With IPsec encryption, you establish an IPsec tunnel between an FSx for ONTAP SVM configured with IPsec enabled, and an IPsec client running on the connected client accessing the data.

We recommend that you use IPsec to encrypt data in transit over NFS, SMB, and iSCSI protocols when accessing your data from clients that do not support Nitro-based encryption, and if your client and SVMs are not joined to an Active Directory, which is required for Kerberos-based encryption. IPsec encryption is the only option available for encrypting data in-transit for iSCSI traffic when your iSCSI client doesn't support Nitro-based encryption.

For IPsec authentication, you can use either pre-shared keys (PSKs) or certificates. If you are using a PSK, the IPsec client you use must support Internet Key Exchange version 2 (IKEv2) with a PSK. The high level steps for configuring IPsec encryption on both FSx for ONTAP and the client are as follows:

1. Enable and configure IPsec on your file system.
2. Install and configure IPsec on your client
3. Configure IPsec for multiple client access

For more information about how to configure IPsec using PSK, see Configure IP security (IPsec) over wire encryption in the NetApp ONTAP documentation center.

For more information about how to configure IPsec using certificates, see Configuring IPsec using certificate authentication.

Enabling SMB encryption of data in transit

By default, when you create an SVM, SMB encryption is turned off. You can either enable SMB encryption required on individual shares, or on an SVM, which turns it on for all shares on that SVM.

> **Note**
>
> When SMB encryption required is enabled on an SVM or share, SMB clients that do not support encryption cannot connect to that SVM or share.

To require SMB encryption for incoming SMB traffic on an SVM

Use the following procedure to require SMB encryption on a SVM using the NetApp ONTAP CLI.

1. To connect to the SVM management endpoint with SSH, use user name `vsadmin` and the vsadmin password that you set when you created the SVM. If you did not set a vsadmin password, use user name `fsxadmin` and the fsxadmin password. You can SSH into the SVM from a client that is in the same VPC as the file system, using the management endpoint IP address or DNS name.

   ```
   ssh vsadmin@svm-management-endpoint-ip-address
   ```

   The command with sample values:

   ```
   ssh vsadmin@198.51.100.10
   ```

   The SSH command using the management endpoint DNS name:

   ```
   ssh vsadmin@svm-management-endpoint-dns-name
   ```

   The SSH command using a sample DNS name:

   ```
   ssh vsadmin@management.svm-abcdef01234567892fs-08fc3405e03933af0.fsx.us-
   east-2.aws.com
   ```

   ```
   Password: vsadmin-password

   This is your first recorded login.
   FsxIdabcdef01234567892::>
   ```

2. Use the `vserver cifs security modify` NetApp ONTAP CLI command to require SMB encryption for incoming SMB traffic to the SVM.

```
vserver cifs security modify -vserver vserver_name -is-smb-encryption-required true
```

3. To stop requiring SMB encryption for incoming SMB traffic, use the following command.

```
vserver cifs security modify -vserver vserver_name -is-smb-encryption-required
 false
```

4. To see the current `is-smb-encryption-required` setting on an SVM, use the `vserver cifs security show` NetApp ONTAP CLI command:

```
vserver cifs security show -vserver vs1 -fields is-smb-encryption-required

vserver  is-smb-encryption-required
-------- -------------------------
vs1      true
```

For more information about managing SMB encryption on an SVM, see Configuring required SMB encryption on SMB servers for data transfers over SMB in the NetApp ONTAP Documentation Center.

To enable SMB encryption on a volume

Use the following procedure to enable SMB encryption on a share using the NetApp ONTAP CLI.

1. Establish a secure shell (SSH) connection to the SVM's management endpoint as described in Managing SVMs with the ONTAP CLI.
2. Use the following NetApp ONTAP CLI command to create a new SMB share and require SMB encryption when accessing this share.

```
vserver cifs share create -vserver vserver_name -share-name share_name -
path share_path -share-properties encrypt-data
```

   For more information, see `vserver cifs share create` in the NetApp ONTAP CLI Command man pages.

3. To require SMB encryption on an existing SMB share, use the following command.

```
vserver cifs share properties add -vserver vserver_name -share-name share_name -
share-properties encrypt-data
```

For more information, see vserver cifs share create in the NetApp ONTAP CLI Command man pages.

4. To turn off SMB encryption on an existing SMB share, use the following command.

```
vserver cifs share properties remove -vserver vserver_name -share-name share_name -
share-properties encrypt-data
```

For more information, see vserver cifs share properties remove in the NetApp ONTAP CLI Command man pages.

5. To see the current `is-smb-encryption-required` setting on an SMB share, use the following NetApp ONTAP CLI command:

```
vserver cifs share properties show -vserver vserver_name -share-name share_name -
fields share-properties
```

If one of the properties returned by the command is the `encrypt-data` property, then that property specifies that SMB encryption must be used when accessing this share.

For more information, see vserver cifs share properties show in the NetApp ONTAP CLI Command man pages.

Configuring IPsec using PSK authentication

If you are using PSK for authentication, the steps for configuring IPsec encryption on both FSx for ONTAP and the client are as follows:

1. Enable and configure IPsec on your file system.
2. Install and configure IPsec on your client
3. Configure IPsec for multiple client access

For details on configuring IPsec using PSK, see Configure IP security (IPsec) over wire encryption in the NetApp ONTAP documentation center.

Configuring IPsec using certificate authentication

The following topics provide instructions for configuring IPsec encryption using certificate authentication on an FSx for ONTAP file system and a client running Libreswan IPsec. This solution uses AWS Certificate Manager and AWS Private Certificate Authority to create a private certificate authority and for generating the certificates.

The high-level steps for configuring IPsec encryption using certificate authentication on FSx for ONTAP file systems and connected clients are as follows:

1. Have a certificate authority in place for issuing certificates.
2. Generate and export CA certificates for the file system and client.
3. Install certificate and configure IPsec on the client instance.
4. Install certificate and configure IPsec on your file system.
5. Define the security policy database (SPD).
6. Configure IPsec for multiple client access.

Creating and installing CA certificates

For certificate authentication, you need to generate and install certificates from a certificate authority on your FSx for ONTAP file system and the clients that will access the data on your file system. The following example uses AWS Private Certificate Authority to set up a private certificate authority, and generate the certificates to install on the file system and the client. Using AWS Private Certificate Authority, you can create an entirely AWS hosted hierarchy of root and subordinate certificate authorities (CAs) for internal use by your organization. This process has five steps:

1. Create a private certificate authority (CA) using AWS Private CA
2. Issue and install the root certificate on the private CA
3. Request a private certificate from AWS Certificate Manager for your file system and clients
4. Export the certificate for the file system and clients.

For more information, see Private CA administration in the AWS Private Certificate Authority User Guide.

To create the root private CA

1. When you create a CA, you must specify the CA configuration in a file that you supply. The following command uses the Nano text editor to create the `ca_config.txt` file, which specifies the following information:

   - The name of the algorithm
   - The signing algorithm that the CA uses to sign
   - X.500 subject information

   ```
   $ > nano ca_config.txt
   ```

   The text editor appears.

2. Edit the file with the specifications for your CA.

   ```
   {
      "KeyAlgorithm":"RSA_2048",
      "SigningAlgorithm":"SHA256WITHRSA",
      "Subject":{
         "Country":"US",
         "Organization":"Example Corp",
         "OrganizationalUnit":"Sales",
         "State":"WA",
         "Locality":"Seattle",
         "CommonName":"*.ec2.internal"
      }
   }
   ```

3. Save and close the file, exiting the text editor. For more information, see Procedure for creating a CA in the AWS Private Certificate Authority User Guide.

4. Use the create-certificate-authority AWS Private CA CLI command to create a private CA.

   ```
   ~/home > aws acm-pca create-certificate-authority \
        --certificate-authority-configuration file://ca_config.txt \
        --certificate-authority-type "ROOT" \
        --idempotency-token 01234567 --region aws-region
   ```

   If successful, this command outputs the Amazon Resource Name (ARN) of the CA.

```
{
   "CertificateAuthorityArn": "arn:aws:acm-pca:aws-region:111122223333:certificate-
authority/12345678-1234-1234-1234-123456789012"
}
```

To create and install a certificate for your private root CA (AWS CLI)

1. Generate a certificate signing request (CSR) using the [get-certificate-authority-csr](#) AWS CLI command.

```
$ aws acm-pca get-certificate-authority-csr \
     --certificate-authority-arn arn:aws:acm-pca:aws-
region:111122223333:certificate-authority/12345678-1234-1234-1234-123456789012 \
     --output text \
     --endpoint https://acm-pca.aws-region.amazonaws.com \
     --region eu-west-1 > ca.csr
```

   The resulting file `ca.csr`, a PEM file encoded in base64 format, has the following appearance.

```
-----BEGIN CERTIFICATE-----
 MIICiTCCAfICCQD6m7oRw0uXOjANBgkqhkiG9w0BAQUFADCBiDELMAkGA1UEBhMC
 VVMxCzAJBgNVBAgTAldBMRAwDgYDVQQHEwdTZWF0dGxlMQ8wDQYDVQQKEwZBbWF6
 b24xFDASBgNVBAsTC0lBTSBDb25zb2xlMRIwEAYDVQQDEwlUZXN0Q2lsYWMxHzAd
 BgkqhkiG9w0BCQEWEG5vb25lQGFtYXpvbi5jb20wHhcNMTEwNDI1MjA0NTIxWhcN
 MTIwNDI0MjA0NTIxWjCBiDELMAkGA1UEBhMCVVMxCzAJBgNVBAgTAldBMRAwDgYD
 VQQHEwdTZWF0dGxlMQ8wDQYDVQQKEwZBbWF6b24xFDASBgNVBAsTC0lBTSBDb25z
 b2xlMRIwEAYDVQQDEwlUZXN0Q2lsYWMxHzAdBgkqhkiG9w0BCQEWEG5vb25lQGFt
 YXpvbi5jb20wgZ8wDQYJKoZIhvcNAQEBBQADgY0AMIGJAoGBAMaK0dn+a4GmWIWJ
 21uUSfwfEvySWtC2XADZ4nB+BLYgVIk60CpiwsZ3G93vUEIO3IyNoH/f0wYK8m9T
 rDHudUZg3qX4waLG5M43q7Wgc/MbQITxOUSQv7c7ugFFDzQGBzZswY6786m86gpE
 Ibb3OhjZnzcvQAaRHhdlQWIMm2nrAgMBAAEwDQYJKoZIhvcNAQEFBQADgYEAtCu4
 nUhVVxYUntneD9+h8Mg9q6q+auNKyExzyLwaxlAoo7TJHidbtS4J5iNmZgXL0Fkb
 FFBjvSfpJIlJ00zbhNYS5f6GuoEDmFJl0ZxBHjJnyp378OD8uTs7fLvjx79LjSTb
 NYiytVbZPQUQ5Yaxu2jXnimvw3rrszlaEXAMPLE=
 -----END CERTIFICATE-----
```

   For more information, see [Installing a root CA certificate](#) in the AWS Private Certificate Authority User Guide.

2. Use the issue-certificate AWS CLI command to issue and install the root certificate on your private CA.

```
$ aws acm-pca issue-certificate \
     --certificate-authority-arn arn:aws:acm-pca:aws-
region:111122223333:certificate-authority/12345678-1234-1234-1234-123456789012 \
     --csr file://ca.csr \
     --signing-algorithm SHA256WITHRSA \
     --template-arn arn:aws:acm-pca:::template/RootCACertificate/V1 \
     --validity Value=3650,Type=DAYS --region aws-region
```

3. Download the root certificate using the get-certificate AWS CLI command.

```
$ aws acm-pca get-certificate \
    --certificate-authority-arn arn:aws:acm-pca:aws-
region:111122223333:certificate-authority/12345678-1234-1234-1234-123456789012 \
    --certificate-arn arn:aws:acm-pca:aws-region:486768734100:certificate-
authority/12345678-1234-1234-1234-123456789012/certificate/
abcdef0123456789abcdef0123456789 \
    --output text --region aws-region > rootCA.pem
```

4. Install the root certificate on your private CA using the import-certificate-authority-certificate AWS CLI command.

```
$ aws acm-pca import-certificate-authority-certificate \
     --certificate-authority-arn arn:aws:acm-pca:aws-
region:111122223333:certificate-authority/12345678-1234-1234-1234-123456789012 \
     --certificate file://rootCA.pem --region aws-region
```

Generate and export the file system and client certificate

1. Use the request-certificate AWS CLI command to request an AWS Certificate Manager certificate to use on your file system and clients.

```
$ aws acm request-certificate \
    --domain-name *.ec2.internal \
    --idempotency-token 12345 \
    --region aws-region \
    --certificate-authority-arn arn:aws:acm-pca:aws-
region:111122223333:certificate-authority/12345678-1234-1234-1234-123456789012
```

If the request is successful, the ARN of the issued certificate is returned.

2. For security, you must assign a passphrase for the private key when exporting it. Create a passphrase and store it in a file named `passphrase.txt`
3. Use the `export-certificate` AWS CLI command to export the private certificate issued previously. The exported file contains the certificate, the certificate chain, and the encrypted private 2048-bit RSA key associated with the public key that is embedded in the certificate. For security, you must assign a passphrase for the private key when exporting it. The following example is for a Linux EC2 instance.

```
$ aws acm export-certificate \
     --certificate-arn arn:aws:acm:aws-
region:111122223333:certificate/12345678-1234-1234-1234-123456789012 \
     --passphrase $(cat passphrase.txt | base64) --region aws-region >
 exported_cert.json
```

4. Use the following `jq` commands to extract the private key and the certificate from the JSON response.

```
$ passphrase=$(cat passphrase.txt | base64)
cat exported_cert.json | jq -r .PrivateKey > prv.key

cat exported_cert.json | jq -r .Certificate > cert.pem
```

5. Use the following `openssl` command to decrypt the private key from the JSON response. After entering the command, you are prompted for the passphrase.

```
$ openssl rsa -in prv.key -passin pass:$passphrase -out decrypted.key
```

Installing and configuring Libreswan IPsec on an Amazon Linux 2 client

The following sections provide instructions for installing and configuring Libreswan IPsec on an Amazon EC2 instance running Amazon Linux 2.

To install and configure Libreswan

1. Connect to your EC2 instance using SSH. For specific instructions on how to do this, see Connect to your Linux instance using an SSH client in the Amazon Elastic Compute Cloud User Guide for Linux Instances.

2. Run the following command to install `libreswan`:

```
$ sudo yum install libreswan
```

3. (Optional) When verifying IPsec in a later step, these properties might be flagged without these settings. We suggest testing your set up first without these settings. If your connection has problems, return to this step and make the following changes.

   After the installation completes, use your preferred text editor to add the following entries to the `/etc/sysctl.conf` file.

```
net.ipv4.ip_forward=1
net.ipv4.conf.all.accept_redirects = 0
net.ipv4.conf.all.secure_redirects = 0
net.ipv4.conf.all.send_redirects = 0
net.ipv4.conf.default.accept_redirects = 0
net.ipv4.conf.default.send_redirects = 0
net.ipv4.conf.lo.accept_redirects = 0
net.ipv4.conf.lo.send_redirects = 0
net.ipv4.conf.all.rp_filter = 0
net.ipv4.conf.default.rp_filter = 0
net.ipv4.conf.eth0.rp_filter = 0
```

   Save the changes and exit the text editor.

4. Apply the changes.

```
$ sudo sysctl -p
```

5. Verify the IPsec configuration.

```
$ sudo ipsec verify
```

   Verify that the version of `Libreswan` you installed is running.

6. Initialize the IPsec NSS database.

```
$ sudo ipsec checknss
```

To install the certificate on the client

1. Copy the certificate you generated for the client to the working directory on the EC2 instance. You
2. Export the certificate generated previously into a format compatible with `libreswan`.

```
$ openssl pkcs12 -export -in cert.pem -inkey decrypted.key \
    -certfile rootCA.pem -out certkey.p12 -name fsx
```

3. Import the reformatted key, providing the passphrase when prompted.

```
$ sudo ipsec import certkey.p12
```

4. Create an IPsec configuration file using the preferred text editor.

```
$ sudo cat /etc/ipsec.d/nfs.conf
```

   Add the following entries to the config file:

```
conn fsxn
    authby=rsasig
    left=172.31.77.6
    right=198.19.254.13
    auto=start
    type=transport
    ikev2=insist
    keyexchange=ike
    ike=aes256-sha2_384;dh20
    esp=aes_gcm_c256
    leftcert=fsx
    leftrsasigkey=%cert
    leftid=%fromcert
    rightid=%fromcert
    rightrsasigkey=%cert
```

You will start IPsec on the client after configuring IPsec on your file system.

Configuring IPsec on your file system

This section provides instructions on installing the certificate on your FSx for ONTAP file system, and configuring IPsec.

To install the certificate on your file system

1. Copy the root certificate (`rootCA.pem`), the client certificate (`cert.pem`) and the decrypted key (`decrypted.key`) files to your file system. You will need to know the passphrase for the certificate.
2. To access the ONTAP CLI, establish an SSH session on the management port of the Amazon FSx for NetApp ONTAP file system or SVM by running the following command. Replace *`management_endpoint_ip`* with the IP address of the file system's management port.

   ```
   [~]$ ssh fsxadmin@management_endpoint_ip
   ```

   For more information, see Managing file systems with the ONTAP CLI.
3. Use **cat** on a client (not on your file system) to list out the contents of the `rootCA.pem`, `cert.pem` and `decrypted.key` files so that you can copy the output of each file and paste it when prompted in the following steps.

   ```
   $ > cat cert.pem
   ```

   Copy the certificate contents.
4. You must install all CA certificates used during the mutual authentication, including both ONTAP-side and client-side CAs, to ONTAP certificate management unless it is already installed (as is the case of an ONTAP self-signed root-CA).

   Use the `security certificate install` NetApp CLI command as follows to install the client certificate:

   ```
   FSxID123:: > security certificate install -vserver dr -type client -cert-name
    ipsec-client-cert
   ```

   ```
   Please enter Certificate: Press <Enter> when done
   ```

   Paste in the contents of the `cert.pem` file that you copied previously and press Enter.

```
Please enter Private Key: Press <Enter> when done
```

Paste in the contents of the `decrypted.key` file, and press enter.

```
Do you want to continue entering root and/or intermediate certificates {y|n}:
```

Enter n to complete entering the client certificate.

5. Create and install a certificate for use by the SVM. The issuer CA of this certificate must already be installed to ONTAP and added to IPsec.

   Use the following command to install the root certificate.

```
FSxID123:: > security certificate install -vserver dr -type server-ca -cert-name
 ipsec-ca-cert
```

```
Please enter Certificate: Press <Enter> when done
```

   Paste in the contents of the `rootCA.pem` file, and press enter.

6. To ensure that the CA installed is within the IPsec CA searching path during authentication, add the ONTAP certificate management CAs to the IPsec module using the “security ipsec ca-certificate add” command.

   Enter the following command to add the root certificate.

```
FSxID123:: > security ipsec ca-certificate add -vserver dr -ca-certs ipsec-ca-cert
```

7. Enter the following command to create the required IPsec policy in the security policy database (SPD).

```
security ipsec policy create -vserver dr -name policy-name -local-ip-
subnets 198.19.254.13/32 -remote-ip-subnets 172.31.0.0/16 -auth-method PKI -action
 ESP_TRA -cipher-suite SUITEB_GCM256 -cert-name ipsec-client-cert -local-identity
 "CN=*.ec2.internal" -remote-identity "CN=*.ec2.internal"
```

8. Use the following command to show the IPsec policy for the file system to confirm.

```
FSxID123:: > security ipsec policy show -vserver dr -instance
```

```
                                    Vserver: dr
                                Policy Name: promise
                            Local IP Subnets: 198.19.254.13/32
                           Remote IP Subnets: 172.31.0.0/16
                                 Local Ports: 0-0
                                Remote Ports: 0-0
                                   Protocols: any
                                      Action: ESP_TRA
                                Cipher Suite: SUITEB_GCM256
          IKE Security Association Lifetime: 86400
        IPsec Security Association Lifetime: 28800
IPsec Security Association Lifetime (bytes): 0
                           Is Policy Enabled: true
                              Local Identity: CN=*.ec2.internal
                             Remote Identity: CN=*.ec2.internal
                      Authentication Method: PKI
             Certificate for Local Identity: ipsec-client-cert
```

Start IPsec on the client

Now IPsec is configured on both the FSx for ONTAP file system and the client, you can start IPsec on the client.

1. Connect to your client system using SSH.
2. Start IPsec.

```
$ sudo ipsec start
```

3. Check the status of IPsec.

```
$ sudo ipsec status
```

4. Mount a volume on your file system.

```
$ sudo mount -t nfs 198.19.254.13:/benchmark /home/ec2-user/acm/dr
```

5. Verify the IPsec setup by showing the encrypted connection on your FSx for ONTAP file system.

```
FSxID123:: > security ipsec show-ikesa -node FsxId123
```

```
FsxId08ac16c7ec2781a58::> security ipsec show-ikesa -node FsxId08ac16c7ec2781a58-01
            Policy Local           Remote
Vserver     Name   Address         Address         Initator-SPI     State
----------- ------ --------------- --------------- ---------------- -----------
dr          policy-name
                   198.19.254.13   172.31.77.6     551c55de57fe8976 ESTABLISHED
fsx         policy-name
                   198.19.254.38   172.31.65.193   4fd3f22c993e60c5 ESTABLISHED
2 entries were displayed.
```

Setting up IPsec for multiple clients

When a small number of clients need to leverage IPsec, using a single SPD entry for each client is sufficient. However, when hundreds or even thousands of clients need to leverage IPsec, we recommend that you use IPsec multiple client configuration.

FSx for ONTAP supports connecting multiple clients across many networks to a single SVM IP address with IPsec enabled. You can accomplish this using either the `subnet` configuration or the `Allow all clients` configuration, which are explained in the following procedures:

To configure IPsec for multiple clients using a subnet configuration

To allow all clients on a particular subnet (192.168.134.0/24 for example) to connect to a single SVM IP address using a single SPD policy entry, you must specify the `remote-ip-subnets` in subnet form. Additionally, you must specify the `remote-identity` field with the correct client side identity.

> **Important**
>
> When using certificate authentication, each client can use either their own unique certificate or a shared certificate to authenticate. FSx for ONTAP IPsec checks the validity of the certificate based on the CAs installed on its local trust store. FSx for ONTAP also supports certificate revocation list (CRL) checking.

1. To access the ONTAP CLI, establish an SSH session on the management port of the Amazon FSx for NetApp ONTAP file system or SVM by running the following command. Replace *`management_endpoint_ip`* with the IP address of the file system's management port.

```
[~]$ ssh fsxadmin@management_endpoint_ip
```

For more information, see Managing file systems with the ONTAP CLI.

2. Use the `security ipsec policy create` NetApp ONTAP CLI command as follows, replacing the *sample* values with your specific values.

```
FsxId123456::> security ipsec policy create -vserver svm_name -name policy_name \
  -local-ip-subnets 192.168.134.34/32 -remote-ip-subnets 192.168.134.0/24 \
  -local-ports 2049 -protocols tcp -auth-method PSK \
  -cert-name my_nfs_server_cert -local-identity ontap_side_identity \
  -remote-identity client_side_identity
```

To configure IPsec for multiple clients using an allow all clients configuration

To allow any client, regardless of their source IP address, to connect to the SVM IPsec-enabled IP address, use the `0.0.0.0/0` wild card when specifying the `remote-ip-subnets` field.

Additionally, you must specify the `remote-identity` field with the correct client side identity. For certificate authentication, you can enter `ANYTHING`.

Also, when the 0.0.0.0/0 wild card is used, you must configure a specific local or remote port number to use. For example, NFS port 2049.

1. To access the ONTAP CLI, establish an SSH session on the management port of the Amazon FSx for NetApp ONTAP file system or SVM by running the following command. Replace *management_endpoint_ip* with the IP address of the file system's management port.

```
[~]$ ssh fsxadmin@management_endpoint_ip
```

For more information, see Managing file systems with the ONTAP CLI.

2. Use the `security ipsec policy create` NetApp ONTAP CLI command as follows, replacing the *sample* values with your specific values.

```
FsxId123456::> security ipsec policy create -vserver svm_name -name policy_name \
  -local-ip-subnets 192.168.134.34/32 -remote-ip-subnets 0.0.0.0/0 \
  -local-ports 2049 -protocols tcp -auth-method PSK \
  -cert-name my_nfs_server_cert -local-identity ontap_side_identity \
```

```
-local-ports 2049 -remote-identity client_side_identity
```

Identity and access management for Amazon FSx for NetApp ONTAP

AWS Identity and Access Management (IAM) is an AWS service that helps an administrator securely control access to AWS resources. IAM administrators control who can be *authenticated* (signed in) and *authorized* (have permissions) to use Amazon FSx resources. IAM is an AWS service that you can use with no additional charge.

Topics

- Audience
- Authenticating with identities
- Managing access using policies
- How Amazon FSx for NetApp ONTAP works with IAM
- Identity-based policy examples for Amazon FSx for NetApp ONTAP
- Troubleshooting Amazon FSx for NetApp ONTAP identity and access
- Using service-linked roles for Amazon FSx
- Using tags with Amazon FSx

Audience

How you use AWS Identity and Access Management (IAM) differs based on your role:

- **Service user** - request permissions from your administrator if you cannot access features (see Troubleshooting Amazon FSx for NetApp ONTAP identity and access)
- **Service administrator** - determine user access and submit permission requests (see How Amazon FSx for NetApp ONTAP works with IAM)
- **IAM administrator** - write policies to manage access (see Identity-based policy examples for Amazon FSx for NetApp ONTAP)

Authenticating with identities

Authentication is how you sign in to AWS using your identity credentials. You must be authenticated as the AWS account root user, an IAM user, or by assuming an IAM role.

You can sign in as a federated identity using credentials from an identity source like AWS IAM Identity Center (IAM Identity Center), single sign-on authentication, or Google/Facebook credentials. For more information about signing in, see How to sign in to your AWS account in the *AWS Sign-In User Guide*.

For programmatic access, AWS provides an SDK and CLI to cryptographically sign requests. For more information, see AWS Signature Version 4 for API requests in the *IAM User Guide*.

AWS account root user

When you create an AWS account, you begin with one sign-in identity called the AWS account *root user* that has complete access to all AWS services and resources. We strongly recommend that you don't use the root user for everyday tasks. For tasks that require root user credentials, see Tasks that require root user credentials in the *IAM User Guide*.

Federated identity

As a best practice, require human users to use federation with an identity provider to access AWS services using temporary credentials.

A *federated identity* is a user from your enterprise directory, web identity provider, or Directory Service that accesses AWS services using credentials from an identity source. Federated identities assume roles that provide temporary credentials.

For centralized access management, we recommend AWS IAM Identity Center. For more information, see What is IAM Identity Center? in the *AWS IAM Identity Center User Guide*.

IAM users and groups

An *IAM user* is an identity with specific permissions for a single person or application. We recommend using temporary credentials instead of IAM users with long-term credentials. For more information, see Require human users to use federation with an identity provider to access AWS using temporary credentials in the *IAM User Guide*.

An *IAM group* specifies a collection of IAM users and makes permissions easier to manage for large sets of users. For more information, see Use cases for IAM users in the *IAM User Guide*.

IAM roles

An *IAM role* is an identity with specific permissions that provides temporary credentials. You can assume a role by switching from a user to an IAM role (console) or by calling an AWS CLI or AWS API operation. For more information, see Methods to assume a role in the *IAM User Guide*.

IAM roles are useful for federated user access, temporary IAM user permissions, cross-account access, cross-service access, and applications running on Amazon EC2. For more information, see Cross account resource access in IAM in the *IAM User Guide*.

Managing access using policies

You control access in AWS by creating policies and attaching them to AWS identities or resources. A policy defines permissions when associated with an identity or resource. AWS evaluates these policies when a principal makes a request. Most policies are stored in AWS as JSON documents. For more information about JSON policy documents, see Overview of JSON policies in the *IAM User Guide*.

Using policies, administrators specify who has access to what by defining which **principal** can perform **actions** on what **resources**, and under what **conditions**.

By default, users and roles have no permissions. An IAM administrator creates IAM policies and adds them to roles, which users can then assume. IAM policies define permissions regardless of the method used to perform the operation.

Identity-based policies

Identity-based policies are JSON permissions policy documents that you attach to an identity (user, group, or role). These policies control what actions identities can perform, on which resources, and under what conditions. To learn how to create an identity-based policy, see Define custom IAM permissions with customer managed policies in the *IAM User Guide*.

Identity-based policies can be *inline policies* (embedded directly into a single identity) or *managed policies* (standalone policies attached to multiple identities). To learn how to choose between managed and inline policies, see Choose between managed policies and inline policies in the *IAM User Guide*.

Resource-based policies

Resource-based policies are JSON policy documents that you attach to a resource. Examples include IAM *role trust policies* and Amazon S3 *bucket policies*. In services that support resource-

based policies, service administrators can use them to control access to a specific resource. You must specify a principal in a resource-based policy.

Resource-based policies are inline policies that are located in that service. You can't use AWS managed policies from IAM in a resource-based policy.

Other policy types

AWS supports additional policy types that can set the maximum permissions granted by more common policy types:

- **Permissions boundaries** – Set the maximum permissions that an identity-based policy can grant to an IAM entity. For more information, see Permissions boundaries for IAM entities in the *IAM User Guide*.
- **Service control policies (SCPs)** – Specify the maximum permissions for an organization or organizational unit in AWS Organizations. For more information, see Service control policies in the *AWS Organizations User Guide*.
- **Resource control policies (RCPs)** – Set the maximum available permissions for resources in your accounts. For more information, see Resource control policies (RCPs) in the *AWS Organizations User Guide*.
- **Session policies** – Advanced policies passed as a parameter when creating a temporary session for a role or federated user. For more information, see Session policies in the *IAM User Guide*.

Multiple policy types

When multiple types of policies apply to a request, the resulting permissions are more complicated to understand. To learn how AWS determines whether to allow a request when multiple policy types are involved, see Policy evaluation logic in the *IAM User Guide*.

How Amazon FSx for NetApp ONTAP works with IAM

Before you use IAM to manage access to Amazon FSx, learn what IAM features are available to use with Amazon FSx.

IAM features you can use with Amazon FSx for NetApp ONTAP

IAM feature	Amazon FSx support
Identity-based policies	Yes
Resource-based policies	No
Policy actions	Yes
Policy resources	Yes
Policy condition keys	Yes
ACLs	No
ABAC (tags in policies)	Yes
Temporary credentials	Yes
Forward access sessions (FAS)	Yes
Service roles	No
Service-linked roles	Yes

To get a high-level view of how Amazon FSx and other AWS services work with most IAM features, see AWS services that work with IAM in the *IAM User Guide*.

Identity-based policies for Amazon FSx

Supports identity-based policies: Yes

Identity-based policies are JSON permissions policy documents that you can attach to an identity, such as an IAM user, group of users, or role. These policies control what actions users and roles can perform, on which resources, and under what conditions. To learn how to create an identity-based policy, see Define custom IAM permissions with customer managed policies in the *IAM User Guide*.

With IAM identity-based policies, you can specify allowed or denied actions and resources as well as the conditions under which actions are allowed or denied. To learn about all of the elements that you can use in a JSON policy, see IAM JSON policy elements reference in the *IAM User Guide*.

Identity-based policy examples for Amazon FSx

To view examples of Amazon FSx identity-based policies, see Identity-based policy examples for Amazon FSx for NetApp ONTAP.

Resource-based policies within Amazon FSx

Supports resource-based policies: No

Policy actions for Amazon FSx

Supports policy actions: Yes

Administrators can use AWS JSON policies to specify who has access to what. That is, which **principal** can perform **actions** on what **resources**, and under what **conditions**.

The `Action` element of a JSON policy describes the actions that you can use to allow or deny access in a policy. Include actions in a policy to grant permissions to perform the associated operation.

To see a list of Amazon FSx actions, see Actions defined by Amazon FSx in the *Service Authorization Reference*.

Policy actions in Amazon FSx use the following prefix before the action:

```
fsx
```

To specify multiple actions in a single statement, separate them with commas.

```
"Action": [
      "fsx:action1",
      "fsx:action2"
         ]
```

To view examples of Amazon FSx identity-based policies, see Identity-based policy examples for Amazon FSx for NetApp ONTAP.

Policy resources for Amazon FSx

Supports policy resources: Yes

Administrators can use AWS JSON policies to specify who has access to what. That is, which **principal** can perform **actions** on what **resources**, and under what **conditions**.

The `Resource` JSON policy element specifies the object or objects to which the action applies. As a best practice, specify a resource using its Amazon Resource Name (ARN). For actions that don't support resource-level permissions, use a wildcard (*) to indicate that the statement applies to all resources.

```
"Resource": "*"
```

To see a list of Amazon FSx resource types and their ARNs, see Resources defined by Amazon FSx in the *Service Authorization Reference*. To learn with which actions you can specify the ARN of each resource, see Actions defined by Amazon FSx.

To view examples of Amazon FSx identity-based policies, see Identity-based policy examples for Amazon FSx for NetApp ONTAP.

Policy condition keys for Amazon FSx

Supports service-specific policy condition keys: Yes

Administrators can use AWS JSON policies to specify who has access to what. That is, which **principal** can perform **actions** on what **resources**, and under what **conditions**.

The `Condition` element specifies when statements execute based on defined criteria. You can create conditional expressions that use condition operators, such as equals or less than, to match the condition in the policy with values in the request. To see all AWS global condition keys, see AWS global condition context keys in the *IAM User Guide*.

To see a list of Amazon FSx condition keys, see Condition keys for Amazon FSx in the *Service Authorization Reference*. To learn with which actions and resources you can use a condition key, see Actions defined by Amazon FSx.

To view examples of Amazon FSx identity-based policies, see Identity-based policy examples for Amazon FSx for NetApp ONTAP.

Access control lists (ACLs) in Amazon FSx

Supports ACLs: No

Attribute-based access control (ABAC) with Amazon FSx

Supports ABAC (tags in policies): Yes

Attribute-based access control (ABAC) is an authorization strategy that defines permissions based on attributes called tags. You can attach tags to IAM entities and AWS resources, then design ABAC policies to allow operations when the principal's tag matches the tag on the resource.

To control access based on tags, you provide tag information in the condition element of a policy using the `aws:ResourceTag/key-name`, `aws:RequestTag/key-name`, or `aws:TagKeys` condition keys.

If a service supports all three condition keys for every resource type, then the value is **Yes** for the service. If a service supports all three condition keys for only some resource types, then the value is **Partial**.

For more information about ABAC, see Define permissions with ABAC authorization in the *IAM User Guide*. To view a tutorial with steps for setting up ABAC, see Use attribute-based access control (ABAC) in the *IAM User Guide*.

For more information about tagging Amazon FSx resources, see Tagging Amazon FSx resources.

To view an example identity-based policy for limiting access to a resource based on the tags on that resource, see Using tags to control access to your Amazon FSx resources.

Using Temporary credentials with Amazon FSx

Supports temporary credentials: Yes

Temporary credentials provide short-term access to AWS resources and are automatically created when you use federation or switch roles. AWS recommends that you dynamically generate temporary credentials instead of using long-term access keys. For more information, see Temporary security credentials in IAM and AWS services that work with IAM in the *IAM User Guide*.

Forward access sessions for Amazon FSx

Supports forward access sessions (FAS): Yes

Forward access sessions (FAS) use the permissions of the principal calling an AWS service, combined with the requesting AWS service to make requests to downstream services. For policy details when making FAS requests, see Forward access sessions.

Service roles for Amazon FSx

Supports service roles: No

Service-linked roles for Amazon FSx

Supports service-linked roles: Yes

A service-linked role is a type of service role that is linked to an AWS service. The service can assume the role to perform an action on your behalf. Service-linked roles appear in your AWS account and are owned by the service. An IAM administrator can view, but not edit the permissions for service-linked roles.

For details about creating or managing Amazon FSx service-linked roles, see Using service-linked roles for Amazon FSx.

Identity-based policy examples for Amazon FSx for NetApp ONTAP

By default, users and roles don't have permission to create or modify Amazon FSx resources. To grant users permission to perform actions on the resources that they need, an IAM administrator can create IAM policies.

To learn how to create an IAM identity-based policy by using these example JSON policy documents, see Create IAM policies (console) in the *IAM User Guide*.

For details about actions and resource types defined by Amazon FSx, including the format of the ARNs for each of the resource types, see Actions, resources, and condition keys for Amazon FSx in the *Service Authorization Reference*.

Topics

- Policy best practices
- Using the Amazon FSx console
- Allow users to view their own permissions

Policy best practices

Identity-based policies determine whether someone can create, access, or delete Amazon FSx resources in your account. These actions can incur costs for your AWS account. When you create or edit identity-based policies, follow these guidelines and recommendations:

- **Get started with AWS managed policies and move toward least-privilege permissions** – To get started granting permissions to your users and workloads, use the *AWS managed policies* that grant permissions for many common use cases. They are available in your AWS account. We recommend that you reduce permissions further by defining AWS customer managed policies that are specific to your use cases. For more information, see AWS managed policies or AWS managed policies for job functions in the *IAM User Guide*.
- **Apply least-privilege permissions** – When you set permissions with IAM policies, grant only the permissions required to perform a task. You do this by defining the actions that can be taken on specific resources under specific conditions, also known as *least-privilege permissions*. For more information about using IAM to apply permissions, see Policies and permissions in IAM in the *IAM User Guide*.
- **Use conditions in IAM policies to further restrict access** – You can add a condition to your policies to limit access to actions and resources. For example, you can write a policy condition to specify that all requests must be sent using SSL. You can also use conditions to grant access to service actions if they are used through a specific AWS service, such as CloudFormation. For more information, see IAM JSON policy elements: Condition in the *IAM User Guide*.
- **Use IAM Access Analyzer to validate your IAM policies to ensure secure and functional permissions** – IAM Access Analyzer validates new and existing policies so that the policies adhere to the IAM policy language (JSON) and IAM best practices. IAM Access Analyzer provides more than 100 policy checks and actionable recommendations to help you author secure and functional policies. For more information, see Validate policies with IAM Access Analyzer in the *IAM User Guide*.
- **Require multi-factor authentication (MFA)** – If you have a scenario that requires IAM users or a root user in your AWS account, turn on MFA for additional security. To require MFA when API operations are called, add MFA conditions to your policies. For more information, see Secure API access with MFA in the *IAM User Guide*.

For more information about best practices in IAM, see Security best practices in IAM in the *IAM User Guide*.

Using the Amazon FSx console

To access the Amazon FSx for NetApp ONTAP console, you must have a minimum set of permissions. These permissions must allow you to list and view details about the Amazon FSx resources in your AWS account. If you create an identity-based policy that is more restrictive than

the minimum required permissions, the console won't function as intended for entities (users or roles) with that policy.

You don't need to allow minimum console permissions for users that are making calls only to the AWS CLI or the AWS API. Instead, allow access to only the actions that match the API operation that they're trying to perform.

To ensure that users and roles can still use the Amazon FSx console, also attach the `AmazonFSxConsoleReadOnlyAccess` AWS managed policy to the entities. For more information, see Adding permissions to a user in the *IAM User Guide*.

You can see the `AmazonFSxConsoleReadOnlyAccess` and other Amazon FSx managed service policies in AWS managed policies for Amazon FSx for NetApp ONTAP.

Allow users to view their own permissions

This example shows how you might create a policy that allows IAM users to view the inline and managed policies that are attached to their user identity. This policy includes permissions to complete this action on the console or programmatically using the AWS CLI or AWS API.

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Sid": "ViewOwnUserInfo",
            "Effect": "Allow",
            "Action": [
                "iam:GetUserPolicy",
                "iam:ListGroupsForUser",
                "iam:ListAttachedUserPolicies",
                "iam:ListUserPolicies",
                "iam:GetUser"
            ],
            "Resource": ["arn:aws:iam::*:user/${aws:username}"]
        },
        {
            "Sid": "NavigateInConsole",
            "Effect": "Allow",
            "Action": [
                "iam:GetGroupPolicy",
                "iam:GetPolicyVersion",
                "iam:GetPolicy",
```

```
                "iam:ListAttachedGroupPolicies",
                "iam:ListGroupPolicies",
                "iam:ListPolicyVersions",
                "iam:ListPolicies",
                "iam:ListUsers"
            ],
            "Resource": "*"
        }
    ]
}
```

Troubleshooting Amazon FSx for NetApp ONTAP identity and access

Use the following information to help you diagnose and fix common issues that you might encounter when working with Amazon FSx and IAM.

Topics

- I am not authorized to perform an action in Amazon FSx
- I am not authorized to perform iam:PassRole
- I want to allow people outside of my AWS account to access my Amazon FSx resources

I am not authorized to perform an action in Amazon FSx

If you receive an error that you're not authorized to perform an action, your policies must be updated to allow you to perform the action.

The following example error occurs when the `mateojackson` IAM user tries to use the console to view details about a fictional *`my-example-widget`* resource but doesn't have the fictional `fsx:`*`GetWidget`* permissions.

```
User: arn:aws:iam::123456789012:user/mateojackson is not authorized to perform:
 fsx:GetWidget on resource: my-example-widget
```

In this case, the policy for the `mateojackson` user must be updated to allow access to the *`my-example-widget`* resource by using the `fsx:`*`GetWidget`* action.

If you need help, contact your AWS administrator. Your administrator is the person who provided you with your sign-in credentials.

I am not authorized to perform iam:PassRole

If you receive an error that you're not authorized to perform the `iam:PassRole` action, your policies must be updated to allow you to pass a role to Amazon FSx.

Some AWS services allow you to pass an existing role to that service instead of creating a new service role or service-linked role. To do this, you must have permissions to pass the role to the service.

The following example error occurs when an IAM user named `marymajor` tries to use the console to perform an action in Amazon FSx. However, the action requires the service to have permissions that are granted by a service role. Mary does not have permissions to pass the role to the service.

```
User: arn:aws:iam::123456789012:user/marymajor is not authorized to perform:
 iam:PassRole
```

In this case, Mary's policies must be updated to allow her to perform the `iam:PassRole` action.

If you need help, contact your AWS administrator. Your administrator is the person who provided you with your sign-in credentials.

I want to allow people outside of my AWS account to access my Amazon FSx resources

You can create a role that users in other accounts or people outside of your organization can use to access your resources. You can specify who is trusted to assume the role. For services that support resource-based policies or access control lists (ACLs), you can use those policies to grant people access to your resources.

To learn more, consult the following:

- To learn whether Amazon FSx supports these features, see How Amazon FSx for NetApp ONTAP works with IAM.
- To learn how to provide access to your resources across AWS accounts that you own, see Providing access to an IAM user in another AWS account that you own in the *IAM User Guide*.
- To learn how to provide access to your resources to third-party AWS accounts, see Providing access to AWS accounts owned by third parties in the *IAM User Guide*.
- To learn how to provide access through identity federation, see Providing access to externally authenticated users (identity federation) in the *IAM User Guide*.

- To learn the difference between using roles and resource-based policies for cross-account access, see Cross account resource access in IAM in the *IAM User Guide*.

Using service-linked roles for Amazon FSx

Amazon FSx uses AWS Identity and Access Management (IAM) service-linked roles. A service-linked role is a unique type of IAM role that is linked directly to Amazon FSx. Service-linked roles are predefined by Amazon FSx and include all the permissions that the service requires to call other AWS services on your behalf.

A service-linked role makes setting up Amazon FSx easier because you don't have to manually add the necessary permissions. Amazon FSx defines the permissions of its service-linked roles, and unless defined otherwise, only Amazon FSx can assume its roles. The defined permissions include the trust policy and the permissions policy, and that permissions policy cannot be attached to any other IAM entity.

You can delete a service-linked role only after first deleting their related resources. This protects your Amazon FSx resources because you can't inadvertently remove permission to access the resources.

For information about other services that support service-linked roles, see AWS Services That Work with IAM and look for the services that have **Yes** in the **Service-Linked Role** column. Choose a **Yes** with a link to view the service-linked role documentation for that service.

Service-linked role permissions for Amazon FSx

Amazon FSx uses the service-linked role named **AWSServiceRoleForAmazonFSx** – Which performs certain actions in your account, like creating Elastic Network Interfaces for your file systems in your VPC, and publishing file system and volume metrics in CloudWatch.

For updates to this policy, see AmazonFSxServiceRolePolicy.

Permissions details

The AWSServiceRoleForAmazonFSx role permissions are defined by the AmazonFSxServiceRolePolicy AWS managed policy. The AWSServiceRoleForAmazonFSx has the following permissions:

> **Note**
>
> The AWSServiceRoleForAmazonFSx is used by all Amazon FSx file system types; some of the listed permissions are not applicable to FSx for ONTAP.

- `ds` – Allows Amazon FSx to view, authorize, and unauthorize applications in your Directory Service directory.
- `ec2` – Allows Amazon FSx to do the following:
  - View, create, and disassociate network interfaces associated with an Amazon FSx file system.
  - View one or more Elastic IP addresses associated with an Amazon FSx file system.
  - View Amazon VPCs, security groups, and subnets associated with an Amazon FSx file system.
  - Assign IPv6 addresses to customer network interfaces that have an `AmazonFSx.FileSystemId` tag.
  - Unassign IPv6 addresses from customer network interfaces that have an `AmazonFSx.FileSystemId` tag.
  - To provide enhanced security group validation of all security groups that can be used with a VPC.
  - Create a permission for an AWS-authorized user to perform certain operations on a network interface.
- `cloudwatch` – Allows Amazon FSx to publish metric data points to CloudWatch under the AWS/FSx namespace.
- `route53` – Allows Amazon FSx to associate an Amazon VPC with a private hosted zone.

JSON

```
{
    "Version":"2012-10-17",
    "Statement": [
        {
            "Sid": "CreateFileSystem",
            "Effect": "Allow",
            "Action": [
                "ds:AuthorizeApplication",
                "ds:GetAuthorizedApplicationDetails",
```

```
                "ds:UnauthorizeApplication",
                "ec2:CreateNetworkInterface",
                "ec2:CreateNetworkInterfacePermission",
                "ec2:DeleteNetworkInterface",
                "ec2:DescribeAddresses",
                "ec2:DescribeDhcpOptions",
                "ec2:DescribeNetworkInterfaces",
                "ec2:DescribeRouteTables",
                "ec2:DescribeSecurityGroups",
                "ec2:DescribeSubnets",
                "ec2:DescribeVPCs",
                "ec2:DisassociateAddress",
                "ec2:GetSecurityGroupsForVpc",
                "route53:AssociateVPCWithHostedZone"
            ],
            "Resource": "*"
        },
        {
            "Sid": "PutMetrics",
            "Effect": "Allow",
            "Action": [
                "cloudwatch:PutMetricData"
            ],
            "Resource": [
                "*"
            ],
            "Condition": {
                "StringEquals": {
                    "cloudwatch:namespace": "AWS/FSx"
                }
            }
        },

        {
            "Sid": "TagResourceNetworkInterface",
            "Effect": "Allow",
            "Action": [
                "ec2:CreateTags"
            ],
            "Resource": [
                "arn:aws:ec2:*:*:network-interface/*"
            ],
            "Condition": {
                "StringEquals": {
```

```
                    "ec2:CreateAction": "CreateNetworkInterface"
                },
                "ForAllValues:StringEquals": {
                    "aws:TagKeys": "AmazonFSx.FileSystemId"
                }
            }
        },
        {
            "Sid": "ManageNetworkInterface",
            "Effect": "Allow",
            "Action": [
                "ec2:AssignPrivateIpAddresses",
                "ec2:ModifyNetworkInterfaceAttribute",
                "ec2:UnassignPrivateIpAddresses"
            ],
            "Resource": [
                "arn:aws:ec2:*:*:network-interface/*"
            ],
            "Condition": {
                "Null": {
                    "aws:ResourceTag/AmazonFSx.FileSystemId": "false"
                }
            }
        },
        {
            "Sid": "ManageRouteTable",
            "Effect": "Allow",
            "Action": [
                "ec2:CreateRoute",
                "ec2:ReplaceRoute",
                "ec2:DeleteRoute"
            ],
            "Resource": [
                "arn:aws:ec2:*:*:route-table/*"
            ],
            "Condition": {
                "StringEquals": {
                    "aws:ResourceTag/AmazonFSx": "ManagedByAmazonFSx"
                }
            }
        }
    ]
}
```

Any updates to this policy are described in Amazon FSx updates to AWS managed policies.

You must configure permissions to allow an IAM entity (such as a user, group, or role) to create, edit, or delete a service-linked role. For more information, see Service-Linked Role Permissions in the IAM User Guide.

Creating a service-linked role for Amazon FSx

You don't need to manually create a service-linked role. When you create a file system in the AWS Management Console, the IAM CLI, or the IAM API, Amazon FSx creates the service-linked role for you.

> **Important**
>
> This service-linked role can appear in your account if you completed an action in another service that uses the features supported by this role. To learn more, see A New Role Appeared in My IAM Account.

If you delete this service-linked role, and then need to create it again, you can use the same process to recreate the role in your account. When you create a file system, Amazon FSx creates the service-linked role for you again.

Editing a service-linked role for Amazon FSx

Amazon FSx does not allow you to edit the AWSServiceRoleForAmazonFSx service-linked role. After you create a service-linked role, you cannot change the name of the role because various entities might reference the role. However, you can edit the description of the role using IAM. For more information, see Editing a Service-Linked Role in the *IAM User Guide*.

Deleting a service-linked role for Amazon FSx

If you no longer need to use a feature or service that requires a service-linked role, we recommend that you delete that role. That way you don’t have an unused entity that is not actively monitored or maintained. However, you must delete all of your file systems and backups before you can manually delete the service-linked role.

> **Note**
>
> If the Amazon FSx service is using the role when you try to delete the resources, then the deletion might fail. If that happens, wait for a few minutes and try the operation again.

To manually delete the service-linked role using IAM

Use the IAM console, the IAM CLI, or the IAM API to delete the AWSServiceRoleForAmazonFSx service-linked role. For more information, see Deleting a Service-Linked Role in the *IAM User Guide*.

Supported regions for Amazon FSx service-linked roles

Amazon FSx supports using service-linked roles in all of the regions where the service is available. For more information, see AWS Regions and Endpoints.

Using tags with Amazon FSx

You can use tags to control access to Amazon FSx resources and to implement attribute-based access control (ABAC). To apply tags to Amazon FSx resources during creation, users must have certain AWS Identity and Access Management (IAM) permissions.

Grant permission to tag resources during creation

With some resource-creating Amazon FSx API actions, you can specify tags when you create the resource. You can use these resource tags to implement attribute-based access control (ABAC). For more information, see What is ABAC for AWS? in the *IAM User Guide*.

For users to tag resources on creation, they must have permission to use the action that creates the resource, such as `fsx:CreateFileSystem`, `fsx:CreateStorageVirtualMachine`, or `fsx:CreateVolume`. If tags are specified in the resource-creating action, IAM performs additional authorization on the `fsx:TagResource` action to verify if users have permissions to create tags. Therefore, users must also have explicit permissions to use the `fsx:TagResource` action.

The following example policy allows users to create file systems and storage virtual machines (SVMs) and apply tags to them during creation in a specific AWS account.

```
{
  "Statement": [
```

```
    {
      "Effect": "Allow",
      "Action": [
         "fsx:CreateFileSystem",
         "fsx:CreateStorageVirtualMachine",
         "fsx:TagResource"
      ],
      "Resource": [
         "arn:aws:fsx:region:account-id:file-system/*",
         "arn:aws:fsx:region:account-id:file-system/*/storage-virtual-machine/*"
      ]
    }
  ]
}
```

Similarly, the following policy allows users to create backups on a specific file system and apply any tags to the backup during backup creation.

```
{
  "Statement": [
    {
      "Effect": "Allow",
      "Action": [
         "fsx:CreateBackup"
      ],
      "Resource": "arn:aws:fsx:region:account-id:file-system/file-system-id*"
    },
    {
      "Effect": "Allow",
      "Action": [
         "fsx:TagResource"
      ],
      "Resource": "arn:aws:fsx:region:account-id:backup/*"
    }
  ]
}
```

The `fsx:TagResource` action is evaluated only if tags are applied during the resource-creating action. Therefore, a user who has permissions to create a resource (assuming there are no tagging conditions) does not require permission to use the `fsx:TagResource` action if no tags are specified in the request. However, if the user attempts to create a resource with tags, the request fails if the user does not have permissions to use the `fsx:TagResource` action.

For more information about tagging Amazon FSx resources, see Tagging Amazon FSx resources. For more information about using tags to control access to Amazon FSx resources, see Using tags to control access to your Amazon FSx resources.

Using tags to control access to your Amazon FSx resources

To control access to Amazon FSx resources and actions, you can use IAM policies based on tags. You can provide this control in two ways:

- You can control access to Amazon FSx resources based on the tags on those resources.
- You can control which tags can be passed in an IAM request condition.

For information about how to use tags to control access to AWS resources, see Controlling access using tags in the *IAM User Guide*. For more information about tagging Amazon FSx resources at creation, see Grant permission to tag resources during creation. For more information about tagging resources, see Tagging Amazon FSx resources.

Controlling access based on tags on a resource

To control which actions a user or role can perform on an Amazon FSx resource, you can use tags on the resource. For example, you might want to allow or deny specific API operations on a file system resource based on the key-value pair of the tag on the resource.

Example policy – Create a file system only when a specific tag is used

This policy allows the user to create a file system only when they tag it with a specific tag key-value pair, in this example, `key=Department`, `value=Finance`.

```
{
    "Effect": "Allow",
    "Action": [
        "fsx:CreateFileSystem",
        "fsx:TagResource"
    ],
    "Resource": "arn:aws:fsx:region:account-id:file-system/*",
    "Condition": {
        "StringEquals": {
            "aws:RequestTag/Department": "Finance"
        }
    }
```

```
}
```

Example policy – Create backups only of Amazon FSx for NetApp ONTAP volumes with a specific tag

This policy allows users to create backups only of FSx for ONTAP volumes that are tagged with the key-value pair `key=Department`, `value=Finance`. The backup is created with the tag `Department=Finance`.

JSON

```
{
    "Version":"2012-10-17",
    "Statement": [
        {
            "Effect": "Allow",
            "Action": [
                "fsx:CreateBackup"
            ],
            "Resource": "arn:aws:fsx:us-east-1:111122223333:volume/*",
            "Condition": {
                "StringEquals": {
                    "aws:ResourceTag/Department": "Finance"
                }
            }
        },
        {
            "Effect": "Allow",
            "Action": [
                "fsx:TagResource",
                "fsx:CreateBackup"
            ],
            "Resource": "arn:aws:fsx:us-east-1:111122223333:backup/*",
            "Condition": {
                "StringEquals": {
                    "aws:RequestTag/Department": "Finance"
                }
            }
        }
    ]
}
```

Example policy – Create a volume with a specific tag from backups with a specific tag

This policy allows users to create volumes that are tagged with `Department=Finance` only from backups that are tagged with `Department=Finance`.

JSON

```
{
    "Version":"2012-10-17",
    "Statement": [
        {
            "Effect": "Allow",
            "Action": [
                "fsx:CreateVolumeFromBackup",
                "fsx:TagResource"
            ],
            "Resource": "arn:aws:fsx:us-east-1:111122223333:volume/*",
            "Condition": {
                "StringEquals": {
                    "aws:RequestTag/Department": "Finance"
                }
            }
        },
        {
            "Effect": "Allow",
            "Action": [
                "fsx:CreateVolumeFromBackup"
            ],
            "Resource": "arn:aws:fsx:us-east-1:111122223333:backup/*",
            "Condition": {
                "StringEquals": {
                    "aws:ResourceTag/Department": "Finance"
                }
            }
        }
    ]
}
```

Example policy – Delete file systems with specific tags

This policy allows a user to delete only file systems that are tagged with `Department=Finance`. If they create a final backup, then it must be tagged with `Department=Finance`.

JSON

```
{
    "Version":"2012-10-17",
    "Statement": [
        {
            "Effect": "Allow",
            "Action": [
                "fsx:DeleteFileSystem"
            ],
            "Resource": "arn:aws:fsx:us-east-1:111122223333:file-system/*",
            "Condition": {
                "StringEquals": {
                    "aws:ResourceTag/Department": "Finance"
                }
            }
        },
        {
            "Effect": "Allow",
            "Action": [
                "fsx:TagResource"
            ],
            "Resource": "arn:aws:fsx:us-east-1:111122223333:backup/*",
            "Condition": {
                "StringEquals": {
                    "aws:RequestTag/Department": "Finance"
                }
            }
        }
    ]
}
```

Example policy – Delete a volume with specific tags

This policy allows a user to delete only volumes that are tagged with `Department=Finance`. If they create a final backup, then it must be tagged with `Department=Finance`.

JSON

```
{
    "Version":"2012-10-17",
    "Statement": [
        {
            "Effect": "Allow",
            "Action": [
                "fsx:DeleteVolume"
            ],
            "Resource": "arn:aws:fsx:us-east-1:111122223333:volume/*",
            "Condition": {
                "StringEquals": {
                    "aws:ResourceTag/Department": "Finance"
                }
            }
        },
        {
            "Effect": "Allow",
            "Action": [
                "fsx:TagResource"
            ],
            "Resource": "arn:aws:fsx:us-east-1:111122223333:backup/*",
            "Condition": {
                "StringEquals": {
                    "aws:RequestTag/Department": "Finance"
                }
            }
        }
    ]
}
```

AWS managed policies for Amazon FSx for NetApp ONTAP

An AWS managed policy is a standalone policy that is created and administered by AWS. AWS managed policies are designed to provide permissions for many common use cases so that you can start assigning permissions to users, groups, and roles.

Keep in mind that AWS managed policies might not grant least-privilege permissions for your specific use cases because they're available for all AWS customers to use. We recommend that you

reduce permissions further by defining customer managed policies that are specific to your use cases.

You cannot change the permissions defined in AWS managed policies. If AWS updates the permissions defined in an AWS managed policy, the update affects all principal identities (users, groups, and roles) that the policy is attached to. AWS is most likely to update an AWS managed policy when a new AWS service is launched or new API operations become available for existing services.

For more information, see AWS managed policies in the *IAM User Guide*.

AmazonFSxServiceRolePolicy

Allows Amazon FSx to manage AWS resources on your behalf. See Using service-linked roles for Amazon FSx to learn more.

AWS managed policy: AmazonFSxDeleteServiceLinkedRoleAccess

You can't attach `AmazonFSxDeleteServiceLinkedRoleAccess` to your IAM entities. This policy is linked to a service and used only with the service-linked role for that service. You cannot attach, detach, modify, or delete this policy. For more information, see Using service-linked roles for Amazon FSx.

This policy grants administrative permissions that allow Amazon FSx to delete its Service Linked Role for Amazon S3 access, used only by Amazon FSx for Lustre.

Permissions details

This policy includes permissions in `iam` to allow Amazon FSx to view, delete, and view the deletion status for the FSx Service Linked Roles for Amazon S3 access.

To view the permissions for this policy, see AmazonFSxDeleteServiceLinkedRoleAccess in the AWS Managed Policy Reference Guide.

AWS managed policy: AmazonFSxFullAccess

You can attach AmazonFSxFullAccess to your IAM entities. Amazon FSx also attaches this policy to a service role that allows Amazon FSx to perform actions on your behalf.

Provides full access to Amazon FSx and access to related AWS services.

Permissions details

This policy includes the following permissions.

- `fsx` – Allows principals full access to perform all Amazon FSx actions, except for `BypassSnaplockEnterpriseRetention`.
- `ds` – Allows principals to view information about the Directory Service directories.
- `ec2`
  - Allows principals to create tags under the specified conditions.
  - To provide enhanced security group validation of all security groups that can be used with a VPC.
- `iam` – Allows principles to create an Amazon FSx service linked role on the user's behalf. This is required so that Amazon FSx can manage AWS resources on the user's behalf.
- `firehose` – Allows principals to write records to a Amazon Data Firehose. This is required so that users can monitor FSx for Windows File Server file system access by sending audit access logs to Firehose.
- `logs` – Allows principals to create log groups, log streams, and write events to log streams. This is required so that users can monitor FSx for Windows File Server file system access by sending audit access logs to CloudWatch Logs.

To view the permissions for this policy, see AmazonFSxFullAccess in the AWS Managed Policy Reference Guide.

AWS managed policy: AmazonFSxConsoleFullAccess

You can attach the `AmazonFSxConsoleFullAccess` policy to your IAM identities.

This policy grants administrative permissions that allow full access to Amazon FSx and access to related AWS services via the AWS Management Console.

Permissions details

This policy includes the following permissions.

- `fsx` – Allows principals to perform all actions in the Amazon FSx management console, except for `BypassSnaplockEnterpriseRetention`.

- `cloudwatch` – Allows principals to view CloudWatch Alarms and metrics in the Amazon FSx management console.
- `ds` – Allows principals to list information about an Directory Service directory.
- `ec2`
  - Allows principals to create tags on route tables, list network interfaces, route tables, security groups, subnets and the VPC associated with an Amazon FSx file system.
  - Allows principals to provide enhanced security group validation of all security groups that can be used with a VPC.
  - Allows principals to view the elastic network interfaces associated with an Amazon FSx file system.
- `kms` – Allows principals to list aliases for AWS Key Management Service keys.
- `s3` – Allows principals to list some or all of the objects in an Amazon S3 bucket (up to 1000).
- `secretsmanager` – Allows principals to list secrets in AWS Secrets Manager for selecting domain join service account credentials.
- `iam` – Grants permission to create a service linked role that allows Amazon FSx to perform actions on the user's behalf.

To view the permissions for this policy, see AmazonFSxConsoleFullAccess in the AWS Managed Policy Reference Guide.

AWS managed policy: AmazonFSxConsoleReadOnlyAccess

You can attach the `AmazonFSxConsoleReadOnlyAccess` policy to your IAM identities.

This policy grants read-only permissions to Amazon FSx and related AWS services so that users can view information about these services in the AWS Management Console.

Permissions details

This policy includes the following permissions.

- `fsx` – Allows principals to view information about Amazon FSx file systems, including all tags, in the Amazon FSx Management Console.
- `cloudwatch` – Allows principals to view CloudWatch Alarms and metrics in the Amazon FSx Management Console.

- `ds` – Allows principals to view information about an Directory Service directory in the Amazon FSx Management Console.
- `ec2`
  - Allows principals to view network interfaces, security groups, subnets and the VPC associated with an Amazon FSx file system in the Amazon FSx Management Console.
  - Allows principals to provide enhanced security group validation of all security groups that can be used with a VPC.
  - Allows principals to view the elastic network interfaces associated with an Amazon FSx file system.
- `kms` – Allows principals to view aliases for AWS Key Management Service keys in the Amazon FSx Management Console.
- `log` – Allows principals to describe the Amazon CloudWatch Logs log groups associated with the account making the request. This is required so that principals can view the existing file access auditing configuration for an FSx for Windows File Server file system.
- `secretsmanager` – Allows principals to list secrets in AWS Secrets Manager for selecting domain join service account credentials.
- `firehose` – Allows principals to describe the Amazon Data Firehose delivery streams associated with the account making the request. This is required so that principals can view the existing file access auditing configuration for an FSx for Windows File Server file system.

To view the permissions for this policy, see AmazonFSxConsoleReadOnlyAccess in the AWS Managed Policy Reference Guide.

AWS managed policy: AmazonFSxReadOnlyAccess

You can attach the `AmazonFSxReadOnlyAccess` policy to your IAM identities.

- `fsx` – Allows principals to view information about Amazon FSx file systems, including all tags, in the Amazon FSx Management Console.
- `ec2` – To provide enhanced security group validation of all security groups that can be used with a VPC.

To view the permissions for this policy, see AmazonFSxReadOnlyAccess in the AWS Managed Policy Reference Guide.

Amazon FSx updates to AWS managed policies

View details about updates to AWS managed policies for Amazon FSx since this service began tracking these changes. For automatic alerts about changes to this page, subscribe to the RSS feed on the Amazon FSx Document History for Amazon FSx for NetApp ONTAP page.

Change	Description	Date
AmazonFSxConsoleFullAccess – Update to an existing policy	Amazon FSx added a new permission, `secretsmanager:ListSecrets` that allows principals to list secrets in AWS Secrets Manager for selecting domain join service account credentials.	November 5, 2025
AmazonFSxConsoleReadOnlyAccess – Update to an existing policy	Amazon FSx added a new permission, `secretsmanager:ListSecrets` that allows principals to list secrets in AWS Secrets Manager for selecting domain join service account credentials.	November 3, 2025
AmazonFSxServiceRolePolicy – Update to an existing policy	Amazon FSx added a new permission, `ec2:AssignIpv6Addresses` that allows principals to assign IPv6 addresses to customer network interfaces that have an `AmazonFSx.FileSystemId` tag.	July 22, 2025
AmazonFSxServiceRolePolicy – Update to an existing policy	Amazon FSx added a new permission, `ec2:UnassignIpv6Addresses` that	July 22, 2025

Change	Description	Date
	allows principals to unassign IPv6 addresses from customer network interfaces that have an `AmazonFSx.FileSystemId` tag.	
AmazonFSxConsoleFullAccess – Update to an existing policy	Amazon FSx added a new permission, `fsx:CreateAndAttachS3AccessPoint` that allows principals to create an S3 access point and attach it to an FSx volume.	June 25, 2025
AmazonFSxConsoleFullAccess – Update to an existing policy	Amazon FSx added a new permission, `fsx:DescribeS3AccessPointAttachments` that allows principals to list all S3 access points in an AWS account in an AWS Region.	June 25, 2025
AmazonFSxConsoleFullAccess – Update to an existing policy	Amazon FSx added a new permission, `fsx:DetachAndDeleteS3AccessPoint` that allows principals to delete an S3 access point.	June 25, 2025
AmazonFSxFullAccess – Update to an existing policy	Amazon FSx added a new permission, `fsx:CreateAndAttachS3AccessPoint` that allows principals to create an S3 access point and attach it to an FSx volume.	June 25, 2025

Change	Description	Date
AmazonFSxFullAccess – Update to an existing policy	Amazon FSx added a new permission, `fsx:DescribeS3AccessPointAttachments` that allows principals to list all S3 access points in an AWS account in an AWS Region.	June 25, 2025
AmazonFSxFullAccess – Update to an existing policy	Amazon FSx added a new permission, `fsx:DetachAndDeleteS3AccessPoint` that allows principals to delete an S3 access point.	June 25, 2025
AmazonFSxConsoleReadOnlyAccess – Update to an existing policy	Amazon FSx added new permission, `ec2:DescribeNetworkInterfaces` that allows principals to view the elastic network interfaces associated with their file system.	February 25, 2025
AmazonFSxConsoleFullAccess – Update to an existing policy	Amazon FSx added new permission, `ec2:DescribeNetworkInterfaces` that allows principals to view the elastic network interfaces associated with their file system.	February 07, 2025

Change	Description	Date
AmazonFSxServiceRolePolicy – Update to an existing policy	Amazon FSx added new permission, `ec2:GetSecurityGroupsForVpc` that allows principals to provide enhanced security group validation of all security groups that can be used with a VPC.	January 9, 2024
AmazonFSxReadOnlyAccess – Update to an existing policy	Amazon FSx added new permission, `ec2:GetSecurityGroupsForVpc` that allows principals to provide enhanced security group validation of all security groups that can be used with a VPC.	January 9, 2024
AmazonFSxConsoleReadOnlyAccess – Update to an existing policy	Amazon FSx added new permission, `ec2:GetSecurityGroupsForVpc` that allows principals to provide enhanced security group validation of all security groups that can be used with a VPC.	January 9, 2024
AmazonFSxFullAccess – Update to an existing policy	Amazon FSx added new permission, `ec2:GetSecurityGroupsForVpc` that allows principals to provide enhanced security group validation of all security groups that can be used with a VPC.	January 9, 2024

Change	Description	Date
AmazonFSxConsoleFullAccess – Update to an existing policy	Amazon FSx added new permission, `ec2:GetSecurityGroupsForVpc` that allows principals to provide enhanced security group validation of all security groups that can be used with a VPC.	January 9, 2024
AmazonFSxFullAccess – Update to an existing policy	Amazon FSx added new permission to enable users to perform cross-region and cross-account data replication for FSx for OpenZFS file systems.	December 20, 2023
AmazonFSxConsoleFullAccess – Update to an existing policy	Amazon FSx added new permission to enable users to perform cross-region and cross-account data replication for FSx for OpenZFS file systems.	December 20, 2023
AmazonFSxFullAccess – Update to an existing policy	Amazon FSx added new permission to enable users to perform on-demand replication of volumes for FSx for OpenZFS file systems.	November 26, 2023
AmazonFSxConsoleFullAccess – Update to an existing policy	Amazon FSx added new permission to enable users to perform on-demand replication of volumes for FSx for OpenZFS file systems.	November 26, 2023

Change	Description	Date
AmazonFSxFullAccess – Update to an existing policy	Amazon FSx added new permissions to enable users to view, enable, and disable shared VPC support for FSx for ONTAP Multi-AZ file systems.	November 14, 2023
AmazonFSxConsoleFullAccess – Update to an existing policy	Amazon FSx added new permissions to enable users to view, enable, and disable shared VPC support for FSx for ONTAP Multi-AZ file systems.	November 14, 2023
AmazonFSxFullAccess – Update to an existing policy	Amazon FSx added new permissions to allow Amazon FSx to manage network configurations for FSx for OpenZFS Multi-AZ file systems.	August 9, 2023
AWS managed policy: AmazonFSxServiceRolePolicy – Update to an existing policy	Amazon FSx modified the existing `cloudwatch:PutMetricData` permission so that Amazon FSx publishes CloudWatch metrics to the `AWS/FSx` namespace.	July 24, 2023
AmazonFSxFullAccess – Update to an existing policy	Amazon FSx updated the policy to remove the `fsx:*` permission and add specific `fsx` actions.	July 13, 2023

Change	Description	Date
AmazonFSxConsoleFullAccess – Update to an existing policy	Amazon FSx updated the policy to remove the `fsx:*` permission and add specific `fsx` actions.	July 13, 2023
AmazonFSxConsoleReadOnlyAccess – Update to an existing policy	Amazon FSx added new permissions to enable users to view enhanced performance metrics and recommended actions for FSx for Windows File Server file systems in the Amazon FSx console.	September 21, 2022
AmazonFSxConsoleFullAccess – Update to an existing policy	Amazon FSx added new permissions to enable users to view enhanced performance metrics and recommended actions for FSx for Windows File Server file systems in the Amazon FSx console.	September 21, 2022
AmazonFSxReadOnlyAccess – Started tracking policy	This policy grants read-only access to all Amazon FSx resources and any tags associated with them.	February 4, 2022
AmazonFSxDeleteServiceLinkedRoleAccess – Started tracking policy	This policy grants administrative permissions that allow Amazon FSx to delete its Service Linked Role for Amazon S3 access.	January 7, 2022

Change	Description	Date
AmazonFSxServiceRolePolicy – Update to an existing policy	Amazon FSx added new permissions to allow Amazon FSx to manage network configurations for Amazon FSx for NetApp ONTAP file systems.	September 2, 2021
AmazonFSxFullAccess – Update to an existing policy	Amazon FSx added new permissions to allow Amazon FSx to create tags on EC2 route tables for scoped down calls.	September 2, 2021
AmazonFSxConsoleFullAccess – Update to an existing policy	Amazon FSx added new permissions to allow Amazon FSx to create Amazon FSx for NetApp ONTAP Multi-AZ file systems.	September 2, 2021
AmazonFSxConsoleFullAccess – Update to an existing policy	Amazon FSx added new permissions to allow Amazon FSx to create tags on EC2 route tables for scoped down calls.	September 2, 2021
AmazonFSxServiceRolePolicy – Update to an existing policy	Amazon FSx added new permissions to allow Amazon FSx to describe and write to CloudWatch Logs log streams. This is required so that users can view file access audit logs for FSx for Windows File Server file systems using CloudWatch Logs.	June 8, 2021

Change	Description	Date
AmazonFSxServiceRolePolicy – Update to an existing policy	Amazon FSx added new permissions to allow Amazon FSx to describe and write to Amazon Data Firehose delivery streams. This is required so that users can view file access audit logs for an FSx for Windows File Server file system using Amazon Data Firehose.	June 8, 2021
AmazonFSxFullAccess – Update to an existing policy	Amazon FSx added new permissions to allow principal s to describe and create CloudWatch Logs log groups, log streams, and write events to log streams. This is required so that principals can view file access audit logs for FSx for Windows File Server file systems using CloudWatch Logs.	June 8, 2021

Change	Description	Date
AmazonFSxFullAccess – Update to an existing policy	Amazon FSx added new permissions to allow principals to describe and write records to a Amazon Data Firehose. This is required so that users can view file access audit logs for an FSx for Windows File Server file system using Amazon Data Firehose.	June 8, 2021
AmazonFSxConsoleFullAccess – Update to an existing policy	Amazon FSx added new permissions to allow principals to describe the Amazon CloudWatch Logs log groups associated with the account making the request. This is required so that principals can choose an existing CloudWatch Logs log group when configuring file access auditing for an FSx for Windows File Server file system.	June 8, 2021

Change	Description	Date
AmazonFSxConsoleFullAccess – Update to an existing policy	Amazon FSx added new permissions to allow principals to describe the Amazon Data Firehose delivery streams associated with the account making the request. This is required so that principals can choose an existing Firehose delivery stream when configuring file access auditing for an FSx for Windows File Server file system.	June 8, 2021
AmazonFSxConsoleReadOnlyAccess – Update to an existing policy	Amazon FSx added new permissions to allow principals to describe the Amazon CloudWatch Logs log groups associated with the account making the request. This is required so that principals can view the existing file access auditing configuration for an FSx for Windows File Server file system.	June 8, 2021

Change	Description	Date
AmazonFSxConsoleReadOnlyAccess – Update to an existing policy	Amazon FSx added new permissions to allow principals to describe the Amazon Data Firehose delivery streams associated with the account making the request. This is required so that principals can view the existing file access auditing configuration for an FSx for Windows File Server file system.	June 8, 2021
Amazon FSx started tracking changes	Amazon FSx started tracking changes for its AWS managed policies.	June 8, 2021

File System Access Control with Amazon VPC

You access your Amazon FSx for NetApp ONTAP file systems and SVMs using the DNS name or the IP address of one of their endpoints, depending on what type of access it is. The DNS name maps to the private IP address of the file system's or SVM's elastic network interface in your VPC. Only resources within the associated VPC, or resources connected with the associated VPC by Direct Connect or VPN, can access the data in your file system over the NFS, SMB, or iSCSI protocols. For more information, see What is Amazon VPC? in the *Amazon VPC User Guide.*

Warning

You must not modify or delete the elastic network interface(s) associated with your file system. Modifying or deleting the network interface can cause a permanent loss of connection between your VPC and your file system.

Amazon VPC security groups

A security group acts as a virtual firewall for your FSx for ONTAP file systems to control incoming and outgoing traffic. Inbound rules control the incoming traffic to your file system, and outbound rules control the outgoing traffic from your file system. When you create a file system, you specify the VPC that it gets created in, and the default security group for that VPC is applied. You can add rules to each security group that allow traffic to or from its associated file systems and SVMs. You can modify the rules for a security group at any time. New and modified rules are automatically applied to all resources that are associated with the security group. When Amazon FSx decides whether to allow traffic to reach a resource, it evaluates all of the rules from all of the security groups that are associated with the resource.

To use a security group to control access to your Amazon FSx file system, add inbound and outbound rules. Inbound rules control incoming traffic, and outbound rules control outgoing traffic from your file system. Make sure that you have the right network traffic rules in your security group to map your Amazon FSx file system's file share to a folder on your supported compute instance.

For more information on security group rules, see Security Group Rules in the *Amazon EC2 User Guide*.

Creating a VPC security group

To create a security group for Amazon FSx

1. Open the Amazon EC2 console at https://console.aws.amazon.com/ec2.
2. In the navigation pane, choose **Security Groups**.
3. Choose **Create Security Group**.
4. Specify a name and description for the security group.
5. For **VPC**, choose the Amazon VPC associated with your file system to create the security group within that VPC.
6. For outbound rules, allow all traffic on all ports.
7. Add the following rules to the inbound ports of your security group. For the **source** field, you should choose **Custom** and enter the security groups or IP address ranges associated with the instances that need to access your FSx for ONTAP file system, including:

   - Linux, Windows, and/or macOS clients that access data in your file system over NFS, SMB, or iSCSI.

- Any ONTAP file systems/clusters that you will peer to your file system (for example, to use SnapMirror, SnapVault, or FlexCache).
- Any clients that you will use to access the ONTAP REST API, CLI, or ZAPIs (for example, a Harvest/Grafana instance, NetApp Connector, or NetApp Console).

Protocol	Ports	Role
All ICMP	All	Pinging the instance
SSH	22	SSH access to the IP address of the cluster management LIF or a node management LIF
TCP	111	Remote procedure call for NFS
TCP	135	Remote procedure call for CIFS
TCP	139	NetBIOS service session for CIFS
TCP	161-162	Simple network management protocol (SNMP)
TCP	443	ONTAP REST API access to the IP address of the cluster management LIF or an SVM management LIF
TCP	445	Microsoft SMB/CIFS over TCP with NetBIOS framing
TCP	635	NFS mount
TCP	749	Kerberos
TCP	2049	NFS server daemon
TCP	3260	iSCSI access through the iSCSI data LIF
TCP	4045	NFS lock daemon
TCP	4046	Network status monitor for NFS
TCP	10000	Network data management protocol (NDMP) and NetApp SnapMirror intercluster communication

Protocol	Ports	Role
TCP	11104	Management of NetApp SnapMirror intercluster communication
TCP	11105	SnapMirror data transfer using intercluster LIFs
UDP	111	Remote procedure call for NFS
UDP	135	Remote procedure call for CIFS
UDP	137	NetBIOS name resolution for CIFS
UDP	139	NetBIOS service session for CIFS
UDP	161-162	Simple network management protocol (SNMP)
UDP	635	NFS mount
UDP	2049	NFS server daemon
UDP	4045	NFS lock daemon
UDP	4046	Network status monitor for NFS
UDP	4049	NFS quota protocol

8. Add the security group to the file system's elastic network interface.

Disallow access to a file system

To temporarily disallow network access to your file system from all clients, you can remove all the security groups associated with your file system's elastic network interface(s) and replace them with a group that has no inbound/outbound rules.

Compliance Validation for Amazon FSx for NetApp ONTAP

Our new AWS sign-up experience is not designed for regulated workloads. If you're using our new AWS sign-up experience, but you want to use AWS for regulated workloads, you can sign up for AWS (advanced) or activate advanced features for your AWS environment.

To learn whether an AWS service is within the scope of specific compliance programs, see AWS services in Scope by Compliance Program and choose the compliance program that you are interested in. For general information, see AWS Compliance Programs.

You can download third-party audit reports using AWS Artifact. For more information, see Downloading Reports in AWS Artifact.

Your compliance responsibility when using AWS services is determined by the sensitivity of your data, your company's compliance objectives, and applicable laws and regulations. For more information about your compliance responsibility when using AWS services, see AWS Security Documentation.

Amazon FSx for NetApp ONTAP and interface VPC endpoints (AWS PrivateLink)

You can improve the security posture of your VPC by configuring Amazon FSx to use an interface VPC endpoint. Interface VPC endpoints are powered by AWS PrivateLink, a technology that enables you to privately access Amazon FSx APIs without an internet gateway, NAT device, VPN connection, or Direct Connect connection. Instances in your VPC don't need public IP addresses to communicate with Amazon FSx APIs. Traffic between your VPC and Amazon FSx does not leave the AWS network.

Each interface VPC endpoint is represented by one or more elastic network interfaces in your subnets. A network interface provides a private IP address that serves as an entry point for traffic to the Amazon FSx API. Amazon FSx supports VPC endpoints configured with IPv4 and Dualstack (IPv4 and IPv6) IP address types. For more information, see Creating an interface VPC endpoint in the *Amazon VPC User Guide*.

Considerations for Amazon FSx interface VPC endpoints

Before you set up an interface VPC endpoint for Amazon FSx, be sure to review Interface VPC endpoint properties and limitations in the *Amazon VPC User Guide*.

You can call any of the Amazon FSx API operations from your VPC. For example, you can create an FSx for ONTAP file system by calling the CreateFileSystem API from within your VPC. For the full list of Amazon FSx APIs, see Actions in the Amazon FSx API Reference.

VPC peering considerations

You can connect other VPCs to the VPC with interface VPC endpoints using VPC peering. VPC peering is a networking connection between two VPCs. You can establish a VPC peering connection between your own two VPCs, or with a VPC in another AWS account. The VPCs can also be in two different AWS Regions.

Traffic between peered VPCs stays on the AWS network and does not traverse the public internet. Once VPCs are peered, resources like Amazon Elastic Compute Cloud (Amazon EC2) instances in both VPCs can access the Amazon FSx API through interface VPC endpoints created in the one of the VPCs.

Creating an interface VPC endpoint for Amazon FSx API

You can create a VPC endpoint for the Amazon FSx API using either the Amazon VPC console or the AWS Command Line Interface (AWS CLI). For more information, see Creating an interface VPC endpoint in the *Amazon VPC User Guide*.

To create an interface VPC endpoint for Amazon FSx, use one of the following:

- **`com.amazonaws.`*`region`*`.fsx`** – Creates an endpoint for Amazon FSx API operations.
- **`com.amazonaws.`*`region`*`.fsx-fips`** – Creates an endpoint for the Amazon FSx API that complies with Federal Information Processing Standard (FIPS) 140-2.

To use the private DNS option, you must set the `enableDnsHostnames` and `enableDnsSupport` attributes of your VPC. For more information, see Viewing and updating DNS support for your VPC in the *Amazon VPC User Guide*.

Excluding AWS Regions in China, if you enable private DNS for the endpoint, you can make API requests to Amazon FSx with the VPC endpoint using its default DNS name for the AWS Region, for example `fsx.us-east-1.amazonaws.com`. For the China (Beijing) and China (Ningxia) AWS Regions, you can make API requests with the VPC endpoint using `fsx-api.cn-north-1.amazonaws.com.cn` and `fsx-api.cn-northwest-1.amazonaws.com.cn`, respectively.

For more information, see Accessing a service through an interface VPC endpoint in the *Amazon VPC User Guide*.

Creating a VPC endpoint policy for Amazon FSx

To control access to the Amazon FSx API, you can attach an AWS Identity and Access Management (IAM) policy to your VPC endpoint. The policy specifies the following:

- The principal that can perform actions.
- The actions that can be performed.
- The resources on which actions can be performed.

For more information, see Controlling access to services with VPC endpoints in the *Amazon VPC User Guide*.

Resilience in Amazon FSx for NetApp ONTAP

The AWS global infrastructure is built around AWS Regions and Availability Zones. AWS Regions provide multiple physically separated and isolated Availability Zones, which are connected with low-latency, high-throughput, and highly redundant networking. With Availability Zones, you can design and operate applications and databases that automatically fail over between zones without interruption. Availability Zones are more highly available, fault tolerant, and scalable than traditional single or multiple data center infrastructures.

For more information about AWS Regions and Availability Zones, see AWS Global Infrastructure.

In addition to the AWS global infrastructure, Amazon FSx offers several features to help support your data resiliency and backup needs.

Backup and restore

Amazon FSx creates and saves automated backups of the volumes in your Amazon FSx for NetApp ONTAP file system. Amazon FSx creates automated backups of your volumes during the backup window of your Amazon FSx for NetApp ONTAP file system. Amazon FSx saves the automated backups of your volumes according to the backup retention period that you specify. You can also back up your volumes manually, by creating a user-initiated backup. You restore a volume backup at any time by creating a new volume with the backup specified as the source.

For more information, see Protecting your data with volume backups.

Snapshots

Amazon FSx creates snapshot copies of the Amazon FSx for NetApp ONTAP volumes. Snapshot copies offer protection against accidental deletion or modification of files in your volumes by end users. For more information, see Protecting your data with snapshots.

Availability Zones

Amazon FSx for NetApp ONTAP file systems are designed to provide continuous availability to data even in the event that a server failure. Each file system is powered by two file servers in at least one Availability Zone, each with its own storage. Amazon FSx automatically replicates your data to protect it from component failure, continuously monitors for hardware failures, and automatically replaces infrastructure components in the event of a failure. File systems automatically fail over and back as needed (typically within 60 seconds), and clients automatically fail over and back with the file system.

Multi-AZ file systems

Amazon FSx for NetApp ONTAP file systems are highly available and durable across AWS Availability Zones, and are designed to provide continuous availability to data even in the event that an Availability Zone is unavailable.

For more information, see *Availability, durability, and deployment options*.

Single-AZ file systems

Amazon FSx for NetApp ONTAP file systems are highly available and durable within a single AWS Availability Zone, and are designed to provide continuous availability within that Availability Zone in the event of an individual file server or disk failure.

For more information, see *Availability, durability, and deployment options*.

Infrastructure security in Amazon FSx for NetApp ONTAP

As a managed service, Amazon FSx for NetApp ONTAP is protected by AWS global network security. For information about AWS security services and how AWS protects infrastructure, see AWS Cloud Security. To design your AWS environment using the best practices for infrastructure security, see Infrastructure Protection in *Security Pillar AWS Well-Architected Framework*.

You use AWS published API calls to access Amazon FSx through the network. Clients must support the following:

- Transport Layer Security (TLS). We require TLS 1.2 and recommend TLS 1.3.
- Cipher suites with perfect forward secrecy (PFS) such as DHE (Ephemeral Diffie-Hellman) or ECDHE (Elliptic Curve Ephemeral Diffie-Hellman). Most modern systems such as Java 7 and later support these modes.

Use NetApp ONTAP Vscan with FSx for ONTAP

You can use NetApp ONTAP's Vscan feature to run supported third-party antivirus software. For more information, see the following resources for each of the supported solutions.

- Deep Instinct – Vscan partner solutions and Deep Instinct documentation[1]
- SentinelOne – Vscan partner solutions and SentinelOne Singularity Cloud Data Security
- Symantec – Vscan partner solutions and Symantec Protection Engine
- Trellix (formerly McAfee) – Vscan partner solutions and Trellix Product Docs
- Trend Micro – Vscan partner solutions
- OPSWAT – Vscan partner solutions and OPSWAT Product Docs

Note

[1] You must log in to Deep Instinct's portal to view their documentation.

ONTAP roles and users

NetApp ONTAP includes a robust and extensible role-based access control (RBAC) capability. ONTAP roles define user capabilities and privileges when using the ONTAP CLI and REST API. Each role defines a different level of administrative capabilities and privileges. You assign roles to users for the purpose of controlling their access to FSx for ONTAP resources when using the ONTAP REST API and CLI. There are ONTAP roles available separately for FSx for ONTAP file system users and storage virtual machine (SVM) users.

When you create an FSx for ONTAP file system, a default ONTAP user is created at the file system level and at the SVM level. You can create additional file system and SVM users, and you can create

additional SVM roles to meet the needs of your organization. This chapters explains ONTAP users and roles, and provides detailed procedures for creating additional users and SVM roles.

File system administrator roles and users

The default ONTAP file system user is `fsxadmin`, which has the `fsxadmin` role assigned to it. There are two predefined roles that you can assign to file system users, listed as follows:

- **`fsxadmin`**—Administrators with this role have unrestricted rights in the ONTAP system. They can configure all file system and SVM-level resources available on FSx for ONTAP file systems.
- **`fsxadmin-readonly`**—Administrators with this role can view everything at the file system level but can't make any changes.

  This role is well-suited for use with monitoring applications such as NetApp Harvest because it has read-only access to all available resources and their properties, but cannot make any changes to them.

You can create additional file system users and assign them either the `fsxadmin` or `fsxadmin-readonly` role. You can't create new roles or modify the existing roles. For more information, see Creating new ONTAP users for file system and SVM administration.

The following table describes the level of access that file system administrator roles have for ONTAP CLI and REST API commands and command directories.

Role name	Level of access	To the following commands or command directories
`fsxadmin`	all	All command directories available in FSx for ONTAP
`fsxadmin-readonly`	all	`security login password` For managing own user account local password and key information only
	none	`security`

Role name	Level of access	To the following commands or command directories
	readonly	All other command directori es available in FSx for ONTAP

SVM administrator roles and users

Each SVM has a separate authentication domain and can be managed independently by its own administrators. For each SVM on your file system, the default user is *vsadmin*, which has the `vsadmin` role assigned by default. In addition to the `vsadmin` role, there are other predefined SVM roles that provide scoped down permissions that you can assign to SVM users. You can also create custom roles that provide the level of access control that meet your organization's needs.

The predefined roles for SVM administrators and their capabilities are as follows:

Role name	Capabilities
`vsadmin`	• Manage your user account, local password, and key information • Manage volumes, except for volume moves • Manage quotas, qtrees, Snapshot copies, and files • Manage LUNs • Perform SnapLock operations, except for privileged delete • Configure protocols: NFS, SMB, and iSCSI • Configure services: DNS, LDAP, and NIS • Monitor jobs • Monitor network connections and the network interface • Monitor the health of the SVM
`vsadmin-volume`	• Manage your user account, local password, and key information

Role name	Capabilities
	• Manage volumes, including volume moves • Manage quotas, qtrees, Snapshot copies, and files • Manage LUNs • Configure protocols: NFS, SMB, and iSCSI • Configure services: DNS, LDAP, and NIS • Monitor the network interface • Monitor the health of the SVM
`vsadmin-protocol`	• Manage your user account, local password, and key information • Manage LUNs • Configure protocols: NFS, SMB, and iSCSI • Configure services: DNS, LDAP, and NIS • Monitor network interface • Monitor the health of the SVM
`vsadmin-backup`	• Manage your user account, local password, and key information • Manage NDMP operations • Make a restored volume read/write • Manage SnapMirror relationships and Snapshot copies • View volumes and network information

Role name	Capabilities
`vsadmin-snaplock`	• Manage your user account, local password, and key information • Manage volumes, except for volume moves • Manage quotas, qtrees, Snapshot copies, and files • Perform SnapLock operations, including privileged delete • Configure protocols: NFS and SMB • Configure services: DNS, LDAP, and NIS • Monitor jobs • Monitor network connections and the network interface
`vsadmin-readonly`	• Manage your user account, local password, and key information • Monitor the health of the SVM • Monitor the network interface • View volumes and LUNs • View services and protocols

For more information on how to create a new SVM role, see Creating SVM roles.

Using Active Directory to authenticate ONTAP users

You can authenticate Windows Active Directory domain users' access to an FSx for ONTAP file system and SVM. You must do the following tasks before Active Directory accounts can access your file system:

- You need configure Active Directory domain controller access to the SVM.

  The SVM you use to configure as a gateway or tunnel for Active Directory domain controller access must either have CIFS enabled, be joined to an Active Directory, or both. If you are not enabling CIFS and only joining the tunnel SVM to an Active Directory, ensure that the SVM is

joined to your Active Directory. For more information, see How joining SVMs to Microsoft Active Directory works.

- You need to enable an Active Directory domain user account to access the file system.

  You can use either password authentication or SSH public key authentication for Windows domain users accessing the ONTAP CLI or REST API.

For procedures describing how to use for configuring Active Directory authentication for file system and SVM administrators, see Configuring Active Directory authentication for ONTAP users.

Creating new ONTAP users for file system and SVM administration

Each ONTAP user is associated with an SVM or the file system. File system users with the `fsxadmin` role can create new SVM roles and users by using the `security login create` ONTAP CLI command.

The `security login create` command creates a login method for the management utility. A login method consists of a user name, an application (access method), and an authentication method. A user name can be associated with multiple applications. It can optionally include an access-control role name. If an Active Directory, LDAP, or NIS group name is used, then the login method gives access to users belonging to the specified group. If the user is a member of multiple groups provisioned in the security login table, then the user will get access to a combined list of the commands authorized for the individual groups.

For information describing how to create a new ONTAP user, see Creating ONTAP users.

Topics

- Creating ONTAP users
- Creating SVM roles
- Configuring Active Directory authentication for ONTAP users
- Configuring public key authentication
- Updating password requirements for file system and SVM roles
- Updating the fsxadmin account password fails

Creating ONTAP users

To create a new SVM or file system user (ONTAP CLI)

Only file system users with the `fsxadmin` role can create new SVM and file system users.

1. To access the ONTAP CLI, establish an SSH session on the management port of the Amazon FSx for NetApp ONTAP file system or SVM by running the following command. Replace *`management_endpoint_ip`* with the IP address of the file system's management port.

   ```
   [~]$ ssh fsxadmin@management_endpoint_ip
   ```

   For more information, see Managing file systems with the ONTAP CLI.

2. Use the `security login create` ONTAP CLI command to create a new user account on your FSx for ONTAP file system or SVM.

   Insert your data for the placeholders in the example to define the following required properties:

   - `-vserver` – Specifies the name of the SVM where you want to create the new SVM role or user. If you are creating a file system role or user, don't specify an SVM.
   - `-user-or-group-name` – Specifies the username or Active Directory group name of the login method. The Active Directory group name can be specified only with the `domain` authentication method and the `ontapi` and `ssh` applications.
   - `-application` – Specifies the application of the login method. Possible values include http, ontapi, and ssh.
   - `-authentication-method` – Specifies the authentication method for login. Possible values include the following:
     - domain – Use for Active Directory authentication
     - password – Use for password authentication
     - publickey – User for public-key authentication
   - `-role` – Specifies the access-control role name for the login method. At the file system-level, the only role that can be specified is `fsxadmin`.

   (Optional) You can also use one or more of the following parameters with the command:

- `[-comment]` – Use to include a notation or comment for the user account. For example, **`Guest account`**. The maximum length is 128 characters.
- `[-second-authentication-method {none|publickey|password|nsswitch}]` – Specifies the second factor authentication method. You can specify the following methods:
  - password – Use for password authentication
  - publickey – Use for Public-key authentication
  - nsswitch – Use for NIS or LDAP authentication
  - none – The default value if you don't specify one

```
Fsx0123456::> security login create -vserver vserver_name -user-or-group-
name user_or_group_name -application login_application -authentication-
method auth_method -role role_or_account_name
```

The following command creates a new file system user `new_fsxadmin` with the `fsxadmin-readonly` role assigned, using SSH with a password for logging in. When prompted, provide a password for the user.

```
Fsx0123456::> security login create -user-or-group-name new_fsxadmin -application
 ssh -authentication-method password -role fsxadmin-readonly

Please enter a password for user 'new_fsxadmin':
Please enter it again:

Fsx0123456::>
```

3. The following command creates a new SVM user `new_vsadmin` on the `fsx` SVM with the `vsadmin_readonly` role, configured to use SSH with a password to login. When prompted, provide a password for the user.

```
Fsx0123456::> security login create -vserver fsx  -user-or-group-name new_vsadmin -
application ssh -authentication-method password -role vsadmin-readonly

Please enter a password for user 'new_vsadmin':
Please enter it again:

Fsx0123456::>
```

4. The following command creates a new read-only file system user `harvest2-user` that is to be used by the NetApp Harvest application to collect performance and capacity metrics. For more information, see Monitoring FSx for ONTAP file systems using Harvest and Grafana.

```
Fsx0123456::> security login create -user-or-group-name harvest2-user -application
 ssh -role fsxadmin-readonly -authentication-method password
```

To view information for all file system and SVM users

- Use the following command to view all login information for your file system and SVMs.

```
Fsx0123456::> security login show

Vserver: Fsx0123456
                                                                 Second
User/Group                Authentication                 Acct    Authentication
Name           Application Method        Role Name        Locked  Method
-------------- ----------- ------------- ---------------- ------ --------------
autosupport    console     password      autosupport      no     none
fsxadmin       http        password      fsxadmin         no     none
fsxadmin       ontapi      password      fsxadmin         no     none
fsxadmin       ssh         password      fsxadmin         no     none
fsxadmin       ssh         publickey     fsxadmin         -      none
new_fsxadmin   ssh         password      fsxadmin-readonly
                                                        no     none

Vserver: fsx
                                                                 Second
User/Group                Authentication                 Acct    Authentication
Name           Application Method        Role Name        Locked  Method
-------------- ----------- ------------- ---------------- ------ --------------
new_vsadmin    ssh         password      vsadmin-readonly no     none
vsadmin        http        password      vsadmin          yes    none
vsadmin        ontapi      password      vsadmin          yes    none
vsadmin        ssh         password      vsadmin          yes    none
10 entries were displayed.

Fsx0123456::>
```

Creating SVM roles

Each SVM that you create has a default SVM administrator that's assigned the predefined `vsadmin` role. In addition to the set of predefined SVM roles, you can create new SVM roles. If you need to create new roles for your SVM, use the `security login role create` ONTAP CLI command. This command is available for file system administrators with the `fsxadmin` role.

To create a new SVM role (ONTAP CLI)

1. You can create a new SVM role using the `security login role create` ONTAP CLI command:

   ```
   Fsx0123456::> security login role create -vserver vs1.example.com -role vol_role -
   cmddirname volume
   ```

2. Specify the following required parameters in the command:

   - `-vserver` the name of the SVM
   - `-role` – The name of the role.
   - `-cmddirname` – The command or command directory to which the role gives access. Enclose command subdirectory names in double quotation marks. For example, `"volume snapshot"`. Enter `DEFAULT` to specify all command directories.

3. (Optional) You can also add any of the following parameters to the command:

   - `-vserver` – The name of the SVM that's associated with the role.
   - `-access` – The access level for the role. For command directories, this includes:
     - none – Denies access to commands in the command directory. This is the default value for custom roles.
     - `readonly` – Grants access to the show commands in the command directory and its subdirectories.
     - `all` – Grants access to all of the commands in the command directory and its subdirectories. To grant or deny access to intrinsic commands, you must specify the command directory.

     For non-intrinsic commands (commands that don't end in `create`, `modify`, `delete`, or `show`):

- none – Denies access to commands in the command directory. This is the default value for custom roles.
- `readonly` – Not applicable. Don't use.
- `all` – Grants access to the command.

- `-query` – The query object that's used to filter the access level, which is specified in the form of a valid option for the command, or for a command in the command directory. Enclose the query object in double quotation marks.

4. Run the `security login role create` command.

   The following command creates an access-control role named "admin" for the vs1.example.com Vserver. The role has all access to the "volume" command but only within the "aggr0" aggregate.

```
Fsx0123456::>security login role create -role admin -cmddirname volume -query "-
aggr aggr0" -access all -vserver vs1.example.com
```

Configuring Active Directory authentication for ONTAP users

Use the ONTAP CLI to configure the use of Active Directory authentication for ONTAP file system and SVM users.

You must be a file system administrator with the `fsxadmin` role to use the commands in this procedure.

To set up Active Directory authentication for ONTAP users (ONTAP CLI)

The commands in this procedure are available to file system users with the `fsxadmin` role.

1. To access the ONTAP CLI, establish an SSH session on the management port of the Amazon FSx for NetApp ONTAP file system or SVM by running the following command. Replace *`management_endpoint_ip`* with the IP address of the file system's management port.

```
[~]$ ssh fsxadmin@management_endpoint_ip
```

   For more information, see Managing file systems with the ONTAP CLI.

2. Use the `security login domain-tunnel create` command as shown to establish a domain tunnel for authenticating Windows Active Directory users. Replace *svm_name* with the name of the SVM you are using for the domain tunnel.

```
FsxId0123456::> security login domain-tunnel create -vserver svm_name
```

3. Use the `security login create` command to create Active Directory domain user accounts that will access the file system.

   Specify the following required parameters in the command:

   - `-vserver` – The name of the SVM configured with CIFS and is joined to your Active Directory. It will be used as the tunnel for authenticating Active Directory domain users' to the file system. which the new role or user will be created.
   - `-user-or-group-name` – The username or Active Directory group name of the login method. The Active Directory group name can be specified only with the `domain` authentication method and `ontapi` and `ssh` application.
   - `-application` – The application of the login method. Possible values include http, ontapi, and ssh.
   - `-authentication-method` – The authentication method used for login. Possible values include the following:
     - domain – for Active Directory authentication
     - password – for password authentication
     - publickey – for public-key authentication
   - `-role` – The access-control role name for the login method. At the file system-level, the only role that can be specified is `-role fsxadmin`.

   The following example creates an Active Directory domain user account `CORP\Admin` for the `filesystem1` file system.

```
FSxId012345::> security login create -vserver filesystem1 -username CORP\Admin -
application ssh -authmethod domain -role fsxadmin
```

   The following example creates the `CORP\Admin` user account with public key authentication.

```
FsxId0123456ab::> security login create -user-or-group-name "CORP\Admin" -
application ssh -authentication-method publickey -role fsxadmin
Warning: To use public-key authentication, you must create a public key for user
 "CORP\Admin".
```

Create a public key for the CORP\Admin user using the following command:

```
FsxId0123456ab::> security login publickey create -username "CORP
\Admin" -publickey "ecdsa-sha2-nistp256 SECRET_STRING_HERE_IS_REDACTED=
 cwaltham@b0be837a91bf.ant.amazon.com"
```

To log in to file system using SSH with Active Directory credentials

- The following example demonstrates how to SSH into your file system with your Active Directory credentials if you choose ssh for the -application type. The username is in the format "domain-name\user-name", which is the domain name and the username that you provided when creating the account, separated by a backslash and enclosed in quotations.

```
Fsx0123456::> ssh "CORP\user"@management.fs-abcdef01234567892.fsx.us-east-2.aws.com
```

When prompted to enter a password, use the Active Directory user's password.

Configuring public key authentication

To enable SSH public key authentication, you must first generate an SSH key and associate it with an administrator account by using the security login publickey create command. This allows the account to access the SVM. The security login publickey create command accepts the following parameters.

Parameter	Description
-vserver (Optional)	The name of the SVM that the account accesses. If you are configuring SSH public key authentication for file system users, don't include -versver.

Parameter	Description
`-username`	The username of the account. The default value, `admin`, is the default name of the cluster administrator.
`-index`	The index number of the public key. The default value is 0 if the key is the first key that's created for the account. Otherwise, the default value is one more than the highest existing index number for the account.
`-publickey`	The OpenSSH public key. Enclose the key in double quotation marks.
`-role`	The access control role that's assigned to the account.
`-comment` (Optional)	Descriptive text for the public key. Enclose the text in double quotation marks.

The following example associates a public key with the SVM administrator account `svmadmin` for the SVM `svm01`. The public key is assigned index number 5.

```
Fsx0123456::> security login publickey create -vserver svm01 -username svmadmin
 -index 5 -publickey "ssh-rsa AAAAB3NzaC1yc2EAAAABIwAAAIEAspH64CYbUsDQCdW22JnK6J/
vU9upnKzd2zAk9C1f7YaWRUAFNs2Qe5lUmQ3ldi8AD0Vfbr5T6HZPCixNAIzaFciDy7hgnmdj9eNGedGr/
JNrftQbLD1hZybX
+72DpQB0tYWBhe6eDJ1oPLobZBGfMlPXh8VjeU44i7W4+s0hG0E=tsmith@publickey.example.com"
```

Important

You must be an SVM or file system administrator to perform this task.

Updating password requirements for file system and SVM roles

You can update the password requirements for a file system or SVM role using the `security login role config modify` ONTAP CLI command. This command is only available to file system administrator accounts with the `fsxadmin` role. When modifying password requirements, the system will warn if there are any existing users with that role that will be impacted by the change.

The following example modifies the minimum length password requirement to 12 characters for users with the `vsadmin-readonly` role on the `fsx` SVM. In this example, there are existing users with this role.

```
FsxId0123456::> security login role config modify -role vsadmin-readonly -vserver fsx -
passwd-minlength 12
```

The system displays the following warning because of existing users:

```
Warning: User accounts with this role exist. Modifications to the username/password
 restrictions on this role could result in non-compliant user
         accounts.
Do you want to continue? {y|n}:

FsxId0123456::>
```

Updating the `fsxadmin` account password fails

When you update the password for the `fsxadmin` user, you may receive an error if it doesn't meet the password requirements set on the file system. You can view the password requirements by using the `security login role config show` ONTAP CLI or REST API command.

To view the password requirements for a file system or SVM role

1. To access the ONTAP CLI, establish an SSH session on the management port of the Amazon FSx for NetApp ONTAP file system or SVM by running the following command. Replace *`management_endpoint_ip`* with the IP address of the file system's management port.

   ```
   [~]$ ssh fsxadmin@management_endpoint_ip
   ```

   For more information, see Managing file systems with the ONTAP CLI.

2. The `security login role config show` command returns the password requirements for a file system or SVM role.

```
FsxId0123456::> security login role config show -role fsxadmin -
fields password_requirement_fields
```

For the `-fields` parameter, specify any or all of the following:

- `passwd-minlength` – The minimum length of the password.
- `passwd-min-special-chars` – The minimum number of special characters in the password.
- `passwd-min-lowercase-chars` – The minimum number of lowercase characters in the password.
- `passwd-min-uppercase-chars` – The minimum number of uppercase characters in the password.
- `passwd-min-digits` – The minimum number of digits in the password.
- `passwd-alphanum` – Information about the inclusion or exclusion of alphanumeric characters.
- `passwd-expiry-time` – The password expiration time.
- `passwd-expiry-warn-time` – The password expiration warning time.

3. Run the following command to see all password requirements:

```
FsxId0123456::> security login role config show -role fsxadmin -fields passwd-
minlength, passwd-min-special-chars, passwd-min-lowercase-chars, passwd-min-
digits, passwd-alphanum, passwd-expiry-time, passwd-expiry-warn-time, passwd-min-
uppercase-chars

vserver                role     passwd-minlength passwd-alphanum passwd-min-
special-chars passwd-expiry-time passwd-min-lowercase-chars passwd-min-uppercase-
chars passwd-min-digits passwd-expiry-warn-time
---------------------- -------- ---------------- ---------------
 ----------------------- ----------------- -------------------------
 ------------------------- ---------------- ----------------------
FsxId0123456           fsxadmin 3                enabled         0
       unlimited          0                        0                        0
               unlimited
```

Quotas

Following, you can find out about quotas when working with Amazon FSx for NetApp ONTAP.

Topics

- Quotas that you can increase
- Resource quotas for each file system

Quotas that you can increase

Following are the quotas for Amazon FSx for NetApp ONTAP for each AWS account, per AWS Region, that you can increase.

Resource	Default	Description
ONTAP file systems	100	The maximum number of Amazon FSx for NetApp ONTAP file systems that you can create in this account.
ONTAP SSD storage capacity	524,288	The maximum amount of SSD storage capacity (in GiB) for all Amazon FSx for NetApp ONTAP file systems that you can have in this account.
ONTAP throughput capacity	10,240	The maximum amount of throughput capacity (in MBps) for all Amazon FSx for NetApp ONTAP file systems that you can have in this account.
ONTAP SSD IOPS	1,000,000	The maximum amount of SSD IOPS for all Amazon FSx for NetApp ONTAP file systems

Resource	Default	Description
		that you can have in this account.
ONTAP backups	10,000	The maximum number of user-initiated volume backups for all Amazon FSx for NetApp ONTAP file systems that you can have in an AWS account.
Amazon S3 access points	10,000	The maximum number of Amazon S3 access points for all supported data source types (e.g., FSx for NetApp ONTAP) that you can create per region in an AWS account. This is also maximum number of S3 access points that you can have attached to a single FSx for NetApp ONTAP file system or volume. This quota is an Amazon S3 service quota and adjustable using Service Quotas.

To request a quota increase

1. Open the AWS Support page, sign in if necessary, and then choose **Create case**.
2. For **Create case**, choose **Account and billing support**.
3. In the **Case details** panel make the following entries:
   - For **Type** choose **Account**.
   - For **Category** choose **Other Account Issues**.
   - For **Subject** enter **`Amazon FSx for NetApp ONTAP service limit increase request`**.

- Provide a detailed **Description** of your request, including:
  - The FSx quota that you want increased, and the value you want it increased to, if known.
  - The reason why you are seeking the quota increase.
  - The file system ID and region for each file system you are requesting an increase for.

4. Provide your preferred **Contact options** and choose **Submit**.

Resource quotas for each file system

The following table lists the quotas on Amazon FSx for NetApp ONTAP resources for each file system in an AWS Region.

Resource	Limit per file system
Minimum SSD storage capacity	1,024 GiB per high-availability (HA) pair
Minimum SSD storage capacity for initiating a decrease operation	1,126 GiB per HA pair
Minimum SSD decrease percentage	9% smaller than current capacity
Maximum SSD storage capacity	• Second-generation Single-AZ file systems: 512 TiB per HA pair, up to 1 PiB • Second-generation Multi-AZ file systems: 512 TiB • First-generation file systems: 192 TiB
Recommended maximum SSD utilization	80% for optimal performance and tiering functionality
Maximum SSD utilization for decrease operations	80% before and after the decrease operation
Maximum SSD IOPS	Second-generation file systems:

Resource	Limit per file system
	• 200,000 per HA pair (up to 12 pairs) for Single-AZ • 200,000 total for Multi-AZ First-generation file systems: • 160,000 in US East (Ohio) Region, US East (N. Virginia) Region, US West (Oregon) Region, and Europe (Ireland) • 80,000 in all other AWS Regions where FSx for ONTAP is available
Minimum throughput capacity	• Second-generation file systems (1 HA pair): 384 MBps • Second-generation file systems (2 or more HA pairs): 1,536 MBps per HA pair • First-generation file systems: 128 MBps

Resource	Limit per file system
Maximum throughput capacity	Second-generation file systems: • 73,728 MBps[1] for Single-AZ • 6,144 MBps for Multi-AZ First-generation file systems: • 4,096 MBps[2] in US East (Ohio) Region, US East (N. Virginia) Region, US West (Oregon) Region, and Europe (Ireland) • 2,048 MBps in all other AWS Regions where FSx for ONTAP is available
Maximum number of volumes	• Second-generation file systems (1 HA pair): 500 • Second-generation file systems (2 or more HA pairs): 1,000 • First-generation file systems: 500 When using S3 access points with your file system: • Second-generation file systems (1 HA pair): 491 • Second-generation file systems (2 or more HA pairs): 975 for 2 HA pairs (903 for 12 HA pairs) • First-generation file systems: 491
Maximum number of snapshots	1,023 per volume[3]
Maximum number of backups	4,091 per volume[4]

Resource	Limit per file system
Maximum number of SVMs	Second-generation file systems with one HA pair and IPv4-only network type: • 6 (384 MBps of throughput capacity) • 6 (768 MBps of throughput capacity) • 14 (1,536 MBps of throughput capacity) • 14 (3,072 MBps of throughput capacity) • 24 (6,144 MBps of throughput capacity) Second-generation file systems with one HA pair and dual-stack network type: • 6 (384 MBps of throughput capacity) • 6 (768 MBps of throughput capacity) • 11 (1,536 MBps of throughput capacity) • 11 (3,072 MBps of throughput capacity) • 11 (6,144 MBps of throughput capacity) Second-generation file systems with 2–12 HA pairs and either IPv4-only or dual-stack network type:

Resource	Limit per file system
	• 11 First-generation file systems with IPv4-only network type: • 6 (128 MBps throughput capacity) • 6 (256 MBps throughput capacity) • 14 (512 MBps throughput capacity) • 14 (1,024 MBps throughput capacity) • 24 (2,048 MBps throughput capacity) • 24 (4,096 MBps throughput capacity) First-generation file systems with dual-stack network type: • 6 (128 MBps throughput capacity) • 6 (256 MBps throughput capacity) • 11 (512 MBps throughput capacity) • 11 (1,024 MBps throughput capacity) • 11 (2,048 MBps throughput capacity) • 11 (4,096 MBps throughput capacity)
Maximum number of tags	50
Maximum retention period for automated backups	90 days

Resource	Limit per file system
Maximum retention period for user-initiated backups	No retention limit
Maximum number of routes supported per file system	50[5]
Maximum number of client connections per file server[6]	100,000

Note

[1] On a second-generation Single-AZ file system with 12 HA pairs (6,144 MBps per HA pair). For more information, see Managing high-availability (HA) pairs.

[2] To provision 4 GBps of throughput capacity, your FSx for ONTAP first-generation file system requires a configuration of the maximum SSD IOPS (160,000) and a minimum of 5,120 GiB of SSD storage capacity in a supported AWS Region. For more information about which AWS Regions support 4,096 MBps of throughput capacity, see Impact of throughput capacity on performance.

[3] You can store up to 1,023 snapshots per volume at any point in time. Once you reach this limit, you must delete an existing snapshot before a new snapshot of your volume can be created.

[4] You can store up to 4,091 backups per volume at any point in time. Once you reach this limit, you must delete an existing backup before a new backup of your volume can be created.

[5] You can configure up to 50 routes per file system at any point in time. Once you reach this limit, you must delete an existing route before a new route can be configured. The number of routes your file system has is determined by the number of SVMs it has and the number of route tables associated with it. You can determine the existing number of routes to a file system using the following equation: (1 + number of SVMs in the file system) * (route tables associated with the file system).

[6] A client connection is defined as a single TCP connection to a given file server. There is one active file server per HA pair in a file system. A client can have multiple TCP connections to a file server. For example, if a client is using multipathing.

Troubleshooting Amazon FSx for NetApp ONTAP

Use the following sections to help troubleshoot FSx for ONTAP file systems.

Topics

- Your file system is in a MISCONFIGURED state
- You can't access your file system
- Your storage virtual machine (SVM) is in a MISCONFIGURED state
- Troubleshooting SSD decrease operation issues
- You can't join a storage virtual machine (SVM) to Active Directory
- You can't delete a storage virtual machine or volume
- Your volume is in a MISCONFIGURED state
- Your volume has insufficient storage capacity
- Your backups fail due to insufficient volume capacity
- Recovering deleted FSx for ONTAP volumes
- Troubleshooting network issues
- Troubleshooting I/O errors and NFS lock reclaim failures

Your file system is in a `MISCONFIGURED` state

There are a number of potential causes for a file system to be in a `MISCONFIGURED` state, each with their own resolution, as follows.

Topics

- The VPC owner account has disabled Multi-AZ VPC sharing
- You can't create a new SVM on a Multi-AZ file system
- Your file system's SSD storage tier is more than 90% full

The VPC owner account has disabled Multi-AZ VPC sharing

Multi-AZ file systems created by a participant AWS account in a shared VPC subnet will go into a `MISCONFIGURED` state for one of the following reasons:

- The owner account that shared the VPC subnet has disabled Multi-AZ VPC sharing support for FSx for ONTAP file systems.
- The owner account has stopped sharing the VPC subnet.

If the owner account has stopped sharing the VPC subnet, you will see the following message in the console for that file system:

```
The vpc ID vpc-012345abcde does not exist
```

To resolve the issue, you must contact the owner account that shared the VPC subnet with you. For more information see Creating FSx for ONTAP file systems in shared subnets for more information.

You can't create a new SVM on a Multi-AZ file system

For Multi-AZ file systems created by a participant AWS account in a shared VPC, you will be unable to create a new SVM for one of the following reasons:

- The owner account that shared the VPC subnet has disabled Multi-AZ VPC sharing support for FSx for ONTAP file systems.
- The owner account has stopped sharing the VPC subnet.

To resolve the issue, you must contact the owner account that shared the VPC subnet with you. For more information see Creating FSx for ONTAP file systems in shared subnets for more information.

Your file system’s SSD storage tier is more than 90% full

Your Single-AZ or Multi-AZ file system’s SSD storage tier is currently more than 90% full. We recommend that you do not exceed 80% utilization of your SSD storage tier on an ongoing basis. If you do not free up space in the SSD storage tier before your file system’s next maintenance window, FSx for ONTAP will temporarily throttle down your file system’s throughput for the duration of the patching operation. This is done to ensure that the background maintenance processes can complete within a reasonable time period. To avoid this, please reduce the utilization of your SSD storage tier to below 90%. You can reduce SSD utilization several ways, including:

- Increasing your file system's SSD storage capacity.
- By deleting unneeded data.
- By deleting unneeded volume snapshots.

For more information, see Managing storage capacity.

You can't access your file system

This section describes issues and resolutions related to being unable to access your file system.

Topics

- Your Multi-AZ file system has missing route table tags
- Your file system has more than 50 routes
- Your file system is missing routes to one or more file servers
- The file system's elastic network interface was modified or deleted
- The Elastic IP address attached to the file system's elastic network interface was deleted
- The file system's VPC security group lacks the required inbound rules
- The compute instance's VPC security group lacks the required outbound rules
- The compute instance's subnet doesn't use any of the route tables associated with your file system
- Amazon FSx can't update route table for Multi-AZ file systems created using CloudFormation
- Can't access a file system over iSCSI from a client in another VPC
- The owning account has stopped sharing the VPC subnet
- Can't access a file system over NFS, SMB, the ONTAP CLI, or the ONTAP REST API from a client in another VPC or on-premises

Your Multi-AZ file system has missing route table tags

Amazon FSx manages VPC route tables for Multi-AZ file systems using tag-based authentication. One or more of the route tables associated with your file system are currently missing these route table tags. These route tables are tagged with `Key: AmazonFSx; Value: ManagedByAmazonFSx`. If you do not manually add these tags before the next maintenance window, any clients in subnets associated with the route tables that are missing the tags will temporarily lose access to the file system for duration of the patching operation. To avoid this, please manually add the missing route table tags.

For more information, see Updating file systems.

Your file system has more than 50 routes

Your file system currently has more than 50 routes associated with it. If you do not remove some of these routes before your file system's next scheduled maintenance window, the failover process may take longer than normal. To avoid this, please reduce the number of routes to less than 50. The following are steps you can take to reduce the number of routes associated with your file system:

- Deleting any excess routes
- Reducing the number of SVMs associated with the file system
- Reducing the number of route tables associated with the file system

For more information, see Updating file systems and Deleting storage virtual machines (SVM).

Your file system is missing routes to one or more file servers

Your file system is currently missing routes to one or more file servers, and the existing route tables do not have sufficient space to add new route table entries. If you do not add the missing routes before your file system's next scheduled maintenance window, any connected clients will be disconnected for the duration of the patching operation. To avoid this, please add the missing routes.

For more information, see Updating file systems and Quotas.

The file system's elastic network interface was modified or deleted

You must not modify or delete any of the file system's elastic network interfaces. Modifying or deleting a network interface can cause a permanent loss of connection between your virtual private cloud (VPC) and your file system. Create a new file system, and don't modify or delete the Amazon FSx network interface. For more information, see File System Access Control with Amazon VPC.

The Elastic IP address attached to the file system's elastic network interface was deleted

Amazon FSx doesn't support accessing file systems from the public Internet. Amazon FSx automatically detaches any Elastic IP address which is a public IP address reachable from the

Internet that gets attached to a file system's elastic network interface. For more information, see Supported clients.

The file system's VPC security group lacks the required inbound rules

Review the inbound rules specified in Amazon VPC security groups, and make sure that the security group associated with your file system has the corresponding inbound rules.

The compute instance's VPC security group lacks the required outbound rules

Review the outbound rules specified in Amazon VPC security groups, and make sure that the security group associated with your compute instance has the corresponding outbound rules.

The compute instance's subnet doesn't use any of the route tables associated with your file system

FSx for ONTAP creates endpoints for accessing your file system in a VPC route table. We recommend that you configure your file system to use all of the VPC route tables that are associated with the subnets in which your clients are located. By default, Amazon FSx uses your VPC's main route table. You can optionally specify one or more route tables for Amazon FSx to use when you create your file system.

If you can ping your file system's Intercluster endpoint but cannot ping your file system's Management endpoint (see File system resources for more information), your client is likely not in a subnet that's associated with one of your file system's route tables. To access your file system, associate one of your file system's route tables with your client's subnet. For information about updating your file system's Amazon VPC route tables, see Updating file systems.

Amazon FSx can't update route table for Multi-AZ file systems created using CloudFormation

Amazon FSx manages VPC route tables for Multi-AZ file systems using tag-based authentication. These route tables are tagged with `Key: AmazonFSx; Value: ManagedByAmazonFSx`. When creating or updating FSx for ONTAP Multi-AZ file systems using CloudFormation we recommend that you add the `Key: AmazonFSx; Value: ManagedByAmazonFSx` tag manually.

If you're unable to reach your Multi-AZ file system, check to see if the VPC route tables associated with the file system are tagged with `Key: AmazonFSx; Value: ManagedByAmazonFSx`. If

they are not, then Amazon FSx cannot update those route tables to route the floating IP addresses of the management and data ports to the active file server when a failover event occurs. For information about updating your file system's Amazon VPC route tables, see Updating file systems.

Can't access a file system over iSCSI from a client in another VPC

To access a file system over the Internet Small Computer Systems Interface (iSCSI) protocol from a client in another VPC, you can configure Amazon VPC peering or AWS Transit Gateway between the VPC associated with your file system and the VPC in which your client resides. For more information, see Create and accept VPC peering connections in the *Amazon Virtual Private Cloud* guide.

The owning account has stopped sharing the VPC subnet

If you created your file system in a VPC subnet that has been shared with you, the owning account may have stopped sharing the VPC subnet.

If the owner account has stopped sharing the VPC subnet, you will see the following message in the console for that file system:

```
The vpc ID vpc-012345abcde does not exist
```

You will need to contact the owning account so that they can re-share the subnet with you.

Can't access a file system over NFS, SMB, the ONTAP CLI, or the ONTAP REST API from a client in another VPC or on-premises

To access a file system over Network File System (NFS), Server Message Block (SMB), or the NetApp ONTAP CLI and REST API from a client in another VPC or on premises, you must configure routing using AWS Transit Gateway between the VPC associated with your file system and the network in which your client resides. For more information, see Accessing your FSx for ONTAP data.

Your storage virtual machine (SVM) is in a `MISCONFIGURED` state

There are a number of potential causes for a Storage Virtual Machine to get into a `MISCONFIGURED` state, each with their own resolution, as follows.

Your SVM has an offline volume

Your file system contains a volume which is in an offline state. We recommend that you keep volumes online in an ongoing basis. If you do not online this volume before your file system's next maintenance window, Amazon FSx will temporarily online this volume for the duration of the patching operation. To avoid this, please online or delete the volume.

To bring an offline volume back online, use the `volume online` ONTAP CLI command, as shown in the following example. If only one SVM (Vserver) exists, you do not need to specify the `-vserver` parameter.

```
FsxID-abcdef123456::> volume online -volume volume_name -vserver svm_name

Volume 'vs1:vol1' is now online.
```

Your SVM has an offline volume with an iSCSI LUN or an NVMe/TCP namespace

Your file system contains a volume which is in a restricted state. We recommend that you keep volumes online in an ongoing basis. If you do not online this volume before your file system's next maintenance window, Amazon FSx will temporarily online this volume for the duration of the patching operation. To avoid this, please online or delete the volume.

To bring an offline volume back online, use the `volume online` ONTAP CLI command, as shown in the following example. If only one SVM (Vserver) exists, you do not need to specify the `-vserver` parameter.

```
FsxID-abcdef123456::> volume online -volume volume_name -vserver svm_name

Volume 'vs1:vol1' is now online.
```

The AWS Secrets Manager secret or KMS key is not configured correctly

Amazon FSx can't establish a connection with your Microsoft Active Directory domain controller or controllers. This is because your AWS Secrets Manager secret or AWS KMS key is not configured correctly. For more information, see Storing Active Directory credentials using AWS Secrets Manager.

To resolve the misconfiguration, do the following:

- Verify that the secret ARN is correct and follows the proper format: `arn:aws:secretsmanager:region:account-id:secret:secret-name-6chars`.
- Verify that the secret contains both required fields with non-empty values:
  - `CUSTOMER_MANAGED_ACTIVE_DIRECTORY_USERNAME` – Your AD service account username.
  - `CUSTOMER_MANAGED_ACTIVE_DIRECTORY_PASSWORD` – Your AD service account password.
- Verify that the secret and key have a resource-based policy that grants the Amazon FSx service principal `fsx.amazonaws.com` permission to retrieve the secret value.

Troubleshooting SSD decrease operation issues

This section describes common issues and resolutions related to SSD capacity decrease operations.

Topics

- Your SSD decrease operation is paused due to high SSD utilization
- Your SSD decrease operation is paused due to FlexClone relationships
- Redirecting client access for volume(s) failed during SSD decrease
- Your SSD decrease operation is taking longer than expected

Your SSD decrease operation is paused due to high SSD utilization

If your SSD storage tier exceeds 80% utilization during a decrease operation, Amazon FSx automatically pauses the operation. You might see an Administrative Actions message similar to:

```
Your file system has insufficient free space in aggr_1. Please free up space or
 increase your file system's storage capacity.
```

The operation will resume once utilization falls below 80%. To resolve this issue, you can do the following:

- Delete unnecessary data from volumes that have already been moved to the new disks.
- Tier more data to the capacity pool by modifying volume tiering policies.
- Submit a request to increase SSD capacity by calling `update-file-system` with a new target value.

You should update your file system's SSD storage capacity so that your file system's resulting SSD capacity doesn't exceed 80% utilization after the decrease operation. For more details, see Updating file system SSD storage and IOPS.

You can identify which volumes have been moved to the new disks by checking the `Message` field in the `STORAGE_OPTIMIZATION` administrative action.

You can also call `describe-volumes` if the aggregate is `aggr1` or `aggr1_old`.

Your SSD decrease operation is paused due to FlexClone relationships

If FlexClone volumes are created after initiating an SSD decrease operation, Amazon FSx pauses the operation until the clones are deleted. This is because ONTAP splits clone relationships while moving volumes, which would result in duplicated storage on the new disks. To resolve this issue, you can identify and delete any FlexClone volumes that were created after the decrease operation started.

After you delete all FlexClone volumes, the decrease operation will automatically resume.

Redirecting client access for volume(s) failed during SSD decrease

During an SSD decrease operation, Amazon FSx needs to redirect client access from the old disks to the new disks for each volume. If this process fails, you might see an Administrative Actions message similar to:

```
Redirecting client access for volume(s) fsvol-123 has failed due to insufficient SSD
 IOPS, throughput capacity, or because the volume is full.
```

To resolve this issue, you can do the following:

- Check your file system's resource utilization metrics in Amazon CloudWatch to ensure that your workload isn't consuming more than 50% of the following resources:
  - `NetworkThroughputUtilization`
  - `FileServerDiskThroughputUtilization`
  - `FileServerDiskIopsUtilization`
  - `CPUUtilization`
  - `DiskIopsUtilization`

- If the volume is full, increase the volume's storage capacity.
- Reduce the workload on your file system during the decrease operation.

After addressing these issues, Amazon FSx will automatically retry to redirect client access once an hour.

Your SSD decrease operation is taking longer than expected

The time required to complete an SSD decrease operation depends on several factors, including the amount of data stored on the file system, ongoing workload activity, and available system resources. If your operation is taking longer than expected, you can do the following:

- Verify that your file system has adequate resources available (less than 50% CPU, disk throughput, and SSD IOPS utilization).
- Reduce write-heavy workloads during the operation to minimize resource contention.

You can track the progress of the operation by checking the `ProgressPercent` property in the `STORAGE_OPTIMIZATION` administrative action.

You can't join a storage virtual machine (SVM) to Active Directory

If you're unable to join an SVM to an Active Directory (AD), first review How joining SVMs to Microsoft Active Directory works. Common problems that prevent an SVM from joining to your Active Directory are listed in the following sections, including the error messages generated for each circumstance.

Topics

- The SVM NetBIOS name is the same as the NetBIOS name for the home domain.
- The SVM is already joined to another Active Directory
- Amazon FSx can't connect to your Active Directory domain controllers because the SVM's NetBIOS name is already in use
- Amazon FSx can't access your Active Directory service account credentials in AWS Secrets Manager
- Amazon FSx can't communicate with your Active Directory domain controllers

- Amazon FSx can't connect to your Active Directory due to unmet port requirements or service account permissions
- Amazon FSx can't connect to your Active Directory domain controllers because the service account credentials are not valid
- Amazon FSx can't connect to your Active Directory domain controllers because of insufficient service account credentials
- Amazon FSx can't communicate with your Active Directory DNS servers or domain controllers
- Amazon FSx can't communicate with your Active Directory because of a invalid Active Directory domain name.
- The service account can't access the administrators group specified in the SVM Active Directory configuration
- Amazon FSx can't connect to the Active Directory domain controllers because the organizational unit specified doesn't exist or isn't accessible

The SVM NetBIOS name is the same as the NetBIOS name for the home domain.

Joining an SVM to your self-managed Active Directory fails with the following error message:

Amazon FSx is unable to establish a connection with your Active Directory. This is because the server name you specified is the NetBIOS name of the home domain. To fix this problem, choose a NetBIOS name for your SVM that is different from the NetBIOS name of the home domain. Then reattempt to join your SVM to your Active Directory.

To resolve this issue, follow the procedure described in Joining SVMs to Active Directory using the AWS Management Console, AWS CLI and API to reattempt joining your SVM to your Active Directory. Ensure that you use a NetBIOS name for your SVM that's different than the NetBIOS name of the Active Directory's home domain.

The SVM is already joined to another Active Directory

Joining an SVM to an Active Directory fails with the following error message:

Amazon FSx is unable to establish a connection to your Active Directory. This is because the SVM is already joined to a domain. To join this SVM to a different domain, you can use the ONTAP CLI or REST API to unjoin this SVM from Active Directory. Then reattempt to join your SVM to a different Active Directory.

To resolve the issue, do the following:

1. Use the NetApp ONTAP CLI to unjoin the SVM from its current Active Directory. For more information, see Unjoin an Active Directory from your SVM using the NetApp ONTAP CLI.
2. Follow the procedure described in Joining SVMs to Active Directory using the AWS Management Console, AWS CLI and API to reattempt joining your SVM to the new Active Directory.

Amazon FSx can't connect to your Active Directory domain controllers because the SVM's NetBIOS name is already in use

Creating an SVM joined to your self-managed Active Directory fails with the following error message:

Amazon FSx is unable to establish a connection with your Active Directory. This is because the NetBIOS (computer) name you specified is already in-use in your Active Directory. To fix this problem, pick a NetBIOS name for your SVM that is not in use in your Active Directory., specifying a NetBIOS (computer) Then reattempt to join your SVM to your Active Directory.

To resolve this issue, follow the procedure described in Joining SVMs to Active Directory using the AWS Management Console, AWS CLI and API to reattempt joining your SVM to your AD. Ensure that you use a NetBIOS name for your SVM that's unique and not already in use in your Active Directory.

Amazon FSx can't access your Active Directory service account credentials in AWS Secrets Manager

The following sections describe common issues and how to resolve them.

Joining an SVM to your self-managed Active Directory fails with the following error message:

```
You can't provide both username/password and a domain join service account secret to connect to your Active Directory. Provide only one set of credentials.
```

To resolve this issue

1. Choose whether you want to provide credentials stored in a Secrets Manager secret, or in plaintext.

2. When joining an Active Directory, only provide one of those parameters and not both.

Joining an SVM to your self-managed Active Directory fails with the following error message:

```
The domain join service account secret ARN format you entered isn't
valid. Use the format: arn:partition:secretsmanager:region:account-
id:secret:secret-name-6chars
```

To resolve this issue

1. Review Storing Active Directory credentials using AWS Secrets Manager.
2. Verify that the ARN format you are entering is correct. A correct format example is `arn:aws:secretsmanager:us-east-1:123456789012:secret:MyDatabaseSecret-Ab3d5f`.

Joining an SVM to your self-managed Active Directory fails with the following error message:

```
Amazon FSx can't access the domain join service account secret [ARN]. Add
a resource permission to the secret that grants the FSx service principal
(fsx.amazonaws.com) permission to access it.
```

To resolve this issue

1. Review Storing Active Directory credentials using AWS Secrets Manager.
2. Verify that the Secrets Manager secret you are providing has the correct policies that allow Amazon FSx to use the secret.

Joining an SVM to your self-managed Active Directory fails with the following error message:

```
You don't have permission to access the domain join service account secret
[ARN]. A resource permission needs to be added to the secret to grant you
access.
```

To resolve this issue

- The Secrets Manager secret owner or administrator needs to give your account access to use this secret. For more information, see Identity-based policies.

Joining an SVM to your self-managed Active Directory fails with the following error message:

```
The domain join service account secret format or content isn't valid. Make
sure the secret includes both CUSTOMER_MANAGED_ACTIVE_DIRECTORY_USERNAME
and CUSTOMER_MANAGED_ACTIVE_DIRECTORY_PASSWORD fields with non-empty
values.
```

To resolve this issue

1. Review Storing Active Directory credentials using AWS Secrets Manager.
2. Verify that the Secrets Manager secret you are providing has both of the required fields.

Amazon FSx can't communicate with your Active Directory domain controllers

Joining an SVM to your self-managed Active Directory fails with the following error message:

Amazon FSx is unable to communicate with your Active Directory. To fix this problem, ensure that network traffic is allowed between Amazon FSx and your domain controllers. Then reattempt to join your SVM to your Active Directory.

To resolve this issue, do the following:

1. Review the requirements described in Network configuration requirements, and make changes needed to enable network communications between Amazon FSx and your AD.
2. Once Amazon FSx is able to communicate with your AD, follow the procedure described in Joining SVMs to Active Directory using the AWS Management Console, AWS CLI and API and reattempt joining your SVM to your AD.

Amazon FSx can't connect to your Active Directory due to unmet port requirements or service account permissions

Joining an SVM to your self-managed Active Directory fails with the following error message:

Amazon FSx is unable to establish a connection with your Active Directory. This is due to either the port requirements for your Active Directory not being met, or the service account provided not having permissions to join the storage virtual machine to the domain with the

specified organization unit. To fix this problem, update your storage virtual machine's Active Directory configuration after resolving any permissions issues with ports and service accounts, as recommended in the Amazon FSx user guide.

To resolve this issue, do the following:

1. Review the requirements described in Network configuration requirements, and make changes needed to meet the networking requirements and make sure communications are enabled on the required ports
2. Review the service account requirements described in Active Directory service account requirements. Ensure that service account has the delegated permissions necessary to join your SVM to the Active Directory domain using the specified organizational unit.
3. Once you have made changes to the port permissions or the service account, follow the procedure described in Joining SVMs to Active Directory using the AWS Management Console, AWS CLI and API and reattempt joining your SVM to your AD.

Amazon FSx can't connect to your Active Directory domain controllers because the service account credentials are not valid

Joining an SVM to your self-managed Active Directory fails with the following error message:

Amazon FSx is unable to establish a connection with your Active Directory domain controller(s) because the service account credentials provided are invalid. To fix this problem, update your storage virtual machine's Active Directory configuration with a valid service account.

To resolve this issue, use the procedure described in Updating existing SVM Active Directory configurations using the AWS Management Console, AWS CLI, and API to update the SVM's service account credentials. When entering the service account user name, be sure to include only the user name (for example, `ServiceAcct`), and don't include any domain prefix (for example, `corp.com\ServiceAcct`) or domain suffix (for example, `ServiceAcct@corp.com`). Don't use the distinguished name (DN) when entering the service account user name (for example, `CN=ServiceAcct,OU=example,DC=corp,DC=com`).

Amazon FSx can't connect to your Active Directory domain controllers because of insufficient service account credentials

Joining an SVM to your self-managed Active Directory fails with the following error message:

Amazon FSx is unable to establish a connection with your Active Directory domain controller(s). This is due to either unmet port requirements for the Active Directory, or the service account provided does not have permission to join the storage virtual machine to the domain with the specified organizational unit.

To resolve this issue, make sure that you have delegated the required permissions to the service account that you provided. The service account must be able to create and delete computer objects in the OU in the domain to which you're joining the file system. The service account also needs, at a minimum, to have permissions to do the following:

- Reset passwords
- Restrict accounts from reading and writing data
- Validated ability to write to the DNS hostname
- Validated ability to write to the service principal name
- Ability to create and delete computer objects
- Validated ability to read and write Account Restrictions

For more information about creating a service account with correct permissions, see Active Directory service account requirements and Delegating permissions to your Amazon FSx service account.

Amazon FSx can't communicate with your Active Directory DNS servers or domain controllers

Joining an SVM to your self-managed Active Directory fails with the following error message:

Amazon FSx is unable to communicate with your Active Directory. This is because Amazon FSx can't reach the DNS servers provided or domain controllers for your domain. To fix this problem, update your storage virtual machine's Active Directory configuration with valid DNS servers and a networking configuration that allows traffic to flow from the storage virtual machine to the domain controller.

To resolve this issue, use the following procedure:

1. If only some of the domain controllers in your Active Directory are reachable, for example due to geographical limitations or firewalls, you can add preferred domain controllers. Using this option, Amazon FSx attempts to contact the preferred domain controllers. Add preferred

domain controllers using the `vserver cifs domain preferred-dc add` NetApp ONTAP CLI command, as follows:

a. To access the ONTAP CLI, establish an SSH session on the management port of the Amazon FSx for NetApp ONTAP file system or SVM by running the following command. Replace *`management_endpoint_ip`* with the IP address of the file system's management port.

```
[~]$ ssh fsxadmin@management_endpoint_ip
```

For more information, see Managing file systems with the ONTAP CLI.

b. Enter the following command, where:

- `-vserver vserver_name` specifies the storage virtual machine (SVM) name.
- `-domain domain_name` specifies the fully qualified Active Directory name (FQDN) of the domain to which the specified domain controllers belong.
- `-preferred-dc IP_address,…` specifies one or more IP addresses of the preferred domain controllers, as a comma-delimited list, in order of preference.

```
FsxId123456789::> vserver cifs domain preferred-dc add -vserver vserver_name -
domain domain_name -preferred-dc IP_address, …+
```

The following command adds domain controllers 172.17.102.25 and 172.17.102.24 to the list of preferred domain controllers that the SMB server on SVM vs1 uses to manage external access to the cifs.lab.example.com domain.

```
FsxId123456789::> vserver cifs domain preferred-dc add -vserver vs1 -domain
 cifs.lab.example.com -preferred-dc 172.17.102.25,172.17.102.24
```

2. Check to see if your Domain Controller can be resolved with DNS. Use the `vserver services access-check dns forward-lookup` NetApp ONTAP CLI command to return the IP address of a hostname based on the look up on the DNS server specified or the vserver's DNS configuration.

a. To access the ONTAP CLI, establish an SSH session on the management port of the Amazon FSx for NetApp ONTAP file system or SVM by running the following command.

Replace *management_endpoint_ip* with the IP address of the file system's management port.

```
[~]$ ssh fsxadmin@management_endpoint_ip
```

For more information, see Managing file systems with the ONTAP CLI.

b. Enter the ONTAP CLI advanced mode using the following command.

```
FsxId123456789::> set adv
```

c. Enter the following command, where:

- `-vserver vserver_name` specifies the storage virtual machine (SVM) name.
- `-hostname host_name` specifies the hostname to look up on the DNS server.
- `-node node_name` specifies the name of the node on which the command is executed.
- `-lookup-type` specifies the type of IP address to be looked up on the DNS server, default is `all`.

```
FsxId123456789::> vserver services access-check dns forward-lookup \
-vserver vserver_name -node node_name \
-domains domain_name -name-servers dns_server_ip_address \
-hostname host_name
```

3. Review the information you need to have when joining an SVM to an AD.
4. Review the networking requirements when joining an SVM to an AD.
5. Use the procedure described in Network configuration requirements to update your SVM's Active Directory configuration using the correct IP addresses for your Active Directory DNS servers.

Amazon FSx can't communicate with your Active Directory because of a invalid Active Directory domain name.

Joining an SVM to your self-managed Active Directory fails with the following error message:

Amazon FSx has detected the provided FQDN is invalid. To fix this problem, update your storage virtual machine's Active Directory configuration with an FQDN that adheres to configuration requirements.

To resolve this issue, use the following procedure:

1. Review the on-premises Active Directory domain name requirements described in Information needed when joining an SVM to an Active Directory Make sure that the Active Directory you are attempting to join meets that requirement.
2. Use the procedure described in Joining SVMs to Active Directory using the AWS Management Console, AWS CLI and API and reattempt joining your SVM to an Active Directory. Be sure to use the correct format for the Active Directory domain's FQDN.

The service account can't access the administrators group specified in the SVM Active Directory configuration

Joining an SVM to your self-managed Active Directory fails with the following error message:

Amazon FSx is unable to apply your Active Directory configuration. This is because the administrators group you provided either doesn't exist or isn't accessible to the service account you provided. To fix this problem, ensure that your networking configuration allows traffic from the SVM to your Active Directory's domain controller(s) and DNS servers. Then update your SVM's Active Directory configuration, providing your Active Directory's DNS servers and, specifying an administrators group in the domain that is accessible to the service account provided.

To resolve this issue, do the following:

1. Review the information about providing a domain group to perform administrative actions on your SVM. Make sure that you are using the correct name of the Active Directory domain administrators group.
2. Use the procedure described in Joining SVMs to Active Directory using the AWS Management Console, AWS CLI and API and reattempt joining your SVM to an AD.

Amazon FSx can't connect to the Active Directory domain controllers because the organizational unit specified doesn't exist or isn't accessible

Joining an SVM to your self-managed Active Directory fails with the following error message:

Amazon FSx is unable to establish a connection with your Active Directory. This is because the organizational unit you specified either doesn't exist or isn't accessible to the service account provided. To fix this problem, update your storage virtual machine's Active Directory configuration, specifying an organizational unit to which the service account has permissions to join.

To resolve this issue, do the following:

1. Review the prerequisites for joining an SVM to an AD.
2. Review the information that you need to have when joining an SVM to an AD.
3. Reattempt joining the SVM to the Active Directory using this procedure with the correct organization unit.

You can't delete a storage virtual machine or volume

Each FSx for ONTAP file system can contain one or more storage virtual machines (SVMs), and each SVM can contain one or more volumes. When you delete a resource, you must first ensure that all its children have been deleted. For example, before deleting an SVM, you must first delete all the non-root volumes in the SVM.

> **Important**
>
> You can only delete storage virtual machines by using the Amazon FSx console, API, and CLI. You can only delete volumes using the Amazon FSx console, API, or CLI if the volume has Amazon FSx backups enabled.

To help protect your data and configuration, Amazon FSx prevents the deletion of SVMs and volumes in certain circumstances. If you attempt to delete an SVM or volume, and your deletion request doesn't succeed, Amazon FSx provides you with information in the AWS console, AWS Command Line Interface (AWS CLI), and API regarding why the resource wasn't deleted. After you have addressed the cause of the deletion failure, you can retry the deletion request.

Topics

- Identifying failed deletions
- SVM deletion: Route tables inaccessible
- SVM deletion: Peer relationship
- SVM or volume deletion: SnapMirror
- SVM deletion: Kerberos-enabled LIF
- SVM deletion: Other reason
- Volume deletion: FlexCache relationship

Identifying failed deletions

When you delete an Amazon FSx SVM or volume, you typically see the resource's `Lifecycle` state transition to `DELETING` for up to a few minutes before the resource disappears from the Amazon FSx console, CLI, and API.

If you attempt to delete a resource and its `Lifecycle` state transitions from to `DELETING` and then back to `CREATED`, this behavior indicates that the resource didn't successfully delete. In this case, Amazon FSx reports an alert icon in the console next to the `CREATED` Lifecycle state. Choosing the alert icon displays the reason for the unsuccessful deletion.

The most common reasons why Amazon FSx prevents SVM and volume deletion are provided in the following sections, with step-by-step instructions on how to resolve these issues.

SVM deletion: Route tables inaccessible

Each FSx for ONTAP file system creates one or more route table entries to provide automatic failover and fail back across Availability Zones. By default, these route table entries are created in your VPC's default route table. You can optionally specify one or more non-default route tables where FSx for ONTAP interfaces can be created. Amazon FSx tags each route table that it associated with a file system with an `AmazonFSx` tag, and if this tag is removed, it can prevent Amazon FSx from being able to delete resources. If this situation occurs, you see the following `LifecycleTransitionReason`:

```
Amazon FSx is unable to complete the requested storage virtual machine
operation because of an inability to access one or more of the route tables
associated with your file system. Please contact Support.
```

You can find your file system's route tables in the Amazon FSx console by navigating to the file system's summary page, under the **Network & security** tab.

Choosing the route tables link takes you to your route tables. Next, verify that each of the route tables associated with your file system is tagged with this key-value pair:

```
Key: AmazonFSx
Value: ManagedByAmazonFSx
```

If this tag isn't present, recreate it, and then try to delete the SVM again.

SVM deletion: Peer relationship

If you're attempting to delete an SVM or volume that's part of a peer relationship, you must first delete the peer relationship before you delete the SVM or volume. This requirement prevents the peered SVMs from becoming unhealthy. If your SVM can't be deleted because of a peer relationship, you see the following `LifecycleTransitionReason`:

Amazon FSx is unable to delete the storage virtual machine because it is part of a SVM peer or transition peer relationship. Please delete the relationship and retry.

You can delete SVM peer relationships through the ONTAP CLI. To access the ONTAP CLI, follow the steps in Managing file systems with the ONTAP CLI. Using the ONTAP CLI, take the following steps.

1. Check for SVM peer relationships by using the following command. Replace *svm_name* with the name of your SVM.

   ```
   FsxId123456789::> vserver peer show -vserver svm_name
   ```

   If this command is successful, you'll see output similar to the following:

   ```
               Peer        Peer                           Peering        Remote
   Vserver     Vserver     State        Peer Cluster      Applications   Vserver
   ----------- ----------- ------------ ----------------- -------------- ---------
   svm_name    test2       peered       FsxId02d81fef0d84734b6
                                                          snapmirror     fsxDest
   svm_name    test3       peered       FsxId02d81fef0d84734b6
                                                          snapmirror     fsxDest
   2 entries were displayed.
   ```

2. Delete each SVM peer relationship by using the following command. Replace *svm_name*, and *remote_svm_name* with your actual values.

```
FsxId123456789abcdef::> vserver peer delete -vserver svm_name -peer-
vserver remote_svm_name
```

If this command is successful, you'll see the following output:

```
Info: 'vserver peer delete' command is successful.
```

SVM or volume deletion: SnapMirror

Just as you can't delete an SVM with a peer relationship without first deleting the peer relationship (see SVM deletion: Peer relationship), you can't delete an SVM that has a SnapMirror relationship without first deleting the SnapMirror relationship. To delete the SnapMirror relationship, use the ONTAP CLI to take the following steps on the file system that's the destination of the SnapMirror relationship. To access the ONTAP CLI, follow the steps in Managing file systems with the ONTAP CLI.

> **Note**
>
> Amazon FSx backups use SnapMirror to create point-in-time, incremental backups of your file system's volumes. You can't delete this SnapMirror relationship for your backups in the ONTAP CLI. However, this relationship is automatically deleted when you delete a volume through the AWS CLI, API, or console.

1. List your SnapMirror relationships on the destination file system by using the following command. Replace *svm_name* with the name of your SVM.

```
FsxId123456789abcdef::> snapmirror show -vserver svm_name
```

If this command is successful, you'll see output similar to the following:

```
Source            Destination    Mirror  Relationship   Total             Last
Path        Type  Path           State   Status         Progress  Healthy Updated
----------- ---- ------------    ------- -------------- --------- ------- --------
```

```
sourceSvm:sourceVol
            XDP  destSvm:destVol Snapmirrored
                                        Idle           -         true    -
```

2. Delete your SnapMirror relationship by running the following command on the destination file system.

```
FsxId123456789abcdef::> snapmirror release -destination-path destSvm:destVol -
source-path sourceSvm:sourceVol -force true
```

SVM deletion: Kerberos-enabled LIF

If you are attempting to delete an SVM that has a logical interface (LIF) with Kerberos enabled, you must first disable Kerberos on that LIF before deleting the SVM.

You can disable Kerberos on a LIF through the ONTAP CLI. To access the ONTAP CLI, follow the steps in Managing file systems with the ONTAP CLI.

1. Enter diagnostic mode in the ONTAP CLI by using the following command.

```
FsxId123456789abcdef::> set diag
```

When prompted to continue, enter **y**.

```
Warning: These diagnostic commands are for use by NetApp personnel only.
Do you want to continue? {y|n}: y
```

2. Check which interfaces have Kerberos enabled. Replace *svm_name* with the name of your SVM.

```
FsxId123456789abcdef::> kerberos interface show -vserver svm_name
```

If this command is successful, you'll see output similar to the following:

```
(vserver nfs kerberos interface show)
               Logical
Vserver        Interface     Address         Kerberos SPN
-------------- ------------- --------------- -------- ----------------------
svm_name       nfs_smb_management_1
                             10.19.153.48    enabled
```

```
5 entries were displayed.
```

3. Disable the Kerberos LIF by using the following command. Replace *svm_name* with the name of your SVM. You'll need to provide the Active Directory username and password that you used to join this SVM to your Active Directory.

```
FsxId123456789abcdef::> kerberos interface disable -vserver svm_name -lif
 nfs_smb_management_1
```

If this command is successful, you'll see the following output. Provide the Active Directory username and password that you used to join this SVM to your Active Directory. When prompted to continue, enter **y**.

```
(vserver nfs kerberos interface disable)
Username: admin
Password: *************

Warning: This command deletes the service principal name from the machine account
 on the KDC.
Do you want to continue? {y|n}: y

Disabled Kerberos on LIF "nfs_smb_management_1" in Vserver "svm_name".
```

4. Verify that Kerberos is disabled on the SVM by using the following command. Replace *svm_name* with the name of your SVM.

```
FsxId123456789abcdef::> kerberos interface show -vserver svm_name
```

If this command is successful, you'll see output similar to the following:

```
(vserver nfs kerberos interface show)
               Logical
Vserver        Interface     Address         Kerberos SPN
-------------- ------------- --------------- -------- ----------------------
svm_name       nfs_smb_management_1
                             10.19.153.48    disabled
5 entries were displayed.
```

5. If the interface is shown as `disabled`, try to delete the SVM again through the AWS CLI, API, or console.

If you weren't able to delete the LIF by using the preceding commands, you can force-delete the Kerberos LIF by using the following command. Replace *svm_name* with the name of your SVM.

> **Important**
>
> The following command can strand the computer object of your SVM on your Active Directory.

```
FsxId123456789abcdef::> kerberos interface disable -vserver svm_name -lif
 nfs_smb_management_1 -force true
```

If this command is successful, you'll see output similar to the following. When prompted to continue, enter **y**.

```
(vserver nfs kerberos interface disable)

Warning: Kerberos configuration for LIF "nfs_smb_management_1" in Vserver
 "svm_name" will be deleted.
The corresponding account on the KDC will not be deleted. Do you want to continue?
 {y|n}: y
```

SVM deletion: Other reason

FSx for ONTAP SVMs create a computer object in your Active Directory when they join your Active Directory. In some cases, you may want to manually unjoin an SVM from your Active Directory by using the ONTAP CLI. To access the ONTAP CLI, follow the steps in Managing file systems with the ONTAP CLI, logging into the ONTAP CLI at the file system level with `fsxadmin` credentials. Using the ONTAP CLI, take the following steps to unjoin an SVM from your Active Directory.

> **Important**
>
> This procedure can strand the computer object of your SVM on your Active Directory.

1. Enter advanced mode in the ONTAP CLI by using the following command.

```
FsxId123456789abcdef::> set adv
```

After running this command, you'll see this output. Enter **y** to continue.

```
Warning: These advanced commands are potentially dangerous; use them only when
      directed to do so by NetApp personnel.
      Do you want to continue? {y|n}: y
```

2. Delete the DNS for your Active Directory by using the following command. Replace *svm_name* with the name of your SVM.

```
FsxId123456789abcdef::> vserver services name-service dns dynamic-update record
 delete -vserver svm_name -lif nfs_smb_management_1
```

> **Note**
>
> If the DNS record has already been deleted or if the DNS server is unreachable, this command fails. If that happens, continue with the next step.

3. Disable the DNS by using the following command. Replace *svm_name* with the name of your SVM.

```
FsxId123456789abcdef::> vserver services name-service dns dynamic-update modify -
vserver svm_name -is-enabled false -use-secure false
```

If this command is successful, you'll see the following output:

```
Warning: DNS updates for Vserver "svm_name" are now disabled.
     Any LIFs that are subsequently modified or deleted
     can result in a stale DNS entry on the DNS server,
     even when DNS updates are enabled again.
```

4. Unjoin the device from Active Directory. Replace *svm_name* with the name of your SVM.

```
FsxId123456789abcdef::> vserver cifs delete -vserver svm_name
```

After running this command, you'll see the following output, where *CORP.EXAMPLE.COM* is replaced with the name of your domain. When prompted, enter your user name and password. When asked if you want to delete the server, enter **y**.

```
In order to delete an Active Directory machine account for the CIFS server,
you must supply the name and password of a Windows account with sufficient
privileges to remove computers from the "CORP.EXAMPLE.COM" domain.
Enter the user name: admin
Enter the password:
Warning: There are one or more shares associated with this CIFS server
     Do you really want to delete this CIFS server and all its shares? {y|n}: y
Warning: Unable to delete the Active Directory computer account for this CIFS
 server.
     Do you want to continue with CIFS server deletion anyway? {y|n}: y
```

Volume deletion: FlexCache relationship

You can't delete volumes that are the origin volumes for a FlexCache relationship unless you delete the cache relationship first. To determine which volumes have a FlexCache relationship, you can use the ONTAP CLI. To access the ONTAP CLI, follow the steps in Managing file systems with the ONTAP CLI.

1. Check for FlexCache relationships by using the following command.

```
FsxId123456789abcdef::> volume flexcache origin show-caches
```

2. Delete any cache relationships by using the following command. Replace *dest_svm_name*, and *dest_vol_name* with your actual values.

```
FsxId123456789abcdef::> volume flexcache delete -vserver dest_svm_name -
volume dest_vol_name
```

3. After you've deleted the cache relationship, try to delete your SVM through the AWS CLI, API, or console again.

Your volume is in a `MISCONFIGURED` state

There are a number of potential causes for an ONTAP volume to get into a `MISCONFIGURED` state, described in the following topics.

Your volume is more than 98% full

Your file system currently contains a volume which is more than 98% full. We recommend that you do not exceed 95% utilization of your volume on an ongoing basis. If you do not free up space in the volume before your file system's next maintenance window, Amazon FSx will disable opportunistic locking on the volume, breaking any existing "oplocks". Amazon FSx will re-enable oplocks on the volume after the patching process completes. To avoid this, please reduce the volume's storage capacity utilization to below 98%. Some of the ways to achieve this include:

- Increasing the size of the volume.
- Deleting unneeded data.
- Deleting unneeded snapshots.

For more information, see Updating storage capacity, and Deleting snapshots.

Your offline volume has an iSCSI LUN or an NVMe/TCP namespace

Your file system currently hosts a volume which is in an offline state, and that volume contains an iSCSI LUN, or an NVMe/TCP namespace, or both. We recommend that you keep volumes online on an ongoing basis. If you do not online this volume before your file system's next maintenance window, Amazon FSx will temporarily online this volume for the duration of the patching operation. To avoid this, please online or delete the volume.

To bring an offline volume back online, use the `volume online` ONTAP CLI command, as shown in the following example. If only one SVM (Vserver) exists, you do not need to specify the `-vserver` parameter.

```
FsxID-abcdef123456::> volume online -volume volume_name -vserver svm_name

Volume 'vs1:vol1' is now online.
```

Your offline volume is a FlexCache origin

Your file system contains a FlexCache origin volume which is in an offline state. We recommend that you keep volumes online on an ongoing basis. If you do not online this volume before your file system's next maintenance window, Amazon FSx will temporarily online this volume for the duration of the patching operation. During this time, it is possible that data will be written back to the FlexCache origin volume with data from the cache volume. To avoid this, please online or delete the volume.

To bring an offline volume back online, use the `volume online` ONTAP CLI command, as shown in the following example. If only one SVM (Vserver) exists, you do not need to specify the `-vserver` parameter.

```
FsxID-abcdef123456::> volume online -volume volume_name -vserver svm_name

Volume 'vs1:vol1' is now online.
```

Your offline volume is part of a SnapMirror relationship

Your file system currently hosts a volume that is in an offline state, and that volume is a SnapMirror source or destination. We recommend that you keep volumes online on an ongoing basis. If you don't online this volume before your file system's next maintenance window, Amazon FSx will temporarily online this volume for the duration of the patching operation and pause the SnapMirror relationship. During this time, it's possible that data will be written to the SnapMirror destination volume with data from the SnapMirror source volume. To avoid this, please online or delete the volume.

To bring an offline volume back online, use the `volume online` ONTAP CLI command, as shown in the following example. If only one SVM (Vserver) exists, you do not need to specify the `-vserver` parameter.

```
FsxID-abcdef123456::> volume online -volume volume_name -vserver svm_name

Volume 'vs1:vol1' is now online.
```

Your restricted volume contains an iSCSI LUN or an NVMe/TCP namespace

Your file system currently hosts a volume that is in a restricted state, and that volume contains an iSCSI LUN, an NVMe/TCP namespace, or both. We recommend that you keep volumes online on an ongoing basis. If you don't online this volume before your file system's next maintenance window, Amazon FSx will temporarily online this volume for the duration of the patching operation. To avoid this, please online or delete the volume.

To bring an offline volume back online, use the `volume online` ONTAP CLI command, as shown in the following example. If only one SVM (Vserver) exists, you do not need to specify the `-vserver` parameter.

```
FsxID-abcdef123456::> volume online -volume volume_name -vserver svm_name

Volume 'vs1:vol1' is now online.
```

Your restricted volume is a FlexCache origin

Your file system contains a FlexCache origin volume that is in a restricted state. We recommend that you keep volumes online on an ongoing basis. If you don't online this volume before your file system's next maintenance window, Amazon FSx will temporarily online this volume for the duration of the patching operation. During this time, it's possible that data will be written back to the FlexCache origin volume with data from the cache volume. To avoid this, please online or delete the volume.

To bring an offline volume back online, use the `volume online` ONTAP CLI command, as shown in the following example. If only one SVM (Vserver) exists, you do not need to specify the `-vserver` parameter.

```
FsxID-abcdef123456::> volume online -volume volume_name -vserver svm_name

Volume 'vs1:vol1' is now online.
```

Your restricted volume is part of a SnapMirror relationship

Your file system currently hosts a volume that is in a restricted state, and that volume is a SnapMirror source or destination. We recommend that you keep volumes online on an ongoing

basis. If you don't online this volume before your file system's next maintenance window, Amazon FSx will temporarily online this volume for the duration of the patching operation and pause the SnapMirror relationship. During this time, it's possible that data will be written to the SnapMirror destination volume with data from the SnapMirror source volume. To avoid this, please online or delete the volume.

To bring an offline volume back online, use the `volume online` ONTAP CLI command, as shown in the following example. If only one SVM (Vserver) exists, you do not need to specify the `-vserver` parameter.

```
FsxID-abcdef123456::> volume online -volume volume_name -vserver svm_name

Volume 'vs1:vol1' is now online.
```

Your volume has insufficient storage capacity

If you are running out of space on your volumes, you can use the procedures shown here to diagnose and resolve the situation.

Topics

- Determine how your volume storage capacity is being used
- Increasing a volume's storage capacity
- Using volume autosizing
- Your file system's primary storage is full
- Deleting snapshots
- Increasing a volume's maximum file capacity

Determine how your volume storage capacity is being used

You can see how your volume's storage capacity is being consumed by using the `volume show-space` NetApp ONTAP CLI command. This information can help you make decisions about how to reclaim or conserve volume storage capacity. For more information, see To monitor a volume's storage capacity (console).

Increasing a volume's storage capacity

You can increase a volume's storage capacity by using the Amazon FSx console, AWS CLI, and Amazon FSx API. For more information about updating a volume with an increased capacity, see Updating volumes.

Alternatively, you can increase a volume's storage capacity using the `volume modify` NetApp ONTAP CLI command. For more information, see To change a volume's storage capacity (console).

Using volume autosizing

You can use volume autosizing so that a volume automatically grows by a specified amount, or to a specified size when it reaches a used space threshold. You can do this for FlexVol volume types, which is the default volume type for FSx for ONTAP, using the `volume autosize` NetApp ONTAP CLI command. For more information, see Enabling autosizing.

Your file system's primary storage is full

If your FSx for ONTAP file system's primary storage is full, you cannot add any more data to the volumes in your file system, even if a volume is showing that it has enough available storage capacity. You can view the amount of available primary storage capacity in the **Monitoring & performance** tab on the file system details page in the Amazon FSx console. For more information, see Monitoring SSD storage utilization

To resolve this issue, you can increase the size of your file system's primary storage tier. For more information, see Updating file system SSD storage and IOPS.

Deleting snapshots

Snapshots are enabled by default on your volumes, using the default snapshot policy. Snapshots are stored in the `.snapshot` directory at the root of a volume. You can manage volume storage capacity with respect to snapshots in the following ways:

- Manually delete snapshots – reclaim storage capacity by deleting snapshots manually.
- Create a snapshot autodelete policy – create a policy that deletes snapshots more aggressively than the default snapshot policy.
- Turn off automatic snapshots – conserve storage capacity by turning off automatic snapshots.

When you delete a snapshot, you do not reclaim the amount of storage equal to the size of the snapshot you are deleting. You can see the amount of storage you can reclaim when deleting a snapshot by using the volume snapshot compute-reclaimable -vserver ONTAP CLI command, using your data to replace *svm_name*, *vol_name*, and *snapshot_name*.

```
fsid8970abc52::> volume snapshot compute-reclaimable -vserver svm_name -volume vol_name
 -snapshot snapshot_name
A total of 667648 bytes can be reclaimed.
```

For more information about deleting snapshots and managing snapshot policies to conserve storage capacity, see Deleting snapshots.

Increasing a volume's maximum file capacity

An FSx for ONTAP volume can run out of file capacity when the number of available inodes, or file pointers, is exhausted. By default, the number of available inodes on a volume is 1 for every 32KiB of volume size. For more information, see Volume file capacity.

The number of inodes in a volume increases commensurately with the volume's storage capacity, up to a threshold of 648 GiB. By default, volumes that have storage capacity of 648 GiB or more all have the same number of inodes, 21,251,126. To view a volume's maximum file capacity, see Monitoring a volume's file capacity.

If you create a volume larger than 648 GiB, and you want to have more that 21,251,126 inodes, you must increase the maximum number of files on the volume manually. If your volume is running out of storage capacity, you can check its maximum file capacity. If it's nearing its file capacity, you can manually increase it. For more information, see To increase the maximum number of files on a volume (ONTAP CLI).

Your backups fail due to insufficient volume capacity

Automatic daily backups of your volume fails with the following message:

```
Amazon FSx could not create a backup of your volume because the backup snapshot was
 deleted.
```

Automatic daily backups are failing because there is insufficient free storage capacity on the volume. To mitigate this condition, you will need to free up storage capacity on the volume. You can accomplish this using one or more of the following options, depending on your situation:

- Increase the volume's storage capacity
- Increase the volume's snapshot reserve
- Disable snapshot auto-delete
- Don't delete the backup-snapshot using the ONTAP CLI

Recovering deleted FSx for ONTAP volumes

When an FSx for ONTAP volume is deleted, it's placed in ONTAP's recovery queue. While you can recover a volume directly from this queue using the ONTAP CLI, the recovered volume won't reappear in the AWS console or Amazon FSx API and any AWS tags that were previously applied to the volume will be permanently lost. To properly recover an FSx for ONTAP volume while preserving AWS integration and tag-based security policies, you can either restore a backup to a new volume or replicate the volume's data to a new volume using SnapMirror. For more information about ONTAP's recovery queue, see NetApp's documentation.

Troubleshooting network issues

If you are experiencing network issues, you can use the procedures shown here to diagnose the problem.

You want to capture a packet trace

Packet tracing is the process of verifying the path of a packet through the layers to its destination. You control the packet tracing process with the following NetApp ONTAP CLI commands:

- **network tcpdump start** – Starts packet tracing
- **network tcpdump show** – Shows currently running packet traces
- **network tcpdump stop** – Stops a running packet trace

These commands are available to users who have the `fsxadmin` role on your file system.

To capture a packet trace from your file system

1. To SSH into the NetApp ONTAP CLI of your file system, follow the steps documented in the Using the NetApp ONTAP CLI section of the *Amazon FSx for NetApp ONTAP User Guide*.

```
ssh fsxadmin@file-system-management-endpoint-ip-address
```

2. Enter the diagnostic privilege level in the ONTAP CLI by using the following command.

```
::> set diag
```

When prompted to continue, enter y.

```
Warning: These diagnostic commands are for use by NetApp personnel only.
Do you want to continue? {y|n}: y
```

3. Identify the location on your file system where you want to save your packet trace. The volume must be online and must be mounted in the namespace with a valid junction path. Use the following command to check for volumes that fulfill those criteria:

```
::*> volume show -junction-path !- -fields junction-path
vserver volume    junction-path
------- --------- -------------
fsx     test_vol1 /test_vol1
fsx     test_vol2 /test_vol2
fsx     test_vol2 /test_vol3
```

4. Start the trace with the minimum required arguments. Replace the following:

- Replace *node_name* with the name of the node (for example, `FsxId01234567890abcdef-01`).
- Replace *svm_name* with the name of your storage virtual machine (for example, `fsx`).
- Replace *junction_path_name* with the name of the volume (for example, `test-vol1`).

```
::*> debug network tcpdump start -node node_name -ipspace Default -pass-through "-i
 e0e -w /clus/svm_name/junction_path_name"
Info: Started network trace on interface "e0e"
Warning: Snapshots should be disabled on the tcpdump destination volume while
 packet traces are occurring. Use the
"volume modify -snapshot-policy none -vserver fsx -volume test_vol1" command to
 disable Snapshots on the
tcpdump destination volume.
```

> **Important**
>
> Packet traces can only be captured on the `e0e` interface and in the `Default` IP space. In FSx for ONTAP, all network traffic uses the `e0e` interface.

When using packet tracing, keep the following in mind:

- When starting a packet trace, you must include the path to where you want to store the trace files, in this format: /clus/*svm_name*/*junction-path-name*
- Optionally, provide the file name for the packet trace. If the filter_name is not specified, it is automatically generated in the form: *node-name_port-name_yyyymmdd_hhmmss*.trc
- If rolling traces are specified, the filter_name is suffixed with a number that indicates the position in the rotation sequence.
- The ONTAP CLI also accepts the following optional **-pass-through** arguments:

```
-B, --buffer-size=<KiB>
-c <number_of_packets>
-C <file_size-mB>
-F <filter_expression_filename>
-G <rotate_seconds>
--time-stamp-precision {micro|nano}
-Q, --direction {in|out|inout}
-s, --snapshot-length=<bytes>
-U, --packet-buffered
-W <rotate_file_count>
<filter-expression>
```

- For information about filter expressions, see pcap-filter(7) man page.

5. View the traces in progress:

```
::*> debug network tcpdump show
Node                    IPspace  Port     Filename
----------------------  -------- -------- --------
FsxId123456789abcdef-01  Default  e0e      /clus/fsx/test_vol1/
FsxId123456789abcdef-01_e0e_20230605_181451.trc
```

6. Stop the trace:

```
::*> debug network tcpdump stop -node FsxId123456789abcdef-01 -ipspace Default -
port e0e
Info: Stopped network trace on interface "e0e"
```

7. Return to the admin privilege level:

```
::*> set -priv admin
::>
```

8. Access the packet traces.

   Your packet traces are stored in the volume that you specified using the **debug network tcpdump start** command, and can be accessed via the NFS export or an SMB share that corresponds with that volume.

For more information about capturing packet traces, see How to use debug network dump in ONTAP 9.10+ in the NetApp Knowledge Base.

Troubleshooting I/O errors and NFS lock reclaim failures

This section describes issues related to I/O errors and NFS lock reclaim failures during failover events on FSx for ONTAP file systems and resolutions for each of them.

You are experiencing I/O errors during failover events

During failovers on FSx for ONTAP Single-AZ file systems, NFS clients may experience transient I/O errors or extended pauses. For NFSv4+ clients, you may see kernel log messages like:

```
NFS: __nfs4_reclaim_open_state: Lock reclaim failed!
```

These messages indicate that the client was unable to successfully reclaim NFS locks during the failover window.

To reduce I/O errors during failover events

On Linux, you can configure network settings on your clients to reduce failover detection time from 55-60 seconds to 15-20 seconds.

Important

Always test these configurations in a non-production environment first. These settings increase Address Resolution Protocol (ARP) traffic, which is used to map IP addresses to physical (MAC) addresses on a local network, and may not be suitable for network-constrained environments.

To configure optimized network settings for NFS clients

1. Create a sysctl configuration file on each NFS client. The following example uses `default` to apply settings to all network interfaces. If your instance has multiple network interfaces, you can replace `default` with the specific interface name (for example, `eth0` or `ens5`) used to connect to your FSx for ONTAP Single-AZ file system:

```
$ sudo tee /etc/sysctl.d/99-fsx-failover.conf > /dev/null << 'EOF'
# NFS client optimizations for faster failover detection
# Replace 'default' with your interface name (e.g., eth0, ens5) to target a
 specific interface
net.ipv4.neigh.default.base_reachable_time_ms=5000
net.ipv4.neigh.default.delay_first_probe_time=1
net.ipv4.neigh.default.ucast_solicit=0
net.ipv4.tcp_syn_retries=3
EOF
```

2. Apply the settings immediately:

```
$ sudo sysctl -p /etc/sysctl.d/99-fsx-failover.conf
```

3. Verify the configuration is active. If you used `default`, you can verify with the following commands. If you specified a specific interface, replace `default` with your interface name (for example, `eth0` or `ens5`):

```
$ sysctl net.ipv4.neigh.default.base_reachable_time_ms
$ sysctl net.ipv4.neigh.default.delay_first_probe_time
$ sysctl net.ipv4.neigh.default.ucast_solicit
$ sysctl net.ipv4.tcp_syn_retries
```

Ensure that these settings are applied consistently across all NFS clients that connect to your FSx for ONTAP file system within the same Availability Zone. When using these network optimizations, keep the following in mind:

- **base_reachable_time_ms=5000** – Reduces ARP cache entry validity from 30 seconds to 5 seconds, allowing clients to detect IP ownership changes more quickly during a failover event.
- **delay_first_probe_time=1** – Reduces the delay before probing a stale network entry from 5 seconds to 1 second.
- **ucast_solicit=0** – Skips unicast neighbor probes and immediately issues broadcast ARP requests, accelerating rediscovery of the active file server.
- **tcp_syn_retries=3** – Reduces TCP connection retry duration from 127 seconds to 15 seconds.

After the network settings are in place, you should monitor your environment to validate the changes. You can test a failover event by modifying throughput capacity of your file system. For more information, see Testing failover on a file system.

Monitoring your environment after applying changes

- **Monitor system logs for NFS errors** to view NFS-related kernel log messages.

```
$ sudo journalctl -f | grep -i nfs
```

  Verify that there are fewer occurrences of messages such as `Lock reclaim failed`.
- **Monitor application logs** to confirm fewer I/O timeouts, connection errors, and retry-related failures during failover events.
- **Validate network impact** to ensure that the increased ARP traffic does not adversely affect network performance in your environment.

Alternative approaches for NFSv4 environments

In NFSv4 environments where modifying client-side configuration is not feasible, consider the following alternatives:

- **Extend NFSv4 lease timeouts.** Work with your storage administrator to increase NFSv4 lease timeouts. Extending these timeouts gives clients additional time to reclaim locks during failover

events. For more information, see Specify the NFSv4 locking grace period in the NetApp ONTAP documentation.

Document History for Amazon FSx for NetApp ONTAP

- **API version:** 2018-03-01
- **Latest documentation update:** May 1, 2026

The following table describes important changes to the *Amazon FSx NetApp ONTAP User Guide*. For notifications about documentation updates, you can subscribe to the RSS feed.

Change	Description	Date
Additional AWS Region support added for Nitro-based encryption	Second-generation FSx for ONTAP file systems now support Nitro-based encryption of data in transit in all AWS Regions where second-generation file systems are available. First-generation file systems now support Nitro-based encryption of data in transit in Asia Pacific (Malaysia), Asia Pacific (New Zealand), Asia Pacific (Taipei), Asia Pacific (Thailand), and Mexico (Central). For more information, see Encrypting data in transit with AWS Nitro System.	July 20, 2026
Additional AWS Region support added	Second-generation (Multi-AZ 2 and Single-AZ 2) FSx for ONTAP file systems are now available in Europe (London), Asia Pacific (Hyderabad), South America (São Paulo), and AWS GovCloud (US-West)	June 3, 2026

	. For more information, see Availability by AWS Region.	
Additional AWS Region support added	FSx for ONTAP file systems are now available in Asia Pacific (New Zealand). For more information, see Availability by AWS Region.	May 1, 2026
Support added for Amazon S3 access points for Amazon FSx for NetApp ONTAP	Amazon S3 access points for Amazon FSx for NetApp ONTAP provide a new way to access data stored in FSx for ONTAP file systems using the Amazon S3 API. With Amazon S3 access points, you can simplify data access for Amazon S3-enabled applications without requiring changes to your existing file system configuration. For more information, see Using Amazon S3 access points for Amazon FSx for NetApp ONTAP.	December 2, 2025
Support added for AWS Secrets Manager integration	Amazon FSx now integrate s with AWS Secrets Manager for enhanced management of Active Directory credentia ls. For more information, see Storing Active Directory credentials using AWS Secrets Manager.	November 5, 2025

AmazonFSxConsoleFullAccess – Update to an existing policy	Amazon FSx added a new permission, `secretsmanager:ListSecrets` , that allows principals to list secrets in AWS Secrets Manager for selecting domain join service account credentials. For more information, see AWS managed policy: AmazonFSxFullAccess .	November 5, 2025
NetApp BlueXP renamed to NetApp Console	NetApp BlueXP is now known as NetApp Console. For more information, see Using NetApp Console.	October 16, 2025
Support added for Internet Protocol version 6 (IPv6)	FSx for ONTAP file systems now support two network type options: IPv4-only and dual-stack (for both IPv4 and IPv6). You must specify one of those options when creating your file system. You can change the network type of an existing FSx for ONTAP file system at any time. For more information, see Managing network type.	September 30, 2025

Additional AWS Region support added	Second-generation (Multi-AZ 2 and Single-AZ 2) FSx for ONTAP file systems are now available in Asia Pacific (Seoul), Canada (Central), Europe (Spain), and Europe (Zurich). For more informati on, see Availability by AWS Region.	September 30, 2025
Additional AWS Region support added	FSx for ONTAP file systems are now available in Asia Pacific (Taipei) Region. For more information, see Availability by AWS Region.	August 18, 2025
Support added for decreasing SSD storage capacity	FSx for ONTAP now allows you to decrease your file system's solid-state drive (SSD) storage capacity on second-generation file systems, enabling you to optimize storage costs for workloads with varying high-performance storage needs. For more information, see When to decrease SSD storage capacity.	August 14, 2025

Amazon FSx updated the AmazonFSxServiceRolePolicy AWS managed policy	Amazon FSx added the `ec2:AssignIpv6Addresses` and `ec2:UnassignIpv6Addresses` permissions to the AmazonFSxServiceRolePolicy. For more information, see Amazon FSx updates to AWS managed policies.	July 22, 2025
Amazon FSx updated the AmazonFSxFullAccess AWS managed policy	The AmazonFSxFullAccess managed policy was updated to add the `fsx:CreateAndAttachS3AccessPoint` , `fsx:DescribeS3AccessPointAttachments` , and `fsx:DetachAndDeleteS3AccessPoint` permissions.	June 25, 2025
Amazon FSx updated the AmazonFSxConsoleFullAccess AWS managed policy	The AmazonFSxConsoleFullAccess managed policy was updated to add the `fsx:CreateAndAttachS3AccessPoint` , `fsx:DescribeS3AccessPointAttachments` , and `fsx:DetachAndDeleteS3AccessPoint` permissions.	June 25, 2025

FSx for ONTAP supports Amazon Elastic VMware Service	FSx for ONTAP can now be used as an external datastore for Amazon EVS. For more information, see Using Amazon Elastic VMware Service with FSx for ONTAP.	June 9, 2025
Additional AWS Region support added	Second-generation (Multi-AZ 2 and Single-AZ 2) FSx for ONTAP file systems are now available in Asia Pacific (Tokyo) and Asia Pacific (Mumbai). For more informati on, see Availability by AWS Region.	June 2, 2025
Support added for FlexCache write-back mode	FSx for ONTAP volumes now support FlexCache write-back mode. For more information, see Replicating your data with FlexCache.	May 28, 2025
Additional AWS Region support added	FSx for ONTAP file systems are now available in Asia Pacific (Thailand) and Mexico (Central). For more informati on, see Availability by AWS Region.	May 8, 2025

Autonomous Ransomware Protection (ARP) is now supported	ARP, a NetApp AI-driven feature that monitors and protects against ransomware and malware attacks, is now supported by FSx for ONTAP. For more information, see Protecting your data with Autonomous Ransomware Protection	April 7, 2025
New topic in the FSx for ONTAP User Guide describes how to set up an SMB server in a workgroup	Setting up an SMB servers in a workgroup describes how to set up an SMB server in workgroup on an SVM as an alternative to joining an SVM to a Microsoft Active Directory.	March 4, 2025
Amazon FSx updated the AmazonFSxConsoleReadOnlyAccess AWS managed policy	Amazon FSx updated the AmazonFSxConsoleReadOnlyAccess policy to add the `ec2:DescribeNetworkInterfaces` permission. For more information, see the AmazonFSxConsoleReadOnlyAccess policy.	February 25, 2025

Additional Harvest dashboards are now supported	Additional Harvest dashboards are now supported by FSx for ONTAP, including dashboards that are not enabled by default. A list of dashboards that FSx for ONTAP does not support has also been added. For more information, see Monitoring FSx for ONTAP file systems using Harvest and Grafana.	February 18, 2025
New FSx for ONTAP Billing and usage reporting topic added to FSx for ONTAP User Guide	The AWS billing and usage reporting for FSx for ONTAP topic explains how to access the billing the usage reports for FSx for ONTAP file systems in the AWS Billing and Cost Management console. It also provides all usage types in both reports that are specific to FSx for ONTAP.	February 13, 2025
Support added for dual-stack VPC interface endpoints for Amazon FSx	You can now create dual-stack VPC interface endpoints for Amazon FSx with both IPv4 and IPv6 IP addresses and DNS names. For more information, see FSx for ONTAP and interface VPC endpoints.	February 7, 2025

Support added for dual-stack API endpoints	The Amazon FSx service API for creating and managing file systems have new dual-stack endpoints. For more informati on, see API endpoints in the Amazon FSx API Reference.	February 7, 2025
Amazon FSx updated the AmazonFSxConsoleFullAccess AWS managed policy	Amazon FSx updated the AmazonFSxConsoleFu llAccess policy to add the `ec2:DescribeNetwor kInterfaces` permission. For more information, see the AmazonFSxConsoleFullAccess policy.	February 7, 2025
New topic published, Replicati ng data with FlexCache	Published a new topic describing how to replicate the data in an on-premises ONTAP file system to an FSx for ONTAP file system using FlexCache was published . For more information, see Replicating data with FlexCache.	December 19, 2024
Support added for second-ge neration file systems	You can now create second-generation Single-AZ and Multi-AZ file systems. A single high-availability (HA) pair now delivers up to 6 GBps of throughput capacity and 200,000 SSD IOPS. For more information, see High-avai lability (HA) pairs.	July 9, 2024

Support added for reading data from a volume while it is being restored from a backup	You can now mount a volume with read-only access to the file data while it is being restored from a backup on second-generation file systems. For more informati on, see Restoring backups to a new volume.	July 9, 2024
Support added for adjusting throughput capacity on second-generation file systems	You can now adjust the throughput capacity of your second-generation file systems after creation. For more information, see Managing throughput capacity.	July 9, 2024
Support added for adding HA pairs to second-generation Single-AZ file systems	You can now add HA pairs to second-generation Single-AZ file systems after creation. You can have 12 HA pairs total on a second-generation Single-AZ file system. For more information, see Adding high-availability (HA) pairs.	July 9, 2024
Support added for Non-Volat ile Memory Express over TCP (NVMe/TCP) protocol	You can now use the NVMe/ TCP protocol for data transport on Amazon FSx for NetApp ONTAP file systems. For more information, see Using block storage protocols	July 9, 2024

Support added for the `fsxadmin-readonly` role for file system administrative users	The `fsxadmin-readonly` role is now available for ONTAP file system administrative users, and can be used for file system monitoring applications such as NetApp Harvest. For more information, see File system administrator roles and users.	April 30, 2024
Support added for SSH public key authentication for Windows domain administrative users	You can now use SSH public key authentication with Active Directory domain file system and SVM users. For more information, see Configuring Active Directory authentication for ONTAP users.	April 30, 2024
Support added for 12 HA pairs in scale-out file systems	Amazon FSx for NetApp ONTAP added support for 12 HA pairs in scale-out file systems. File systems with 12 HA pairs can deliver up to 72 GBps of throughput capacity and 2,400,000 SSD IOPS across 12 high-availability (HA) pairs. For more information, see High-availability (HA) pairs and Amazon FSx for NetApp ONTAP performance.	March 4, 2024
Support added for cloud write mode	Amazon FSx for NetApp ONTAP added support for cloud write mode for volumes. For more information, see Enabling cloud write mode on a volume.	February 6, 2024

Support added for backing up FlexGroup volumes with AWS Backup	You can now use AWS Backup to back up and restore FlexGroup volumes on your FSx for ONTAP file systems. For more information, see Using AWS Backup with Amazon FSx.	January 11, 2024
Amazon FSx updated the AmazonFSxFullAccess, AmazonFSxConsoleFullAccess, AmazonFSxReadOnlyAccess, AmazonFSxConsoleReadOnlyAccess, and AmazonFSxServiceRolePolicy AWS managed policies	Amazon FSx updated the AmazonFSxFullAccess, AmazonFSxConsoleFullAccess, AmazonFSxReadOnlyAccess, AmazonFSxConsoleReadOnlyAccess, and AmazonFSxServiceRolePolicy policies to add the `ec2:GetSecurityGroupsForVpc` permission. For more information, see Amazon FSx updates to AWS managed policies.	January 9, 2024
Amazon FSx updated the AmazonFSxFullAccess and the AmazonFSxConsoleFullAccess AWS managed policies	Amazon FSx updated the AmazonFSxFullAccess and AmazonFSxConsoleFullAccess policies to add the `ManageCrossAccountDataReplication` action. For more information, see Amazon FSx updates to AWS managed policies.	December 20, 2023

Support added for scale-out metrics	FSx for ONTAP now provides Amazon CloudWatch metrics for file systems with multiple HA pairs. For more informati on, see Scale-out file system metrics.	November 26, 2023
Support added for scale-out file systems	Amazon FSx for NetApp ONTAP added support for scale-out file systems that can deliver up to 36 GBps of throughput capacity and 1,200,000 SSD IOPS across six high-availability (HA) pairs. For more information, see High-availability (HA) pairs and Amazon FSx for NetApp ONTAP performance.	November 26, 2023
Support added for FlexGroup volumes	Amazon FSx for NetApp ONTAP added support for FlexGroup volumes. For more information, see Volume styles.	November 26, 2023
Shared VPC support added for Multi-AZ file systems	Participant accounts can now create Multi-AZ file systems in a VPC that has been shared with them. Owner accounts can manage this feature in the Amazon FSx console, CLI, and API. For more informati on, see Creating FSx for ONTAP file systems in shared subnets	November 26, 2023

Amazon FSx updated the AmazonFSxFullAccess and the AmazonFSxConsoleFullAccess AWS managed policies	Amazon FSx updated the AmazonFSxFullAccess and AmazonFSxConsoleFullAccess policies to add the `fsx:CopySnapshotAndUpdateVolume` permission. For more information, see Amazon FSx updates to AWS managed policies.	November 26, 2023
Amazon FSx updated the AmazonFSxFullAccess and the AmazonFSxConsoleFullAccess AWS managed policies	Amazon FSx updated the AmazonFSxFullAccess and AmazonFSxConsoleFullAccess policies to add the `fsx:DescribeSharedVPCConfiguration` and `fsx:UpdateSharedVPCConfiguration` permissions. For more information, see Amazon FSx updates to AWS managed policies.	November 14, 2023
Support added for creating additional ONTAP roles and users	Amazon FSx for NetApp ONTAP now supports creating additional ONTAP roles and users to define user capabilities and privileges when using the ONTAP CLI and REST API. For more information, see Roles and users in Amazon FSx for NetApp ONTAP.	September 6, 2023

Support added for additional CloudWatch metrics and an enhanced monitoring dashboard	FSx for ONTAP now provides additional performance metrics and an enhanced monitoring dashboard for improved visibility into file system activity. For more information, see Monitoring with CloudWatch.	August 17, 2023
Amazon FSx updated the AmazonFSxServiceRolePolicy AWS managed policy	Amazon FSx updated the `cloudwatch:PutMetricData` permission in the AmazonFSxServiceRolePolicy. For more information, see Amazon FSx updates to AWS managed policies.	July 24, 2023
Support added for using NetApp System Manager directly	You can manage your FSx for ONTAP file systems using System Manager directly from NetApp BlueXP. For more information, see Using NetApp System Manager with BlueXP.	July 13, 2023
Support added for monitoring EMS events	You can monitor FSx for ONTAP file system events using NetAPP ONTAP's native Events Management System (EMS). You can view EMS events using the NetApp ONTAP CLI. For more information, see Monitoring FSx for ONTAP EMS events.	July 13, 2023

Support added for SnapLock	FSx for ONTAP now supports SnapLock volumes. SnapLock allows you to protect your files by transitioning them to a write once, read many (WORM) state, which prevents modification or deletion for a specified retention period. FSx for ONTAP supports the Compliance and Enterprise retention modes with SnapLock. For more information, see Working with SnapLock.	July 13, 2023
Support added for IPsec encryption of data in transit	FSx for ONTAP now supports using IPsec encryption to encrypt data in transit between file systems and connected clients. For more information, see Configuring IPsec using PSK authentication and Configuring IPsec using certificate authentication.	July 13, 2023
Maximum volume size has increased	FSx for ONTAP updated the maximum size of a volume from 100 TB to 300 TB. For more information, see Turn on volume autosizing.	July 13, 2023

Amazon FSx updated the AmazonFSxFullAccess AWS managed policy	Amazon FSx updated the AmazonFSxFullAccess policy to remove the `fsx:*` permission and add specific `fsx` actions. For more information, see AmazonFSx FullAccess policy.	July 13, 2023
Amazon FSx updated the AmazonFSxConsoleFullAccess AWS managed policy	Amazon FSx updated the AmazonFSxConsoleFullAccess policy to remove the `fsx:*` permission and add specific `fsx` actions. For more information, see AmazonFSx ConsoleFullAccess policy.	July 13, 2023
Support added for joining existing storage virtual machines to an Active Directory	You can join existing storage virtual machines to an Active Directory using the AWS Management Console, AWS CLI and API. For more information, see Joining an SVM to an Active Directory.	June 13, 2023
Support for NVMe read cache added for Single-AZ file systems	NVMe read cache is now supported for Single-AZ file systems created after November 28, 2022 with at least 2 GBps of throughput capacity in US East (Ohio) Region, US East (N. Virginia) Region, US West (Oregon) Region, and Europe (Ireland). For more information, see Impact of deployment type on performance.	November 28, 2022

Support added for using in-VPC IP address ranges to create Multi-AZ file systems	You can now create Multi-AZ FSx for ONTAP file systems by specifying endpoints that are within the IP address range of your VPC. For more information, see Creating FSx for ONTAP file systems.	November 28, 2022
Support added for updating VPC route tables on Multi-AZ file systems	You can now associate (add) a new VPC route table to an existing Multi-AZ FSx for ONTAP file system or disassociate (remove) an existing VPC route table from an existing Multi-AZ FSx for ONTAP file system. For more information, see Updating a file system.	November 28, 2022
Support added for encryption of data in transit with AWS Nitro System	Data in transit is encrypted automatically when accessed from supported Amazon EC2 instances in US East (Ohio) Region, US East (N. Virginia) Region, US West (Oregon) Region, and Europe (Ireland) . For more information, see Encrypting data in transit with AWS Nitro System.	November 28, 2022

Support added for creating DP volumes	You can now create DP (data-protection) volumes by using the Amazon FSx console, AWS CLI, or Amazon FSx API. You can use DP volumes as the destination of a NetApp SnapMirror or SnapVault relationship, when you want to migrate or protect a single volume's data. For more information, see Volume types.	November 28, 2022
Support added for copying volume tags to backups	You can now enable `CopyTagsToBackups` in the AWS CLI or Amazon FSx API to automatically copy tags from your volumes to backups. For more informati on, see Copying tags to backups.	November 28, 2022
Support added for choosing a snapshot policy	You can now choose from three built-in snapshot policies when creating or updating a volume using the Amazon FSx console, AWS CLI, or Amazon FSx API. You can also select a custom snapshot policy that you made in the ONTAP CLI or REST API. For more informati on, see Snapshot policies.	November 28, 2022

Support added for additional file system throughput capacity option	FSx for ONTAP now supports 4,096 MBps of throughput capacity for file systems created after November 28, 2022 in US East (Ohio) Region, US East (N. Virginia) Region, US West (Oregon) Region, and Europe (Ireland). For more information, see Impact of throughput capacity on performance.	November 28, 2022
Support added for additional SSD IOPS	FSx for ONTAP now supports 160,000 SSD IOPS for file systems created after November 28, 2022 in US East (Ohio) Region, US East (N. Virginia) Region, US West (Oregon) Region, and Europe (Ireland). For more information, see Impact of throughput capacity on performance.	November 28, 2022
Support added for using FSx for ONTAP as an external datastore for VMware Cloud on AWS	You can use FSx for ONTAP as an external datastore for VMware Cloud on AWS Software-Defined Data Centers (SDDCs). This added support provides flexibility to scale storage up or down independently from compute resources for VMware Cloud on AWS workloads. For more information, see Using VMware Cloud with FSx for ONTAP.	August 30, 2022

Automatically increase a file system's storage capacity	Use an AWS-developed customizable CloudFormation template to automatically increase your file system's storage capacity when the amount of used SSD storage capacity exceeds a threshold that you specify. For more information, see Increasing SSD storage capacity dynamically.	June 3, 2022
Amazon FSx is now integrated with AWS Backup	You can now use AWS Backup to back up and restore your FSx file systems in addition to using the native Amazon FSx backups. For more information, see Using AWS Backup with Amazon FSx.	May 18, 2022
Support added for single Availability Zone ONTAP file system deployments	You can create Single-AZ FSx for ONTAP file systems, which are designed to provide high availability and durability within a single Availability Zone (AZ). For more information, see Choosing file system deployment.	April 13, 2022
Support added for AWS PrivateLink interface VPC endpoints	You can now use interface VPC endpoints to access the Amazon FSx API from your VPC without sending traffic over the internet. For more information, see Amazon FSx and interface VPC endpoints.	April 5, 2022

Support added for modifying throughput capacity for existing ONTAP file systems	You can now modify the throughput capacity that is available to your existing ONTAP file systems. For more information, see Managing throughput capacity.	March 30, 2022
Support added for SSD storage capacity and provisioned IOPS scaling	You can now increase the SSD storage capacity and provisioned IOPS for existing FSx for ONTAP file systems as your storage and IOPS requirements evolve. For more information, see Managing storage capacity and provisioned IOPS.	January 25, 2022
Support added for Amazon CloudWatch metrics	You can monitor your file system using Amazon CloudWatch, which collects and processes raw data from FSx for ONTAP into readable, near real-time metrics. For more information, see Monitoring with Amazon CloudWatch.	January 19, 2022
Support added for additional file system throughput options	FSx for ONTAP now supports 128 MBps and 256 MBps options for file system throughput. For more information, see Impact of throughput capacity on performance.	November 30, 2021

Amazon FSx for NetApp ONTAP is now generally available	FSx for ONTAP is a fully managed service that provides highly reliable, scalable, performant, and feature-rich file storage built on NetApp's ONTAP file system. It provides the familiar features, performan ce, capabilities, and APIs of NetApp file systems with the agility, scalability, and simplicity of a fully managed AWS service.	September 2, 2021